



Altair Panopticon™

PANOPTICON REAL TIME 2023.2 - INSTALLATION AND REFERENCE GUIDE

TABLE OF CONTENTS

[1] INTRODUCTION	1
Overview	1
System Requirements	1
System Hardware Requirements	3
[2] SETTING UP PANOPTICON REAL TIME	5
Panopticon Real Time Deployment Model	5
Server Platforms	
Environment Promotion Options	6
Begin You Begin	6
OpenJDK 11+ Dependencies	7
Configuring catalina.bat	8
Configuring startup.bat	
Installing Panopticon Real Time	9
Setting Up Panopticon Real Time on Linux	9
Setting Up Panopticon Real Time on Windows	13
The Welcome Page	
Importing the Bundle of Example Workbooks	
Configuration of the Client Properties	21
Map Tile Provider Customization	29
Additional Information About the URL Format	31
Notes on using Google Maps or Bing Maps	31
Implications of Moving a Workbook to Another Server	31
Consequences of File Editing Mistakes	31
Licensing	32
Using Altair Units License in Altair's License Server	33
Using Managed Altair Units License Via Altair One	34
Managing File Handles	37
Identifying the Problem	37
Enabling Event Poll to Avoid False Warnings	38
Configuration Properties	38
Proxy	39
Apache HTTP Server	39
Load Balancer	40
Apache HTTP Server	40
Multiple Instances	41
Backup	42
Data Access and Caching	42
Content Repository	44
Server Cluster Configuration	
Synchronizing Tokens	47
Exporting Legacy Files	



Upgrading Panopticon Real Time	48
Content Migration	49
[3] AUTHENTICATION	51
Introduction	51
Configuring Which Users are Allowed to Log On to Panopticon	52
Token	53
Tomcat Realm	54
Tomcat User Base	54
LDAP	57
Active Directory	60
Windows Authentication	62
SAML	62
Using SAML Through OpenAM	63
OAuth 2.0	63
Example	65
Using OAuth 2.0 Through OpenAM	66
OAuth 2.0 Integration with Azure Active Directory	66
Filter	68
Creating a Custom Filter	68
Header	70
[4] TOMCAT SECURITY CONFIGURATION	74
[4] TOMICAT SECURITY CONFIGURATION	/ 1
Replacing Parameter Values with HTTP Headers and Cookies	71
Configuring HTTP Header Security Filter	74
Disabling Specific HTTP Methods	75
Preventing Cacheable HTTP Response	76
Additional Cache-Control Directives	77
Legacy HTTP Header Pragma	77
Creating a Custom filter for Cache-control with Tomcat	77
[5] ADDITIONAL OR OPTIONAL STEPS	79
File Upload Size Limits Settings in Tomcat and Panopticon	79
Tomcat Memory Configuration for Linux	
Tomcat Memory Configuration for Windows	80
Set Client Automatic Reconnection to the Server when Disconnected	
Automatic Logout of Users on Timeout to Save Unused Licenses	83
Setting the Transportation Protocol	
Panopticon Real Time Configurations for Email Send Outs and Alerts	
Font Installation Requirement for PDFs and Image export with CJK Characters	
Setting Server Properties Through the Environment Variables	
5 - 1 - 1 - 1 - 1 - 1 - 1 - 1 - 1 - 1 -	
ICLADVANCED CERVED DERI CVMENTO	0=
[6] ADVANCED SERVER DEPLOYMENTS	87

Usage in SSL Enabled Environments	87
Enabling SSL for Panopticon Real Time	87
Defining a TrustStore	89
[7] AUTHORIZATION	91
Secure Access	91
Creating Folders	91
Adding Groups and Users with Allowed Authorization	93
Adding Groups and Users with Denied Access	96
Creating Subfolders	
Updating Folder or Subfolder Properties	100
Downloading a Workbook	
Exporting Workbook or Folder Bundle	
Importing Workbooks Bundle	
Data Level Secure Access	
[8] SYSTEM ADMINISTRATION	106
System Settings	107
View License Information	107
View Panopticon Real Time Information	109
View Plugin Subscriptions	110
Working with Caches	112
View Logs	114
Scheduling Tasks	117
Creating Task to Clear and Import Data Table to Data Store	120
Creating Task to Import Data Table to Data Store	
Creating Task to Send CSV Data via Email	
Creating Task to Send an MS Excel File via Email	
Creating Task to Send an HTML Formatted Data via Email	
Creating Task to Send Image File via Email	
Creating Task to Send PDF File via Email	
Creating Task to Extract Data	
Uploading a Scheduler Task	
Downloading a Scheduler Task	
Other Scheduler Tasks Operations	
Managing Panopticon Real Time Users	
Viewing Logged In Users	
Sorting Logged In Users	
Logging Out Users	
Logging Out Osers	
Logging Out Individual Users	
Refreshing the Logged In Users List	
Managing API Tokens	
Adding Custom Fonts	
Adding Odston Fonts	142

[9] CONNECTIVITY AND INTEGRATION	146
Third Party Software Dependency Installation	146
Database	149
JDBC Driver Installation	149
JNDI Connection Details	149
Common Databases and their JNDI Configurations	150
R and Python Transform Support	
R Integration	
Python Integration	
Load Custom Data Plugins	
[10] VIEWING AND MANAGING WORKBOOKS	156
Accessing Workbooks	
Searching for Workbooks	
Folders and Workbooks Display View	
Sorting Workbooks	
Creating Workbooks	
Renaming Workbooks or Folders	
Uploading Workbooks	
Viewing Workbook History and Republishing	
Moving Workbooks	
Copying Workbooks	
Parameter Value Passing Into the Web Client Special Symbols to Pass Parameter Values Into the HTML5 Client	
[11] DATA LIBRARY	177
Setting up Data Store	179
Caching	180
[12] WEBHOOKS	181
Folders and Webhooks Display View	182
Searching for Webhooks	183
Creating Webhooks	184
Webhooks Toolbar and Context Menu	
Sorting Webhooks	188
Renaming a Webhook	
Moving Webhooks	
Copying Webhooks	
Deleting Webhooks	
Triggering Webhooks	
[13] ALERTING	194

Setting Up Alerts	194
Sorting Alerts	202
Searching for Alerts	202
Enabling Alerts on the Alerts Page	203
Displaying Active Alerts	205
Activating or Deactivating All Alerts	206
Viewing Triggered Alerts	206
Importing Alerts	208
Exporting Alerts	208
Modifying Alert Settings	209
Deleting Alerts	209
Enabling Alerts	212
Viewing and Managing Alerts for Non-Administrator users	214
Sample Email Alerts	215
Sample Web Client Alerts	216
[14] GLOBAL PARAMETERS	220
Adding Parameters	220
Modifying Parameters	
Deleting Parameters	225
Refresh Parameters	226
Searching Parameters	226
[15] MANAGING WORKBOOK THEMES	228
[15] MANAGING WORKBOOK THEMES Folders and Themes Display View	
	230
Folders and Themes Display View	230
Folders and Themes Display ViewSearching for Themes	230 231 232
Folders and Themes Display ViewSearching for ThemesCreating a New Theme	
Folders and Themes Display ViewSearching for ThemesCreating a New ThemeDefining the Default Style Settings of a Theme	
Folders and Themes Display View	
Folders and Themes Display View Searching for Themes Creating a New Theme Defining the Default Style Settings of a Theme Defining the Custom Style Settings of a Theme Defining the Color Palettes Settings of a Theme Defining the General Color Settings of a Theme Defining the Editor Style Settings of a Theme Defining the Shape Palettes of a Theme Defining the Dashboard Templates of a Theme Themes Toolbar and Context Menu Sorting Themes Renaming a Theme Moving Themes Copying Themes Downloading Themes Deleting Themes	
Folders and Themes Display View	

Creating a New Single Color Palette	266
Creating a New Sign Color Palette	267
Creating a New Text Color Palette	269
Creating a Sequential or Diverging Numeric Color Palette	272
Modifying Color Palettes	275
Creating a Duplicate of a Color Palette	276
Deleting Color Palettes	277
Shape Palettes	
Creating a New Shape Palette	278
Uploading a Shape Palette	
Downloading a Shape Palette	
Modifying Shape Palettes	
Creating a Duplicate of a Shape Palette	
Rearranging Shape Palettes	
Deleting Shape Palettes	
[16] PCLI: COMMAND UTILITIES FOR PANOPTICON REAL TIME	285
Clearcache	286
Plugins	286
Publish	286
Publishing a Workbook to Panopticon Real Time	286
Publishing a Workbook to a Folder	
Publishing a Workbook Folder to Panopticon Real Time	
Version	
Help	
Upgrade	
Schemify	
Exportdatasource	
Convertpermissions	
MigrateDatabaseToJDBC	
Mockdata	
Encrypt	
Decrypt	292
[17] REST INTERFACE	293
API	293
Export Data	294
CSV	
PDF	
Excel Workbook	
Email Data	
PDF	
Image	300
[49] LOCCING/MONITORING	202

Server Logging	303
Configuring Server Logs	303
Configuring Apache Tomcat Logs	304
Using java.util.logging (Default)	305
Audit Logging	308
Data Log Access in Dashboards	309
Server Monitoring	309
Web Portal Integration	310
Setting the Server Metrics Publisher	310
Setting the Logging Level	312
[19] TROUBLESHOOTING	313
Resolving Installation Issues	313
Server Log	313
No Appropriate Protocol Error When Publishing Splunk Data on Panopticon Real Time	314
Pie Charts and Shapes Not Displaying Correctly in Chrome	314
Session Tokens Not Working in Chrome	315
Managed Altair Units License SSL Error	316
[20] KNOWN ISSUES	317
Out of Memory Exception	317
[21] PANOPTICON RESOURCES	318
[APPENDIX]	320
Properties: Panopticon	320

[1] INTRODUCTION

Altair Panopticon™ Real Time supports the following data connectors:

OVERVIEW

General Connectivity: MS Excel, Text, XML, JSON, Restful Web services, JDBC Databases
 Big Data: Cassandra, Elasticsearch 6.x, Elasticsearch 7.x, KsqlDB, Livy Spark, MongoDB, Splunk
 Event Processing: Kx kdb+Tick, OneMarketData OneTick CEP, Tibco Streambase, Tibco LiveView, Panopticon Streams
 Messaging Streaming: Apache/Confluent Kafka, JMS (e.g., ActiveMQ), Solace, RabbitMQ, WebSocket, JMX, Google Cloud Pub/Sub, MQTT
 Tick Data: OneMarketData OneTick, OneTick Cloud, Kx kdb+, InfluxDB

□ Custom code data connections, transforms, and ML model scoring: Python, R, and REST service calls

In addition, Panopticon Real Time includes a Panopticon bundle file of example workbooks (**Examples.exz**). To use the example workbooks, the bundle file must be imported into the server after the server installation.

NOTE

- Beginning with version 17.1, MS Access, Valo, Apache Qpid, Valo Streaming, Ultra Messaging Streams, and OData connectors are deprecated.
- Beginning with version 16.2, DataDirect based connectors, along with Vertica, are deprecated. The Database connector or JDBC Database connector should be used.
- Existing workbooks will continue to operate, but connectivity will need to be migrated for subsequent releases.

SYSTEM REQUIREMENTS

Panopticon Real Time is supported on these operating systems:

- ☐ Linux which includes the following distributions and versions:
 - RHEL/CentOS 7 or higher
 - Debian 8 or higher
 - Ubuntu 14 or higher
 - Fedora 21 or higher
- ☐ Windows 10 (64-bit) For Development Environments Only
- Windows Server 2012 (64-bit)

■ Windows Server 2016 (64-bit)

Panopticon Real Time also requires:

Oracle Java SE 8, Oracle Java SE 11, Open JDK 8, and Open JDK 11 are supported after installing the dependency files that are distributed with Panopticon Real Time.

NOTE

- Unzip the contents of the dependency package file provided by Panopticon into the TOMCAT_HOME/lib folder to be able to run Altair Panopticon software on JRE 11 and Open JDK 11.
- Please refer to Java documentation about setting up the JAVA_HOME environment variable in your system.

■ Apache Tomcat 9.0.x

NOTE

When running on Windows instead of Linux, it is recommended to use the zip distribution of Apache Tomcat for Windows rather than the Windows Service Installer. This is because the zip distribution will let you run Apache Tomcat without any dependency on the Windows service manager, and management of the Apache Tomcat server will conform more with how it is done on Linux.

NOTE

Starting with Tomcat 9, Debian Linux implements a security policy which puts a harder default restriction on which folders a Tomcat 9 web application can write to.

The change is described in full detail here:

https://salsa.debian.org/java-team/tomcat9/-/commit/3ca5cbdc2f970470341926354f210dff032fc5f3

Quoting from the release notes:

 Tomcat is sandboxed by systemd and only has write access to the following directories:

Directory	Actual Directory
/var/lib/tomcat9/conf/Catalina	/etc/tomcat9/Catalina
/var/lib/tomcat9/logs	/var/log/tomcat9
/var/lib/tomcat9/webapps	
/var/lib/tomcat9/work	/var/cache/tomcat9

• If write access to other directories is required, override the service settings. This is done by creating an override.conf file in

/etc/systemd/system/tomcat9.service.d/ containing:

[Service]

ReadWritePaths=/path/to/the/directory/

Ensure to restart the service afterward with:

- o systemctl daemon-reload
- systemctl restart tomcat9


rar	Panopticon Real Time is supported for deployment on the following cloud providers:	
	Amazon Web Services (AWS)	
	Microsoft Azure	
	Google Cloud Platform	
	□ Oracle Cloud	
	Containerized deployment with Docker Linux containers is also supported.	
Sup	Supported browsers include the latest version of:	
	□ Safari	
	• Panopticon Real Time requires administrative privileges durin Administrative privileges are not required after installation is of	
	 Panopticon Real Time does not support Tomcat 7.x, Tomcat 8.5.x. 	8.0.x, or Tomcat
	System Hardware Requirements Development / Test	
	□ 1 x Dual Core CPU (Hyper Threaded to 4 Cores/Threads)	
	□ 8GB RAM	
	□ 4GB Disk (Available)	
	In Memory Caching limited to available Server RAM	
Sm	Small Scale Deployment	
	□ 1 x Quad Core CPU Or Equivalent (Hyper Threaded to 8 Cores/Threads)	
	□ 16GB RAM	
	□ 4GB Disk (Available)	
	□ In Memory Caching limited to available Server RAM	
Me	Medium Scale Deployment	
	□ 4 x Quad Core CPU Or Equivalent (Hyper Threaded to 32 Cores/Threads)	
	□ 32GB RAM	

	4GB Disk (Available)
	In Memory Caching limited to available Server RAM
Lar	ge Scale Deployment
	8 x Quad Core CPU Or Equivalent (Hyper Threaded to 64 Cores/Threads)
	64GB RAM
	4GB Disk (Available)

□ In Memory Caching limited to available Server RAM

[2] SETTING UP PANOPTICON REAL TIME

PANOPTICON REAL TIME DEPLOYMENT MODEL



Full scale Panopticon Real Time deployment

Panopticon Real Time is deployed and hosted on an internal network. The server can be accessed internally and/or externally from the internet. Upon allowing access to the server from the internet it is recommended to have a proxy and firewall in front of the server.

Panopticon Real Time exposes web services from both a SOAP interface and a REST interface. These interfaces are used by the Web client but can also be used to execute functionality directly on the server such as by batch jobs.

Workbook access is secured through the underlying application Panopticon Real Time security model, such as authentication and configuration of directories in Tomcat.

Furthermore, Panopticon Real Time is capable of the following features:

- □ Single Sign-On (SSO) Support through SAML
- JDBC / JNDI Data Sources
- JMX Monitoring

Server Platforms

Panopticon Real Time consist of multiple components such as the following:

Components	Description
Panopticon Real Time	Formerly named Panopticon Visualization Server, responsible for managing all the published workbooks and all the resources that go with them. It is also responsible for authorization, data connections, transformations, scheduled tasks, report generation, alerting, etc.
Panopticon Streams	Processing of data streams for real-time visualization in dashboards.
Web Client	Graphical interface for administration of the server and for creation and design of dashboard applications.

See Installation for more information.

ENVIRONMENT PROMOTION OPTIONS

You may need to set up multiple environments for Altair Panopticon. For example, you may wish to set up your system to support one of the following migration paths:

- □ Staging → Production
- □ Development → User Acceptance Testing → Production

The primary complication when promoting workbooks between environments is access to data repositories since you may wish to use separate data repositories for each environment. If you require different data repositories in each environment, use JNDI or global parameters. These abstract the location of the data repository from the workbook.

BEGIN YOU BEGIN

Before you begin the installation of Panopticon Real Time, you may need to:

- □ Verify that your system meets the system requirements.
- □ Set up OpenJDK 11+ dependencies for running Panopticon on OpenJDK 11 and up.
- Configure <u>catalina.bat</u> and <u>startup.bat</u>.

IMPORTANT

Before installing Panopticon on Tomcat, you must start Tomcat at least once. Make sure Tomcat is stopped before starting the installation of Panopticon.

OpenJDK 11+ Dependencies

The AltairPanopticonVisualizationServerWAR_<version number>.zip file includes OpenJDK11Dependencies.zip which contains necessary dependencies for running Altair Panopticon software on Open JDK 11 and up.

The overview, installation, and list of the contents of <code>OpenJDK11Dependencies.zip</code> are provided and discussed in the <code>OpenJDK11Dependencies</code> <code>README.txt</code> file.

Background

In Java 9, a number of Java EE modules were marked for deprecation, and subsequently removed completely from Java 11.

With missing Java EE dependencies, the typical exceptions would include NoClassDefFoundError exceptions being thrown for javax/xml/bind classes.

```
Exception in thread "main" java.lang.NoClassDefFoundError:
javax/xml/bind/JAXBException
    at monitor.Main.main(Main.java:27)
Caused by: java.lang.ClassNotFoundException: javax.xml.bind.JAXBException
    at
java.base/jdk.internal.loader.BuiltinClassLoader.loadClass(BuiltinClassLoader.java:582)
    at
java.base/jdk.internal.loader.ClassLoaders$AppClassLoader.loadClass(ClassLoaders.java:185)
    at java.base/java.lang.ClassLoader.loadClass(ClassLoader.java:496)
    ... 1 more
```

In order to support deployment on either Java 1.8 or Open JDK 11+, we have packaged the necessary Java EE dependencies separately for simple installation in Tomcat.

Installation

Do the following to make the dependencies available to the Java Virtual Machine (JVM) and the Altair Panopticon server:

- 1. Stop Tomcat.
- 2. Unzip the contents of OpenJDK11Dependencies.zip into the TOMCAT HOME/lib folder.
- 3. Start Tomcat.

Zip File Content

- ☐ Jakarta XML Binding API (jakarta.xml.bind-api), version 2.3.2
 - jakarta.xml.bind-api-2.3.2.jar
 - jakarta.activation-api-1.2.1.jar
- ☐ JAXB Runtime (jaxb-runtime), version 2.3.2
 - jakarta.xml.bind-api-2.3.2.jar
 - txw2-2.3.2.jar

- istack-commons-runtime-3.0.8.jar
- jakarta.activation-api-1.2.1.jar
- stax-ex-1.8.1.jar
- jakarta.activation-api-1.2.1.jar
- jakarta.xml.bind-api-2.3.2.jar
- FastInfoset-1.2.16.jar
- jakarta.activation-api-1.2.1.jar
- ☐ Jakarta SOAP Implementation (saaj-impl), version 1.5.1
 - saaj-impl-1.5.1.jar
 - jakarta.xml.bind-api-2.3.2.jar
 - jakarta.activation-api-1.2.1.jar
 - jakarta.xml.soap-api-1.4.1.jar
 - mimepull-1.9.11.jar
 - stax-ex-1.8.1.jar
- Java API for XML Web Services (jaxws-api), version 2.3.1
 - jaxws-api-2.3.1.jar
 - jaxb-api-2.3.1.jar
 - javax.activation-api-1.2.0.jar
 - javax.xml.soap-api-1.4.0.jar
 - javax.annotation-api-1.3.2.jar

Configuring catalina.bat

You could have several versions of Java installed on your system, but you need to let Apache Tomcat know which one to use. You also need to create an instruction to the JVM to use UTF-8-character encoding to ensure non-ASCII characters are correctly displayed.

NOTE

Before editing any files, the Tomcat server must be stopped.

Steps:

- 1. Navigate to the tomcat home\bin folder and find the catalina.bat file.
- 2. Right-click on the catalina.bat file and select Edit with Notepad in the context menu.
- 3. In the opened file, scroll down and enter new lines like this after the initial rem chunk ends.

```
setlocal
set JAVA_HOME=OpenJDK_home\[OpenJDK folder]
set JRE_HOME= OpenJDK_home\[OpenJDK folder]
set JAVA OPTS=%JAVA OPTS% -Dfile.encoding=UTF-8
```

For example:

```
setlocal
set JAVA_HOME=C:\Program Files\RedHat\java-1.8.0-openjdk-1.8.0.362-1
set JRE_HOME=C:\Program Files\RedHat\java-1.8.0-openjdk-1.8.0.362-1
set JAVA OPTS=%JAVA OPTS% -Dfile.encoding=UTF-8
```

4. Save and close.

Configuring startup.bat

You could have several versions of Apache Tomcat on your system. To ensure that the desired Tomcat version will be run, you must explicitly specify which one to use.

NOTE

Before editing any files, the Tomcat server must be stopped.

Steps:

- 1. Navigate to the tomcat home\bin folder and find the startup.bat file.
- 5. Right-click on the startup.bat file and select Edit with Notepad in the context menu.
- 6. In the opened file, scroll down and enter new lines like this after the initial rem chunk ends.

```
setlocal
set CATALINA_HOME=tomcat_home
```

For example:

```
setlocal
set CATALINA HOME=C:\apache-tomcat-9.0.73
```

7. Save and close.

INSTALLING PANOPTICON REAL TIME

This section provides instructions on how to install Panopticon Real Time on Linux or Windows.

NOTE

If you need to upgrade your previously installed Panopticon Real Time, proceed to the <u>Upgrade</u> section.

Setting Up Panopticon Real Time on Linux

Follow the steps and guidelines below to install Panopticon Real Time on Linux.

Steps:

1. Extract the contents of AltairPanopticonVisualizationServerWAR_<version number>.zip file to a new location.

This zip file will contain the following folder and files:

- pcli-java folder
- tomcat-users_example.xml
- start_Python_connectivity.sh
- start_Python_connectivity.bat
- pyro.py
- panopticon.xml
- panopticon.war
- PanopticonJNDIRealm.jar
- OpenJDK11Dependencies_README.txt
- OpenJDK11Dependencies.zip
- Examples.exz
- CustomMessageParserExample.zip
- Elastic_5X_Dependencies.zip
- Elastic_6X_Dependencies.zip
- Elastic_7X_Dependencies.zip
- Panopticon Web Authoring Quick Start Guide
- Panopticon Web Authoring Guide
- Panopticon Real Time Installation and Reference Guide
- User_License.rtf

NOTE

To support Python Transform, the following files are included in the installation zip file:

- start_Python_connectivity.sh
- start_Python_connectivity.bat
- pyro.py

Refer to Python Integration for more information.

- 2. Create the AppData folder (i.e., /usr/share/vizserverdata) and ensure that the user account Local Service running Tomcat has read/write and execute permissions to this folder.
- 3. In the Tomcat config folder (/tomcat_home/conf/Catalina/localhost) create the panopticon.xml file with the following information:

NOTE

• Instead of setting the path of the environment variable
PanopticonAppData on the panopticon.xml file, you can do so on
the System Environment Variables. For example:

Variable	New Value
PanopticonAppData	/usr/share/panopticondata

- If the directory path is set in both an environment variable and in the panopticon.xml file, the value set in the XML file will take precedence.
- Starting with 21.2, the DatawatchVDDAppData is replaced with PanopticonAppData as the specifier for the Panopticon application data directory. You can still use DatawatchVDDAppData as a fallback, but going forward, PanopticonAppData should be used.
- 4. Copy the panopticon.war file into the Tomcat webapps folder (/tomcat home/webapps).
- 5. For a basic installation using the Tomcat inbuilt XML file user directory, copy the provided tomcatusers_example.xml and overwrite the existing tomcat-users.xml file which is available in the Tomcat config folder (/tomcat home/conf).

The provided tomcat-users example.xml contains the following roles and users:

```
<role rolename="user"/>
<role rolename="designer"/>
<role rolename="admin"/>
<user username="viewer" password="viewer" roles="user" />
<user username="designer" password="designer" roles="user,designer" />
<user username="admin" password="admin" roles="user,admin"/>
<user username="su" password="su" roles="user,admin"/>
<user username="su" password="su" roles="user,designer,admin"/>
```

NOTE

In Panopticon 2020.0 and onwards, the Administrators.txt and AdministratorGroup.txt files are no longer used to authorize administrator users. The function provided by these files has been replaced by a set of properties in Panopticon.properties:

```
access.default.roles=VIEWER
access.administrator.groups=admin
access.designer.groups=designer
access.viewer.groups=
```

The access.default.roles property defines the default roles assigned to any user accessing the server, defaulting to VIEWER. The administration

(access.administrator.groups property) and content creation (access.designer.groups property) on the server are mapped by default to groups named "admin" and "designer".

For more complex authentication and user directory options, see section [3] Authentication.

IMPORTANT •

- Before proceeding to step 7, ensure the Tomcat temp folder (e.g., (/tomcat home/temp) is available.
- You can opt to choose a different temp folder with the CATALINA_TMPDIR environment variable. For example:

Variable	Value
CATALINA_TMPDIR	/tomcat_home/dev/temp

6. Start Tomcat to deploy the panopticon.war file.

The server initializes the AppData directory with an empty content repository and empty subdirectories for other types of data. The Panopticon.properties file is created with the default server properties.

- 7. Specify the license type that will be used. Use any of the following license types:
 - Volume License file (PanopticonLicense.xml) that must be copied to the designated AppData folder.
 - Altair Units license. Refer to <u>Using Altair Units License in Altair's License Server</u> for more information.
 - Managed Altair Units license. Refer to <u>Using Managed Altair Units License Via Altair One</u> for more information.
- 8. Increase the <u>Java heap size of Tomcat</u>.
- 9. You can also opt to install Java data connector's dependencies.
- 10. You should now be able to log on to Panopticon Real Time using the following:

```
[Host Name]:[Port]/[Name of your application]
```

For example:

http://localhost:8080/panopticon

The more advanced configuration options are also discussed in this document.

Setting Up Panopticon Real Time on Windows

NOTE

You should use the Windows zip distribution of Apache Tomcat for Windows rather than the Windows Service Installer.

Follow the steps and guidelines below to install Panopticon Real Time on Windows.

Steps:

1. Extract the contents of AltairPanopticonVisualizationServerWAR_<version number>.zip file to a new location.

This zip file will contain the following folder and files:

- pcli-java folder
- tomcat-users_example.xml
- start_Python_connectivity.sh
- start_Python_connectivity.bat
- pyro.py
- panopticon.xml
- panopticon.war
- PanopticonJNDIRealm.jar
- OpenJDK11Dependencies_README.txt
- OpenJDK11Dependencies.zip
- Examples.exz
- CustomMessageParserExample.zip
- Elastic_5X_Dependencies.zip
- Elastic_6X_Dependencies.zip
- Elastic_7X_Dependencies.zip
- Panopticon Web Authoring Quick Start Guide
- Panopticon Web Authoring Guide
- Panopticon Real Time Installation and Reference Guide
- User_License.rtf

NOTE

To support Python Transform, the following files are included in the installation zip file:

- start_Python_connectivity.sh
- start_Python_connectivity.bat
- pyro.py

Refer to Python Integration for more information.

2. Create the AppData folder (i.e., vizserverdata) and ensure that the user account Local Service running Tomcat has read/write and execute permissions to this folder.

Example: C:\vizserverdata

3. Copy the extracted panopticon.xml file into the Tomcat config folder. This file contains the following information:

NOTE

Instead of setting the path of the environment variable PanopticonAppData on the panopticon.xml file, you can do so on the System Environment Variables. For example:

Variable	New Value
PanopticonAppData	C:\panopticondata

- If the directory path is set in both an environment variable and in the panopticon.xml file, the value set in the XML file will take precedence.
- Starting with 21.2, the DatawatchVDDAppData is replaced with PanopticonAppData as the specifier for the Panopticon application data directory. You can still use DatawatchVDDAppData as a fallback, but going forward, PanopticonAppData should be used.
- 4. Copy the panopticon.war file into the Tomcat webapps folder (\Apache Software Foundation\Tomcat 9.0\webapps).
- 5. For a basic install using the Tomcat inbuilt XML file user directory, copy the provided tomcatusers_example.xml and overwrite the existing tomcat-users.xml file which is available in the Tomcat config folder (\Apache Software Foundation\Tomcat 9.0\conf).

The provided tomcat-users example.xml contains the following roles and users:

```
<role rolename="user"/>
<role rolename="designer"/>
<role rolename="admin"/>
<user username="viewer" password="viewer" roles="user" />
<user username="designer" password="designer" roles="user,designer" />
<user username="admin" password="admin" roles="user,admin"/>
<user username="su" password="su" roles="user,admin"/>
<user username="su" password="su" roles="user,designer,admin"/>
```

NOTE

In Panopticon 2020.0 and onwards, the Administrators.txt and AdministratorGroup.txt files are no longer used to authorize administrator users. The function provided by these files has been replaced by a set of properties in Panopticon.properties:

access.administrator.groups=admin access.default.roles=VIEWER access.designer.groups=designer access.viewer.groups=user

The access.default.roles property defines the default roles assigned to any user accessing the server, defaulting to VIEWER. The administration (access.administrator.groups property) and content creation (access.designer.groups property) on the server are mapped by default to groups named "admin" and "designer".

For more complex authentication and user directory options, see section [3] Authentication.

6. You can also opt to install Java data connector's dependencies, and JDBC driver JAR files as required.


IMPORTANT •

- Before proceeding to step 8, ensure the Tomcat temp folder (e.g., (\Apache Software Foundation\Tomcat 9.0\temp) is available.
- You can opt to choose a different temp folder with the CATALINA_TMPDIR environment variable. For example:

Variable	Value
CATALINA_TMPDIR	C:\tomcat\dev\temp

7. Start Tomcat to deploy the .war file.

The panopticon folder is extracted in the Tomcat webapps folder:




The server initializes the AppData directory with an empty content repository and empty subdirectories for other types of data. The Panopticon.properties file is created with the default server properties.

- 8. Specify the license type that will be used. Use any of the following license types:
 - Volume License file (PanopticonLicense.xml) that must be copied to the designated AppData folder.
 - Altair Units license. Refer to <u>Using Altair Units License in Altair's License Server</u> for more information.
 - Managed Altair Units license. Refer to <u>Using Managed Altair Units License Via Altair One</u> for more information.
- 9. Increase the <u>Java heap size of Tomcat</u>.
- 10. You should now be able to log on to Panopticon Real Time using the following:

[Host Name]:[Port]/[Name of your application]

For example:

http://localhost:8080/panopticon




The more advanced configuration options are also discussed in this document.

NOTE


Panopticon Real Time supports different user roles. To have full access to all the services, the user is required to have ADMINISTRATOR and DESIGNER roles.

For example, logging on using the ADMINISTRATOR role added in step 6 (i.e., admin/admin), will display:



All of the available user specific folders in the authentication method used are displayed.


However, logging on with a DESIGNER role (i.e., designer/designer) will only display:



The allowed features available for the DESIGNER role is extensively discussed in the Web Authoring Guide.

The Welcome Page

The *Welcome* page is the first screen that displays when you log on to Panopticon Real Time. This page can also be accessed by clicking the **Altair Panopticon** logo on the header.




From this page you can:

- ☐ Click See All Workbooks to go to the Workbooks page
- □ Open recently viewed workbooks
- Explore workbooks available in your organization
- Open the Analyst User Guide
- □ View online documentation and help

⇒ See All Workbooks

If there are no recently viewed workbooks, header.

is displayed parallel to the $\ensuremath{\textit{Getting Started}}$




Importing the Bundle of Example Workbooks

The AltairPanopticonVisualizationServerWAR_<version number>.zip file includes the bundle file of the example workbooks and their associated data files (Examples.exz).

Follow the instructions below to import this bundle to Panopticon Real Time.

Steps:

 On the Workbooks and Folders Summary page, right-click on a folder and select Import Bundle on the context menu.




The Import Bundle dialog displays.



- 2. To import the bundle, you can either:
 - Drag it from your desktop and drop on the dialog, or
 - Click Choose Bundle to Import and select one on the Open dialog that displays.

The name of the selected bundle is displayed on the dialog box.



3. Select the Keep Folder Structure checkbox.

This means the exported folder structure is maintained when uploading the bundle. If the folders do not exist on the server, they will be created.


4. To replace an existing workbook, select the Replace existing workbook checkbox.



The example workbooks that you can view and explore are imported.

CONFIGURATION OF THE CLIENT PROPERTIES

Starting with version 2020.1, Panopticon Real Time generates JSON configuration files in the JavaScriptConfiguration directory of the AppData folder (i.e., C:\vizserverdata).



```
NOTE

In the JSON files, a dot in the name (e.g., name1.name2) is used to denote a nested object structure:

{
    "name1": {
        "name2": ...
     }
}
```

The default content of the admin.json file has the following objects/names:

```
{
  "baseUrl" : ".",
  "hideAuthenticationButton" : false,
}
```

In the admin.json file, you can control the configuration of the following objects/names:

Object/Name	automaticReconnectOnServerDisconnect
Description	If set to true , the real time connection (WebSocket or long polling) to the Panopticon server will be automatically reconnected if it is disconnected.
Default Value	false
Required	No
Object/Name	baseUrl
Description	Location of Panopticon Real Time.
Default Value	"."
Required	Yes
Object/Name	dataLoading.transport
Description	Controls which transport should be used when viewing log from the server. Valid values are "websocket" and "long-polling". If configured to "websocket", but the WebSocket connection fails, then the web client will automatically fall back to "long-polling".
Default Value	"websocket"
Required	No
Object/Name	hideAuthenticationButton
Description	Boolean. Hides the login and logout buttons.
Default Value	false
Required	No
Object/Name	localization.defaultLocale

Description	Locale used if the browser locale is not supported, or if the useBrowserLocale is set to false.
Default Value	"en-US"
Required	No
Object/Name	localization.fallbackLocale
Description	Locale used if a resource string is missing from the locale in use. Should be specified if localization.defaultLocale is specified.
Default Value	value of localization.defaultLocale
Required	No
Object/Name	localization.useBrowserLocale
Description	Boolean. If set to true , the browser navigator.language, navigator.userLanguage on IE11, controls the localization of the UI. Not all languages are supported.
Default Value	true
Required	No
Object/Name	localizationOverride
Description	Nested object with resource strings per language. Used to customize resource strings.
Default Value	
Required	No
Object/Name	logLevel
Description	Controls which types of logs Panopticon will write to the browser dev console. Valid values are: "trace", "debug", "info", "warn", "error" and "silent".
Default Value	"info"
Required	No
Object/Name	workbookUrl
Description	Location of the workbook application. NOTE: The workbookUrl property should reflect the actual location of the workbook application, but it doesn't rename or change the location of said application.
Default Value	"workbook"
Required	Yes
Object/Name	dataLoading.connectTimeout
Description	Controls the timeout used, in milliseconds, when opening the data loading connection to the server.
Default Value	10000
Required	No
Object/Name	showFileUploadUI
Description	Controls the visibility of UI that is used to upload a file to the server.

Default Value	true
Required	No
Object/Name	showLinkToFileUI
Description	Controls the visibility of UI that is used to specify a data file on the server local file system as a data source. Per default, this flag is automatically inserted into the client configuration at runtime.
Default Value	true
Required	No

The default content of the workbook.json file has the following objects/names:

```
"baseUrl" : "..",
  "forceClientSelectionHandling" : true,
  "startUrl" : "../",
  "subscriptionCompression" : true,
  "dataLoading" : {
     "transport" : "websocket"
  },
  "webGlEnabled" : true,
  "pdfMultiplePagesEnabled" : true
}
```

In the workbook.json file, you can control the configuration of the following objects/names:

Object/Name	baseUrl
Description	Location of Panopticon Real Time.
Default Value	"."
Required	Yes
Object/Name	localization.useBrowserLocale
Description	Boolean. If set to true, the browser navigator.language, navigator.userLanguage on IE11, controls the localization of the UI. Not all languages are supported.
Default Value	true
Required	No
Object/Name	localization.defaultLocale
Description	Locale used if the browser locale is not supported, or if useBrowserLocale is set to false.
Default Value	"en-US"
Required	No
Object/Name	localization.fallbackLocale

Description	Locale used if a resource string is missing from the locale in use. Should be specified if localization.defaultLocale is specified.
Default Value	value of localization.defaultLocale
Required	No
Object/Name	localizationOverride
Description	Nested object with resource strings per language. Used to customize resource strings.
Default Value	
Required	No
Object/Name	logLevel
Description	Controls which types of logs Panopticon will write to the browser dev console. Valid values are: "trace", "debug", "info", "warn", "error" and "silent".
Default Value	"info"
Required	No
Object/Name	disableExternalHelpText
Description	Disables the browser dev console splash screen.
Default Value	false
Required	No
Object/Name	theme
Description	Name of the default theme for all workbooks. Per default, the first theme available is picked as the default theme.
Default Value	
Required	No
Object/Name	allowOrigin
Description	A comma separated list of allow origins, used by the Panopticon POST message API.
Default Value	
Required	No
Object/Name	automaticReconnectOnServerDisconnect
Description	If set to true , the real time connection (WebSocket or long polling) to the Panopticon server will be automatically reconnected if it is disconnected.
Default Value	false
Required	No
Object/Name	alwaysHideNonInteractiveParametersInDialog
Description	Hides parameters that are not interactive when displaying the interactive parameter dialog.
Default Value	false
Required	No

Object/Name	enableDevicePixelRatioCanvasScaling
Description	Enable or disable handling of device pixel ratio for 2D visualizations.
Default Value	true
Required	No
Object/Name	staleStateTimeout
Description	Time (in milliseconds) that controls how fast the "stale data" overlay should be rendered on top of visualizations. Only applies to those interactions that don't show "data loading" animation. A value equal to or less than zero will disable the stale data overlay.
Default Value	150
Required	No
Object/Name	preloadDetailsPopup
Description	Data to be shown in the <i>Details</i> pop-up is preloaded as part of the visualization data request. If set to false , then the details data will be loaded on demand.
Default Value	true
Required	No
Object/Name	forceClientSelectionHandling
Description	If set to true , then selection handling in the visualizations will be performed by the client. If set to false , then the server will calculate the selection.
Default Value	false
Required	No
Object/Name	subscriptionCompression
Description	Controls if data query strings longer than 2048 chars should be compressed by the web client before sending them to the server.
Default Value	false
Required	No
Object/Name	pdfMultiplePagesEnabled
Description	Controls the visibility of the "Create multiple pages" checkbox in the ad hoc PDF report dialog.
	dialog.
Default Value	true
Default Value Required	
	true
Required	true No
Required Object/Name	true No startUrl
Required Object/Name Description	true No startUrl
Required Object/Name Description Default Value	true No startUrl URL used by the Home and Back buttons, and by the dialog for unexpected errors.

Description	If set to true, the Back button will execute window.history.back() when pressed. This setting takes precedence over having a configured startUrl.
Default Value	false
Required	No
Object/Name	hideThemeSelection
Description	Controls the visibility of the theme drop down.
Default Value	false
Required	No
Object/Name	dataLoading.transport
Description	Controls which transport should be used when loading data from the server and receiving notifications. Valid values are "websocket" and "long-polling". If configured to "websocket", but the WebSocket connection fails, then the web client will automatically fall back on "long-polling".
Default Value	"websocket"
Required	No
Object/Name	dataLoading.connectTimeout
Description	Controls the timeout used, in milliseconds, when opening the data loading connection to the server.
Default Value	10000
Required	No
Object/Name	preventVisualizationMouseWheelDefaultEvents
Description	Prevents the browser default action when using the mouse wheel over a visualization. Useful in an embed scenario if the hosting web page is scrolled when the user tries to zoom in a visualization using the mouse wheel.
Default Value	false
Required	No
Object/Name	webGlEnabled
Description	Enables the use of WebGL in visualizations that supports it.
Default Value	true
Required	No
Object/Name	maxClipboardLength
Description	Maximum length of text that will be attempted to be put into the system clipboard (copy). If too much text is attempted, then the browser might become unresponsive.
Default Value	500000
Required	No
Object/Name	selectionInDetailsPopup

Description	Enables/disables selection data in the visualization details popup. Primary use case for this setting is to disable it on a server level.
Default Value	true
Required	No
Object/Name	showAlertsButton
Description	Controls the visibility of the Alerts workbook button.
Default Value	true
Required	No
Object/Name	showBackButton
Description	Controls the visibility of the Back workbook button.
Default Value	true
Required	No
Object/Name	showBookmarksButton
Description	Controls the visibility of the Bookmarks workbook button.
Default Value	true
Required	No
Object/Name	showCopyDashboardImageButton
Description	Controls the visibility of the Copy Image workbook button.
Default Value	true
Required	No
Object/Name	showHomeButton
Description	Controls the visibility of the Home workbook button.
Default Value	true
Required	No
Object/Name	showPdfExportButton
Description	Controls the visibility of the Create PDF Report workbook button.
Default Value	true
Required	No
Object/Name	showRefreshDataButton
Description	Controls the visibility of the Refresh workbook button.
Default Value	true
Required	No
Object/Name	showPauseRealtimeButton
Description	Controls the visibility of the Pause Real-Time workbook button.

Default Value	true
Required	No
Object/Name	pluginDenyList
Description	Array of plugin IDs, used to block the specified dashboard parts and visualizations.
Default Value	empty array
Required	No
Object/Name	pluginAllowList
Description	Array of plugin IDs, used to allow only the specified dashboard parts and visualizations. The default value, an empty array, allows all plugins.
Default Value	empty array
Required	No
Object/Name	showFileUploadUI
Description	Controls the visibility of UI that is used to upload a file to the server.
Default Value	true
Required	No
Object/Name	showLinkToFileUI
Description	Controls the visibility of UI that is used to specify a data file on the server local file system as a data source. Per default, this flag is automatically inserted into the client configuration at runtime.
Default Value	true
Required	No

- With the new application configuration files, the workbook/config.js inside the extracted war file is no longer valid.
- If there are no config files available on the server, default ones will be created and saved. After that, you can alter them in any way you would like and keep the configuration even if the server is restarted.

MAP TILE PROVIDER CUSTOMIZATION

When creating a Map Plot visualization, the map images are retrieved from a map tile provider on web URL. Panopticon provides a default map tile provider preconfigured within the software. In addition, custom map tile providers can be added to the server configuration by editing the following file:

/vizserverdata/default-settings/tileproviders.json

The default map tile provider that is shipped with the product can be overridden by specifying a different one and use the providerId **Default**.

In case the tileproviders.json file is deleted or moved and hence not found on server startup, then a new default tileproviders.json file will be created in the default-settings folder.

NOTE

You will not be able to keep the original default map tile provider with a different name. The original default will become unavailable for as long as the new map tile provider service with the name **Default** exists in the configuration.

Each provider is a name-value pair object with the following parameters:

Parameter	Description
providerId	The name label that will be visible in the selection dropdown in the settings of the Map Plot visualization. This value must be unique across all map tile providers saved in the file.
minZoom	The default value is 0 . This is the minimum zoom level that should be available in the Panopticon Map Plot when using this map tile provider. However, the minimum zoom level available from the tile service may be a higher value (e.g., 5). Refer to the documentation of the map tile service provider.
maxZoom	The default value is 18 . This is the maximum zoom level that should be available in the Panopticon Map Plot when using this map tile provider. However, the maximum zoom level available from the tile service may be a higher value (e.g., 20) or a lower value (e.g., 15). Refer to the documentation of the map tile service provider.
tileSize	The default value is 256 . This is the size of each tile image coming from the map tile service. It describes a raster size, 256 by 256 . Some services also use 512 by 512 . NOTE: It is required to have the correct tileSize setting for the service you are using. Otherwise, the tiles received will not be positioned correctly in the Map Plot and you will not see a correct map. Refer to the documentation of the map tile service provider. If the tile size is not specified by the map tile provider, assume 256 .
urlFormat	This is the URL of the map tile provider, and it will be different for each map tile provider. For map tile providers that use the OSM tile coordinates encoding, the URL will end with $\{z\}/\{x\}/\{y\}$.png or $\{z\}/\{x\}/\{y\}$.jpg, which for Panopticon must be changed into $\{0\}/\{1\}/\{2\}$.png or $\{0\}/\{1\}/\{2\}$.jpg. Some tile providers will require an API key, which is appended as a URL request parameter, on this form: ?apikey=abc123. For map tile providers that use the QUAD_KEY tile coordinates encoding, the URL will contain a {quadkey} reference which for Panopticon must be changed into {0}.
tileCoordEncoding	The default value is OSM . This value means that the map tile service uses the same URL principle as OpenStreetMap, where each tile URL request contains $/\texttt{zoomlevel/x-coord/y-coord/}, \text{ which corresponds to } / \{0\}/\{1\}/\{2\}/\text{ in the urlFormat.}$ Value QUAD_KEY means that the map tile service uses the QuadKey principle, for example, like what Bing maps do. QuadKey is short for Quadtree Key, which is a one-dimensional string of digits, created from the two-dimensional X-Y coordinates. A Quadkey uniquely identifies a map tile at a specific zoomlevel.

Additional Information About the URL Format

In the URL of map tile providers using the OSM tile coordinates encoding, **{0}** represents the zoom level value **z**, **{1}** represents the x-coordinate value **x**, and **{2}** represents the y-coordinate value **y**. For any actual map tile URL, these will have been replaced by coordinate numbers (integers) by Panopticon before the request for a tile is sent to the map tile provider server.

The Map Plot in Panopticon takes care of inserting those numeric values as required, instead of the **{0}** and **{1}** and **{2}** values. When you read the service documentation from map tile service providers, you will notice that instead of referencing **{0}**, **{1}**, **{2}**, they will be referencing **{z}**, **{x}**, **{y}**.

NOTE

- You must replace z,x,y with 0,1,2 when using the URL in Panopticon.
 Also, some services will present a URL which includes a dollar sign, like /\${z}/\${x}/\${y}. These dollar signs must be removed.
- Raster Tiles are supported.
- Vector tiles are not supported.

Notes on using Google Maps or Bing Maps

In Panopticon, the configuration of a custom map tile provider is static. The configuration is saved in a JSON file which is read by Panopticon on start up, and any change of the information will require a server restart. For this reason, it is not practical to use either one of Google Maps map tile servers or Bing Maps map tile servers, because:

The Google Maps API requires that an API key is first used to retrieve a session token, with a POST request.
Map tiles are subsequently loaded with GET requests from a URL where both the API key and the session
token must be appended as URL request parameters. This means that the map tile URL will no longer work
when the session token expires.

The Bing Maps API has frequently changing map tile URLs, and to get currently valid map tile URLs, you must
start by making a request to a special API endpoint, which returns currently valid map tile URLs as well as
various metadata about the map tiles. This means that the map tile URL will work for some time, but eventually
will become invalid.

Implications of Moving a Workbook to Another Server

If a workbook using a custom map tile provider is exported from one Panopticon server and imported into another Panopticon server which does not have a custom map tile provider by that providerId name, then the Map Plot will display as blank--only marks/dots will show, but no map images. This can be corrected by changing the configuration of the Map Plot to use the **Default** map tile provider, or any other custom map tile provider added to that server.

Consequences of File Editing Mistakes

If the file tileproviders.json is not properly configured, for example if a quote character or comma or curly bracket is missing anywhere, then only the Panopticon default map tile provider will be available.

The server log will display any of the following warnings:

Unexpected	end-of-input:	expected	close	marker	for (Object

Illegal unquoted character

Cannot construct instance of
$\verb `com.panopticon.server.core.web.repository.file.SettingFileRepository\$TileProviders and the providers and the provider$

☐ Unexpected character ('{' (code 123)): was expecting double-quote to start field name

These are some examples of map tile providers:

https://wiki.openstreetmap.org/wiki/Raster_tile_providers

https://stadiamaps.com/

https://www.maptiler.com/

https://www.thunderforest.com/

https://www.maptilesapi.com/

Here's a useful website for comparing different tile maps side by side:

https://mc.bbbike.org/mc/

LICENSING

Licensing within Panopticon Real Time supports the following license types:

a volume-based XML file (named **PanopticonLicense.xml**) that is used to store all license information for a specific customer, must be copied to the designated AppData folder (i.e., **C:\vizserverdata**)

NOTE

Starting with 21.2, the newly issued volume-based license file is named PanopticonLicense.xml. For customers with the DatawatchLicense.xml file, it can still be used but it is strongly recommended to rename it to PanopticonLicense.xml.

- ☐ Altair Units license which is available in Altair's License server you are connected to (local or over the network)
- Managed Altair Units license via Altair One

The license file type you will use is delivered separately from the installation packages.

NOTE

In the Panopticon documentation, HyperWorks Units (HWU) and Hosted HyperWorks Units (HHWU) are now named Altair Units.

In the Panopticon product, these license types are still named HyperWorks Units and Hosted HyperWorks Units.

For more information on Altair Units, visit https://www.altair.com/altair-units/.

Using Altair Units License in Altair's License Server

If your license source is Altair's License server, it is required to configure the following properties in the $\underline{\texttt{Panopticon.properties}}$ file located in the $\underline{\texttt{AppData}}$ folder or C: $\underline{\texttt{vizserverdata}}$:

Property	Service authentication level
Attribute	authentication.required
Description	The property that will make the authentication required. It will force the user to login to use any of the services provided by the server. Must be set to true .
Default Value	true
Property	Licensing
Attribute	license.hwu.uri
Description	The path where the License Server is running e.g., 6200@191.255.255.0 where the syntax is PORTNUMBER@HOST. If multiple servers are specified, use the ';' semicolon separator sign for Windows and the ':' colon separator sign for Linux. NOTES: If value is not set in the Panopticon.properties, the environment variable ALTAIR_LICENSE_PATH serves as the backup path and will be used.
Example	For Windows: license.hwu.uri=6200@192.168.5.51;6200@192.168.5.52 For Linux: license.hwu.uri=6200@192.168.5.51:6200@192.168.5.52
Default Value	
Property	Licensing
Attribute	license.hwu.version
Description	Value must match the license version found in the Altair Units license file.
Default Value	19.0
Property	Licensing
Attribute	license.mode
Description	The license mode. Possible values are FILE or HWU. Must be set to HWU .
Default Value	FILE

For example:

```
authentication.required=true
license.hwu.uri=6200@192.168.5.51;6200@192.168.5.52
license.hwu.version=19.0
license.mode=HWU
```

 Panopticon Real Time supports different user roles which check out different numbers of Altair Units.

Role	Altair Units License Draw
Viewer	2
Designer	2 10 when designing a workbook
Administrator	2

- Alerts and scheduled tasks are leveled towards each other. Regardless
 of the number of alerts or scheduled tasks a user creates, only two
 Altair Units licenses will be checked out.
- These units are separate from the units that are checked out for a user
 of the server. For example, if a user is logged on to the server (two
 units) and starts an alert (two units), a total of four units are checked
 out. If the user then starts two more alerts and a scheduled task, the
 total number of checked out units will still be four. If the user logs out
 without shutting off any alerts, two units will remain checked out.
- Two products (e.g., Panopticon Real Time and Panopticon Streams) or two instances of one product, must not be configured to use Altair unit licensing if they run on the same Tomcat.

Using Managed Altair Units License Via Altair One

Using the Altair Units licensing will support simplifying the license management by removing all manual aspects of emailing license files, extending evaluation periods, among others.

In addition, Altair Units licensing will help small to medium deployment customers who do not want to host onpremise license server.

Before using Altair Units, it is required to configure the following properties in the $\frac{\texttt{Panopticon.properties}}{\texttt{properties}}$ file located in the AppData folder or C:vizserverdata:

Property	Licensing
Attribute	license.hwu.hosted
Description	Boolean stating if you wish to use Managed or Local Altair Units licensing. Set to true if you wish to use managed licensing.
Default Value	false
Property	Licensing
Attribute	license.hwu.hosted.authorization.username
Description	Username to the Altair One account.
Default Value	

Property	Licensing
Attribute	license.hwu.hosted.authorization.password
Description	Password to the Altair One account.
Default Value	
Property	Licensing
Attribute	license.hwu.hosted.authorization.token
Description	An authorization token generated through the Altair One admin portal. Used to authorize a machine to the managed Altair Units system.
Default Value	


NOTE	• To use the managed Altair Units licensing, set the following properties: license.hwu.hosted=true license.mode=HWU authentication.required=true license.hwu.version=20.0
	Add the Panopticon application to your Altair One account.

To authorize the machine against the managed Altair Units system, you have two options.

Option 1


Use an authorization code generated through Altair One:

Log on to Altair One (https://admin.altairone.com) then navigate to User Profile and select Authorized Machines.



2. Click Generate Auth Code

The page displays the auth code and a timer indicating the code's expiration.



Click Copy to Clipboard to copy the generated auth code.

- 3. Paste the generated code into the license.hwu.hosted.authorization.token property in the Panopticon.properties file.
- 4. Start the server.

Option 2

Directly use your Altair One credentials in Panopticon.properties:

- 1. Enter your Altair One credentials into the license.hwu.hosted.authorization.username and license.hwu.hosted.authorization.password properties in the Panopticon.properties file.
- 2. Start the server.

NOTE

- If a token is entered, this will be tried first. If the token was invalid or not present, and credentials are present, the credentials will be used to authorize the machine towards the managed Altair Units system.
- In Option 1, the generated auth code is only valid for 15 minutes and you should restart your server within that timeframe to properly get access to your licenses.
- In Option 2, Altair One credentials are only required at first restart of the server to generate
 the auth token and should be removed from the Panopticon.properties file going

forward to avoid exposing these credentials.

- A working Internet connection is required to use Altair Units licensing.
- If your company uses proxy, you might need to add exception in your proxy to allow access to the Managed Altair Licenses.

Please refer to this link for more information:

https://community.altair.com/kb_view.do?sys_kb_id=bb9bf3fc97205590e3b0361e6253af03

Or see Managed Altair Units License SSL Error section below.

• If you don't have an Altair One account, you can sign up for a free trial that will allow you to test the product for 14 days.

Managing File Handles

In some cases, the Tomcat process that runs the Panopticon server may run out of file descriptors, which are handles used by the operating system to access a file (file handles). Panopticon data connections and license units checkouts count towards the total number of file handles in use.

When the maximum limit of file handles (open files) is reached, you cannot open any additional files, or make any additional TCP connections, or check out additional Altair license units.

On a Linux system, maximum file handles limit (open files) and other limits such as memory usage are called Resource Limits or rlimits. The rlimit values can be viewed and changed using the ulimit command and various arguments to that command. Please refer to Linux documentation for details on using the ulimit command, for example https://linuxhint.com/linux_ulimit_command/.

The system will have an overall limit (global system maximum) as set in the kernel variable file /proc/sys/fs/file-max. In addition, there are rlimits set for each process, or for each user running a process. The rlimits for any given process will have a soft limit and a hard limit. The soft limit is what will be in effect, and the hard limit says what the maximum is if you want to raise the soft limit.

The reason for setting rlimits specific for a process that are lower than the overall system rlimits, is that you want to economize system resources between several processes to ensure that no single process consumes all available system resources, thereby causing problems for other processes. Likewise, a process specific rlimit set lower than the system maximum is also useful for protecting the system, avoiding system total resource depletion.

Identifying the Problem

When a user encounters the maximum limit of file handles in Panopticon, data connection or logging into Panopticon could fail. To confirm that Panopticon has hit the file handle limit, you should look for this message in the Panopticon log:

(Err: 60) Out of file descriptors suitable for socket operation

In conjunction with the error message above, you may also see the following messages in the Panopticon log:

com.panopticon.server.core.exception.HyperWorksUnitsLicenseException: Unable to check out a license java.lang.Throwable: Altair License Manager: License error

Other things that could indicate that Panopticon has reached the maximum limit for file handles, but can also have other reasons, are:

□ The browser console may show error messages like:

Unable to check out a lie	cense
---------------------------	-------

☐ The dashboard may show the following message when you click the **Edit** button:

Unable to edit - HWU license error

☐ The dashboard may show the following when a Viewer wants to open a workbook:

AW Snap! Unable to checkout license; Go to workbook overview

Enabling Event Poll to Avoid False Warnings

Altair Units License checkouts count towards the total number of open files. The Altair Units License SDK by default uses the **select(2)** interface in Linux to monitor the number of available file handles or sockets. The highest number that select(2) can return is **1024**. This means that as soon as 1024 or more file handles are open, the license server process will not see any available file descriptors.

However, the Altair Units License SDK can also use the **epoll(7)** interface in Linux, which is not suffering from the limitation of select(2). To make the ALSDK use epoll(7) instead of select(2), you must set an environment variable as follows:

LMX_USE_EPOLL=1

Still, epoll(7) is nonetheless bound by the rlimit settings, which means that in addition to setting the above environment variable, you may also need to raise the open files rlimit for the Tomcat process, by using the ulimit command.

CONFIGURATION PROPERTIES

Encoding

The default encoding of the JVM is the same as the system it is running on. It is recommended to configure your Java and Apache Tomcat to use the UTF-encoding. This is achieved by setting the property file.encoding to UTF-8.

There are several ways to configure the property and one method is to create a setenv file in your Apache Tomcat bin folder:

	setenv	.bat	for	Windows
--	--------	------	-----	---------

setenv.sh for Linux

The following operating systems should contain the following information in order to use the UTF-8 encoding:

For Windows:

```
set JAVA_OPTS=%JAVA_OPTS% -Dfile.encoding=UTF-8
```

For Linux:

JAVA_OPTS="\$JAVA_OPTS -Dfile.encoding=UTF-8"

Restart the Apache Tomcat to save the changes.

PROXY

A proxy is a server or software running on a server that acts as an intermediary for requests from clients seeking resources from other servers. Instead of using a proxy, you can use a load balancer.

It is recommended to use a proxy when setting up Panopticon Real Time. There are a variety of proxies available. One of the most commonly used proxies is Apache HTTP Server with the proxy module. Refer to the section below on how to setup an Apache HTTP Server with Proxy functionality.

Apache HTTP Server

This section describes the steps on how to install and configure an Apache Proxy. The guide expects that the Apache HTTP Server is being setup for the first time. Please note that the installation steps might vary depending on your environment. These steps cover how to install and configure an Apache HTTP Server with proxy support for Microsoft Windows.

- 1. Download the Apache HTTP Server from the official webpage: https://httpd.apache.org/download.cgi
- 2. Unzip and copy the files to a folder.
- 3. Configure the proxy by opening the httpd.conf file in the conf folder.
- 4. Update the SRVROOT variable. The value must be updated to the file location of the Apache HTTP server.

```
Define SRVROOT "/Path/To/Apache"
ServerRoot "${SRVROOT}"
```

5. Modules are required to be loaded to make the Apache HTTP Server into a proxy. Add the following lines in the httpd.conf file.

```
LoadModule proxy_module modules/mod_proxy.so
LoadModule proxy_http_module modules/mod_proxy_http.so
LoadModule proxy_wstunnel_module modules/mod_proxy_wstunnel.so
LoadModule rewrite module modules/mod rewrite.so
```

NOTE

In the httpd.conf file:

- Ensure that the line Include conf/extra/httpd-vhosts.conf is uncommented.
- Replace Listen 80 with Listen 10088.
- 6. Configure the logic for the proxy and how requests should be passed. The Virtual host config should look like this and be added to the httpd-vhosts.conf file in the conf/extra folder:

```
<VirtualHost :10088>
  ServerAdmin webmaster@localhost
  ProxyPreserveHost On
  ProxyPass /panopticon http://localhost:8080/panopticon
  ProxyPassReverse /panopticon http://localhost:8080/panopticon
  ProxyPass /panopticon/server/ws http://localhost:8080/panopticon/server/ws
```

```
ServerName localhost:8080
RewriteEngine on
RewriteCond %{HTTP:UPGRADE} ^websocket$ [NC]
RewriteCond %{HTTP:CONNECTION} Upgrade [NC]
RewriteRule . ws://localhost:8080%{REQUEST_URI} [P]
</VirtualHost>
```

7. The Apache HTTP Server can be started when all the configurations are in place. This is done by running the httpd script or application in the Apache bin folder.

LOAD BALANCER

A load balancer is a server used to distribute the workload across multiple computer resources. A load balancer allows you to scale the system to max and optimize the resource use and throughput, and at the same time minimize the response time. A load balancer can also be used to ensure that the system will still be available, even during downtime on a computer resource.

Very much like proxies, there are a variety of load balancers available. The only requirement Panopticon Real Time has on the load balancer is that it supports persistence or stickiness. This means that the proxy will establish a user session and ensure that the user continues to use the same computer resource.

Stickiness is mainly implemented in two means: **Cookies** or **URL encoding**. These two alternatives will be used to determine which route the user will continue to take in the load balancer. The rest of this section will cover how to implement stickiness with cookies.

Sticky load balancer that are using cookies are normally using session tokens. Due to this, it is required to configure Panopticon to use session tokens. This is done by updating the following property to **SESSION** in the Panopticon.properties file: authentication.token.persistence.

authentication.token.persistence=SESSION

IMPORTANT

After modifying the property value to SESSION, ensure to clear the AppData/Token folder before starting the server.

For details on how to configure multiple servers to run in a cluster and synchronize content between them, see <u>Server</u> Cluster Configuration.

Apache HTTP Server

The following section describes the steps on how to install and configure an Apache Load Balancer. The guide expects that the Apache HTTP Server is being setup for the first time. Please note that the installation steps might vary depending on your environment. These steps cover how to install and configure an Apache HTTP Server with proxy support for Microsoft Windows.

- Download the Apache HTTP Server from the official webpage: https://httpd.apache.org/download.cgi
- 2. Unzip and copy the files to a folder.
- 3. Configure the proxy by opening the httpd.conf file in the conf folder.

4. Update the SRVROOT variable. The value must be updated to the file location of the Apache HTTP server.

```
Define SRVROOT "/Path/To/Apache"
ServerRoot "${SRVROOT}"
```

5. Modules are required to be loaded to make the Apache HTTP Server into a load balancer. Add or uncomment the following lines in the httpd.conf file.

```
LoadModule proxy_module modules/mod_proxy.so
LoadModule proxy_http_module modules/mod_proxy_http.so
LoadModule proxy_wstunnel_module modules/mod_proxy_wstunnel.so
LoadModule rewrite_module modules/mod_rewrite.so
LoadModule headers_module modules/mod_headers.so
LoadModule lbmethod_byrequests_module
modules/mod_lbmethod_byrequests.so
LoadModule proxy_balancer_module modules/mod_proxy_balancer.so
LoadModule slotmem_shm_module modules/mod_slotmem_shm.so
```

6. Configure the logic for the load balancer and how requests should be passed.

In the following example, we have configured the load balancer to listen to port **10080** and to use two balancer members (**Route 1** and **Route 2**). The example will also set a session cookie named **ROUTEID**. The cookie contains the route that the user took and will continue to use throughout the active session.

7. The Apache HTTP Server can be started when all the configurations are in place. This is done by running the httpd script or application in the Apache bin folder.


MULTIPLE INSTANCES

Multiple instances of	of Panonticon	Real Time ca	an be deployed	l onto a single	machine

The common usage models for multiple instances are:

- Multi-tenant deployments, providing separate **Sand boxes** for each tenant
- ☐ Multi environments (Development, Test, Production)
- Regression Testing

	To deploy multiple servers, the WAR and corresponding configuration file must be updated to have a unique name.
В	ACKUP
Pan	nopticon Real Time consists of:
	Software Installation & Server Configuration
	License
	Usage Configuration
	Published Workbooks
	Data
	Caches
Pan	ATA ACCESS AND CACHING approximately approx
This	s means either:
	Load Subset of Data in Memory
	Load Summary and Parameterized Detail Views
	ROLAP (Dynamically explore datasets)
	nsequently, for direct access, Panopticon is only as fast as the underlying data platform, or the refreshing of result caches.
	en data is not changing on a timely basis, such as a daily updated data warehouse, there is the additional option etrieving data into a data store.



Consequently:

- Only required data is retrieved. Majority of the data stays in the underlying data sources.
- ☐ Typically aggregated, conflated, filtered data is retrieved.
- ☐ Behind each dashboard part (visualization) is a micro-cube.
- ☐ Each cube is designed for streaming real time updates.
- ☐ Behind each cube is a real-time data table (also powering filters).
- Behind each data table is a resultset cache.
- □ Behind the cache is the underlying data repository.
- ☐ Caches can be loaded on the fly, or pre-loaded on a periodic basis.
- All caching is optional.
- Consequently, data access is either:
 - Work Directly against underlying sources (either Exploratory Analysis (ROLAP), Or Pre-Defined Parameterised Views)
 - Import data into the Data Store

Usage is typically **Hybrid**. Based on the characteristics of the underlying data, you choose whether to import to Data Store, or query directly.

This is to cater for real world data landscapes, where different data has different data retrieval latency characteristics, and different timeliness; and where there is too much data to simply load all into memory.

CONTENT REPOSITORY

Previous versions of the server stored workbook files in the Workbooks subdirectory of the application data directory (i.e., C:\vizserverdata\Workbooks), and older versions of those workbooks in the Archive subdirectory (i.e., C:\vizserverdata\Archive). Starting with the 2020.0 release, workbooks are now stored in a version tracking repository, located in the .repository subdirectory (i.e., C:\vizserverdata\.repository).

The repository also stores other types of content that was previously stored in separate subdirectories of the application data directory, such as data files and bookmarks.

The new workbook repository tracks changes to content, folders, and permissions. It also makes it possible for multiple servers to synchronize their repositories, so you only have to make changes to a workbook on one node in a server cluster, and it will automatically propagate to the other servers [see section on cluster configuration].

The first time you start the 2020.0 server, it will initialize an empty repository in the application data directory. If you are upgrading an existing install, you have the option of migrating content from the old application data directory into the new repository [see section on content migration].

For the list of properties that control the repository behavior, refer to those starting with 'repository.' in the Properties: Panopticon section.

SERVER CLUSTER CONFIGURATION

When you have multiple servers running, you can set them up, so they synchronize content between them. The servers will use an internal protocol over http(s) to propagate changes and make sure their content is the same.

The cluster component discovers the other servers and the topology that connects them and can use various methods to do so. The cluster component also identifies one of the running servers as the **leader**, the others are **followers**.

The leader-follower relationship determines how content is synchronized. A follower will immediately push any local change to the leader, for example, when you save a workbook after editing it. On the other hand, a follower periodically polls the leader for changes. This means the leader has the "latest" version of the content, whereas a follower may lag by a few seconds. The leader is also special if there are conflicting changes, for example, if two users edit and save the same dashboard. In this case, the leader's changes always win.

The REST services, that the servers call to synchronize content, expose potentially sensitive information such as data tables and data source settings. They are protected by token validation just as other services on the server, and only accepts special "server" tokens that are never issued to users. A server can only get a token from another server if they have both been configured with the same shared secret. That said, the calls are not encrypted, so if you connect two servers over the internet, you will want to use HTTPS.

Even though the content synchronization makes it easier to run a set of servers as a cluster behind a load balancer, you still need to use sticky sessions (session affinity). The server requires that a single user stays with the same server instance for the duration of a session.

There are four different cluster modes:

None - Each server is completely stand-alone, and nothing will be synchronized. This is the default, and no further configuration is needed.
Fixed - One server is the permanent leader. The other servers will synchronize with it if it is up. If the leader goes down, the followers will log the problem, but will continue to run basically as stand-alone servers. When the leader comes back up, they will start synchronizing again.

In practice, the fixed mode has a single point of failure. Because the followers connect through the leader, even if they keep running, their content will not be synchronized, and conflicts become more likely the more their content diverge.

To configure fixed mode, set cluster.shared.secret to the same non-empty string on all, set cluster.mode to FIXED on all, and then set cluster.fixed.leader to the URL of the leader on the followers only (leave it blank on the leader).

The leader URL should be the path to the web application, for example

http://panoserver:8080/panopticon/. It needs to identify the leader server and be resolvable on the network that the followers run on. If you use a load balancer, you cannot use the externally exposed URL, as it always needs to resolve to the leader server. If the leader server is dynamically assigned an IP, you need to take extra steps to assign it with a URL that does not change.

Bully - The server with the lowest ID (lexicographically) of the running servers is chosen as leader, and if it goes down a new leader is automatically appointed.

When a new server joins a bully cluster, it needs to discover the current list of members and their IDs. To do this, it tries to contact any running server from a list of known servers, called the boot servers. If any one of them answers, it replies with the current members and leader. If none of them answers, it starts as the single member of the cluster if it is one of the boot servers, or refuses to start if not.

In a sense, the bully mode is more flexible than the fixed mode since it eliminates the single point of failure. As long as one server is still running, there will be a leader, so synchronization will happen. In another sense, it's less flexible as you need to provide more non-changing URLs, one for each server.

To configure the bully mode, set cluster.shared.secret (see above), set cluster.mode to BULLY on all, set cluster.bully.id to a unique ID string for each server (lower ID has higher leader priority), set cluster.bully.bind on each to the URL on which the other servers can reach it, and cluster.bully.boot to a comma-separated list of known server URLs.

An example bully configuration with three servers:

On server #1:

```
cluster.shared.secret=supersecretpassword
cluster.mode=BULLY
cluster.bully.id=panopticon-1
cluster.bully.bind=http://192.168.0.10/panopticon
cluster.bully.boot=\
http://192.168.0.10/panopticon,\
http://192.168.0.11/panopticon
```

On server #2:

```
cluster.shared.secret=supersecretpassword
cluster.mode=BULLY
cluster.bully.id=panopticon-2
cluster.bully.bind=http://192.168.0.11/panopticon
cluster.bully.boot=\
http://192.168.0.10/panopticon,\
http://192.168.0.11/panopticon
```

On server #3:

```
cluster.shared.secret=supersecretpassword
cluster.mode=BULLY
cluster.bully.id=panopticon-3
cluster.bully.bind=http://192.168.0.12/panopticon
cluster.bully.boot=\
http://192.168.0.10/panopticon,\
http://192.168.0.11/panopticon
```

Note that only servers #1 and #2 are boot servers, and that only id and bind differ between servers. With this configuration, servers #1 and #2 can be started in any order, but at least one of them must be up before #3 starts. On the other hand, you can add server #3 without #1 and #2 knowing about it up front, so non-boot servers can be useful in auto-scaling scenarios.

One caveat with non-boot servers is that if all the boot servers go down, a non-boot server will become the leader. If a new server joins, or a boot server rejoins, there is no way for them to see this, and you will end up with two separate clusters.

Kubernetes - The servers discover each other through the Kubernetes API Server, and the one whose pod has the lowest name (lexicographically) is chosen as leader. Each server periodically refreshes this information, so if the list of available pods changes, they adapt.

To call the Kubernetes API, the server needs to know the address of the API Server and have valid credentials. By default, the address is passed into the pod via Kubernetes downward API as environment variables KUBERNETES_SERVICE_HOST/PORT, and the credentials are mounted to /var/run/secrets/kubernetes.io/serviceaccount/, and the server will use these, so no extra configuration is needed.

The server discovers the other servers (pods) with a Kubernetes label selector. You can use any label and any selector for this, e.g., give each pod the metadata label "app" with value "panopticon" and use the selector "app=panopticon". The server will assume that all pods returned by the guery are standard Panopticon servers.

You also need to tell each server what its own pod name is, so it can tell if it's supposed to be a leader or follower and avoid calling itself. You can use the Kubernetes downward API to pass this in: use valueFrom, fieldRef and fieldPath "metadata.name" (see example below).

To configure the Kubernetes mode, set cluster.shared.secret (see above), set cluster.mode to KUBERNETES, set cluster.kubernetes.id to the pod's name, set cluster.kubernetes.label_selector to the pod selector, and cluster.kubernetes.peer_path to the web application path.

If the pod that runs the Panopticon server container also runs other containers, the first container will be used. If this is not the case, you can set cluster.kubernetes.container_name to the name of the container that runs the Panopticon server.

Example yaml snippet:

```
template:
 metadata:
    labels:
     app: panopticon
  spec:
    containers:
      . . .
      enw.
        - name: CLUSTER SHARED SECRET
          value: supersecretpassword
        - name: CLUSTER MODE
          value: KUBERNETES
        - name: CLUSTER KUBERNETES ID
          valueFrom:
            fieldRef:
              fieldPath metadata.name
        - name: CLUSTER KUBERNETES LABEL SELECTOR
          value: app=panopticon
        - name: CLUSTER KUBERNETES PEER PATH
          value: panopticon/
```

SYNCHRONIZING TOKENS

When a user has authenticated successfully with a server, a token is issued that is passed back and forth in a cookie. These tokens may be long-lived with a default expiration time of seven days and normally automatically reissued. So, when the server is regularly used, the user will rarely need to log in again. Similarly, API tokens never expire.

Normally, a token issued by one server is only valid on that server. The server keeps track of issued tokens and validates each incoming token against its stored tokens. Furthermore, tokens are revoked when an administrator logs out a user, and the token is removed from the server's list.

If there are multiple servers that are being used as a cluster with a load balancer in front, they should be configured to have synchronized tokens. Even if the load balancer uses sticky sessions as it should, a token is typically valid for a longer time than a session lasts, and the user should not have to log in again just because a new session is directed to a different server than last time.

Token synchronization uses a different mechanism from repository synchronization. The repository stores content with its change history, and there are scenarios where the user may want to synchronize one and not the other. For example, there may be one QA server and one production server then use a common login.

Tokens are synchronized through the cluster shared store. By default, this is just a subdirectory <appdata>/shared/ which is not synchronized. The store also keeps other types of non-content data that the user may want to synchronize between servers.

To enable token synchronization:

Change the property cluster.shared.store.type from its default PRIVATE_DIRECTORY to SHARED_DIRECTORY.
Set cluster.shared.store.shared_directory.path to a location that is accessible from all servers. On Kubernetes, this would typically be a volume that you mount on a path in the container.
Ensure all servers use the same cookie name in authentication.token.cookie, or a cookie issued by one server would not be visible to another.
Ensure all servers (i.e., validating server and the one that issued the token) have the same authentication.token.secret. This secret is used to sign and validate tokens.

EXPORTING LEGACY FILES

Starting with Panopticon 2020.0, the new server installation will no longer include Workbooks and Data folders in the AppData folder. To recreate these folders and export workbooks and their associated data files, GroupAccessRestrictions, and parameters that are stored inside the repository, you can either:

do a POST call to
http://[host]:[port]/[serverappname]/server/rest/server/export/legacy/files?replaceExistingDataFiles=true&replace
ExistingWorkbooks=true

Example:

http://localhost:8080/panopticon/server/rest/server/export/legacy/files?replaceExistingDataFiles=true&replaceExistingWorkbooks=true

- or perform the following steps
- 1. Set the documentation.enabled property in Panopticon.properties to true.

documentation.enabled=true

- 2. Restart the server.
- 3. Access the REST API to call the /rest/server/export/legacy/files service using this URL:

http://[host]:[port]/[serverappname]/swagger-ui.html

Example: http://localhost:8080/panopticon/swagger-ui.html

The Panopticon REST API page displays.

- 4. Select legacy in the Select a Definition drop-down list.
- 5. Expand the Server section and find the Export Legacy Files service then run it.

If successful, the Data and Workbooks folders are recreated in the AppData folder with the exported workbooks, data files, parameters, and GroupAccessRestrictions.

UPGRADING PANOPTICON REAL TIME

The server stores all its content in the AppData (e.g., C: vizserverdata) directory. Ensure that you back up this directory frequently. You can always revert the server to an earlier state by restoring the entire AppData directory from a backup.

In general, a newer server will use an AppData from an older server, with exceptions for some types of content that you may need to migrate manually. In contrast, the server will refuse to start if you point an older server to an AppData that has been used with a newer server.

NOTE

Two servers should never share the same AppData directory.

It is recommended that you try out the new server version with your existing content before you decide to upgrade. The best way to do this is on a dedicated server machine, or at a minimum on a separate Tomcat instance. You should use a separate AppData directory for the new server while you are evaluating it --- if for some reason you decide to wait with the upgrade, you will not be able to use the new version's AppData on the old server, even if you have not made any changes.

Summary of steps:

- 1. Make a full backup of the old server's AppData directory.
- 2. Configure a new Tomcat, ideally on a separate machine.
- 3. Put the new server WAR file in the new Tomcat's webapps directory.
- 4. Copy the entire AppData from the old server to the new server.
- 5. Make sure the new server is pointed at the new AppData copy.
- 6. Read <u>below</u> for how content is migrated between versions.
- 7. Start the new server and then review its log file carefully to see if there were any warnings related to migration.
- 8. Try out the new server. Keep in mind that content created or changed on the new server cannot be moved back to the old server if you decide to roll back.
- 9. If you have continued to use the old server in parallel with testing, you should copy over the AppData again to make sure you have the latest content.

Content Migration

The format of the AppData changes between versions. Certain types of content may be moved to a different location with the AppData e.g., bookmarks from loose files into the repository for version tracking and cluster replication. Frequently, new features may be added to the content which may include changes to the content models, e.g., workbooks with new property. Typically, a newer server version will do this migration behind the scenes when it first starts up, and any issues found will be logged with at least a warning level.

NOTE

After starting a new server version for the first time, check the log file for warnings. It is much easier to address these issues immediately than later on, for example, if you wish to redo a one-time migration step.

By default, the server will check for content in an old location in AppData and do a one-time migration of anything it finds when it starts. Typically, the server will copy old content from loose files into the repository. This type of migration is controlled through the repository.migrate.<type>.path properties in Panopticon.properties.

For example, in versions 21.1 and older, the server stored workbook bookmarks as loose files in the AppData/Bookmarks/ directory. Version 21.2 stores them inside the repository in AppData /.repository/instead. The property repository.migrate.bookmarks.path defaults to Bookmarks which is relative to AppData and therefore points to the 21.1 bookmark files. When the 21.2 server starts, this can happen:

- There are no bookmarks in the repository but are available in AppData/Bookmarks/ or to some other location you have set the property to. The server will do a one-time migration and move them into the repository. The result of this will be logged. The old bookmark files are left in the old location but will no longer be used.
- There are bookmarks in the repository. You may have created them on the new server, or the migration has run already. In this case, it does not matter if the old location has bookmarks or not, and the server will log a warning that it will not run a second migration. To get rid of the warning, simply blank out the property value.
- There are no bookmarks in either location, but the property is still set. This would be the default on a new server. In this case, you will get a false migration warning because the server cannot find AppData/Bookmarks/. Again, just blank out the property value to get rid of the warning.

NOTE

- Because the server will not migrate a type of content (e.g., bookmarks) if that
 type of content is already in the repository, you will need to delete the
 repository to run the migration again. The easiest way is to start over with the
 AppData from the old server.
- After the content has been migrated, the original files are left in the old location in AppData. They are no longer used, to clean up, you may want to delete them after you have checked the logs for any migration issues.

There are some types of content that have changed so much between releases that they cannot be automatically migrated like this.

Workbooks and their history in version 17 and older were stored separately in <code>AppData/Workbooks/</code> and <code>AppData/Archive/</code>. You can use the <code>repository.migrate.workbooks.path</code> and <code>repository.migrate.archive.path</code> properties to migrate them, but we do not default these to the old locations (e.g., you may not want to migrate the entire history), and for clarity you need to use absolute paths if you set them.

Data files used with text data sources can now optionally be stored in the repository so they can be bundled with the workbook, and replicated to other servers in a cluster. You can still have data files in AppData/Data/, so old workbooks will continue to work on new servers, but old files are not automatically migrated into the repository.

Permissions on workbook folders were in version 17 and older stored in XML files in the AppData/Workbooks/subtree. The permissions model has changed completely since then, so they are not automatically migrated. To migrate permissions from version 17, you need to:

- 1. Use PCLI <u>convertpermissions</u> to create a permissions template which, as closely as possible, reflects the old permissions. This is a single JSON file which the new server can apply to its repository.
- 2. Review the generated permissions template in a text editor to make sure it is correct.
- 3. Point the repository.startup.apply.permissions.path to the template file and start the server. You can control how the template is applied with the properties repository.startup.apply.permissions.clean and repository.startup.apply.permissions.create.
- Clear the properties after the server has started, or they will be applied on each startup overwriting changes you
 make.

NOTE

In version 17 and earlier, the files AppData/Administrators.txt and AppData/AdministratorsGroup.txt were used to give users administrative permissions. Currently, with the normal permissions model, these files are no longer used.

Authentication tokens are server-specific. They will only work on a new server if it has the same authentication.token.secret value as the old server that created them. In addition, a normal user token is also stored as cookie in the user's browser and will only get sent to a new server if it has the same URL as the old server. For these reasons, tokens are not automatically migrated, and users will have to log in again.

The exception to token migration is API tokens. In version 21.1 and older, these were stored in AppData/APIToken/. In 21.2, all tokens, including the API tokens, are stored in the shared cluster storage (even if you only have one single server), by default in AppData/shared/tokens/. See also the section on Synchronizing Tokens. If the server finds API tokens in the old location, they will be migrated on startup.

[3] AUTHENTICATION

INTRODUCTION

Panopticon Real Time provides multiple approaches on authentication. It can easily be configured to use different authentication mechanisms depending on the environment and the setup. The server only supports authentication and authorization and does not have any support for user management or administration of users.

There are mainly two properties that manage the authentication on the server. These properties are listed and described in the table below. Please note that more properties might need to be configured depending on the authentication mechanism you are using.

Property	Description	Default value
authentication.role	The required role or group that the user needs to be identified as a Panopticon user. The property can be left blank if no role or group is required.	
authentication.required	This property will make the authentication required. It will force the user to login in order to use any of the services provided by the server.	true
authentication.type	The type of authentication that should be used when authenticating the user. The property allows the following values: BASIC, FILTER, HEADER, OAUTH2, SAML, WINDOWS.	BASIC
authentication.domain	The default domain information for user authentication.	

Depending on the authentication or user management mechanism used, the role that a user should have is specified and then mapped to a group set in Panopticon.properties.

Property	Description	Default Value
access.administrator.groups	The role that is mapped to the administrator group.	admin
access.default.roles	The default roles applied to all users of the server. For example, if access.default.roles=DESIGNER,ADMINISTRATOR and a user with a VIEWER role logs on to the server, then the user will simultaneously have a VIEWER, DESIGNER, and ADMINISTRATOR roles. A blank value for access.default.roles is equivalent to ANONYMOUS. A blank value or the value ANONYMOUS will NOT block users from authenticating. NOTE: The roles that can be assigned in this property can only be ADMINISTRATOR, VIEWER, ANONYMOUS, and/or DESIGNER. This property is case sensitive.	VIEWER
access.designer.groups	The role that is mapped to the designer group.	designer
access.viewer.groups	The role that is assigned to the viewer group.	

- Group sets can be added for a role, separated by a comma.
- To be able to use all of the features of Panopticon Real Time, a user is required to have Designer and Administrator roles.
- When using <u>Altair Units licensing</u>, different user roles will check out different numbers of Altair Units.

Role	Altair Unit Draw
Viewer	2
Designer	2 10 when designing a workbook
Administrator	2

Normally, you should use role mapping to control user access. This way you can manage access in the same place that you manage your users without having to reconfigure the server.

In some scenarios, it may be impossible to set up appropriate roles for Panopticon in your external system, or you may want to make one-off exceptions for specific users. As a workaround for these cases, you can also explicitly list individual users and their access in the server configuration with the access.designer.users, and access.you can also explicitly list.

Configuring Which Users are Allowed to Log On to Panopticon

When access.default.roles is set to blank (nothing), it is equivalent to setting it to the role **ANONYMOUS**. This means that, authenticated users will get the role **ANONYMOUS** when they don't have any of the roles that give them any of the following capabilities such as **VIEWER**, **DESIGNER**, or **ADMINISTRATOR** in Panopticon. The role **ANONYMOUS** in practice gives a user **VIEWER** capabilities in any folders where "Everyone" is allowed to read.

This means that setting access.default.roles to blank is NOT a valid way of preventing users from successfully authenticating and getting access to Panopticon. It is only related to default authorization of users, while it does not affect authentication.

In an organization where only, selected users should have access to Panopticon, as opposed to letting any existing user have access, one of the following approaches should be taken:

a. The authentication approach (preferred)

Configure the authentication layer integration to specify which group memberships are required to be allowed to authenticate, so that only users to whom you intend to give access to Panopticon are allowed to authenticate. For example, when using LDAP, add a userPattern specification of an OU (Organizational Unit) that is allowed to authenticate in the Realm configuration.

b. The content access control approach (use only of option **a** is unavailable)

Change the general content access control on Panopticon by changing the settings on its root folder, so that the role names associated with **VIEWER** and **DESIGNER** capabilities are listed as Allowed to Read and remove "Everyone" from the *Allowed* section. (NOTE: Users with roles that are associated with ADMINISTRATOR capability will always have access to all folders.) The disadvantage of using this approach is, any existing user will still be able to successfully authenticate and view any content where "Everyone" is allowed to read.

Token

A web token is used when the user has successfully logged into Panopticon Real Time when using one of the following authentication types: **BASIC**, **SAML**, or **WINDOWS**. The token is used to identify the user and represent the user's ongoing session. This is done to prevent user credentials being sent between the user and server more than necessary.

The token is returned from Panopticon Real Time in the form of a cookie when the user has been authenticated. By default (false), the cookie will be stored in the browser as https cookie and is accessible to the JavaScript.

The token can be configured differently to suit your needs and requirement. The token can be configured to be valid at a certain amount of time, if it can refresh itself, if it should be persistent or if it should only last for a user session (while the browser is still open), and/or it can be stored as a HttpOnly cookie. All this can be configured in the Panopticon.properties. The table below lists all available token properties.

Property	Description	Default Value
authentication.token.persistence	This property is used to determine if the token should persist if the browser is closed or if it should only last while the browser is open. There are two possible values: PERSISTENT and SESSION . PERSISTENT will persist the token in the browser even if the browser has been closed and reopened. SESSION will remove the token from the browser if it is shutdown. IMPORTANT: After modifying the property value to SESSION , ensure to clear the AppData/Token folder before starting the server.	PERSISTENT
authentication.token.refreshable	This property determines if the token can refresh itself. The Web client can identify if the token is about to expire and then request a new token with the existing token. A token is refreshable if the property is set to true . The token will expire and invalidate the user session if the property is set to false .	true
authentication.token.secret	The secret is used to sign the token. The secret will be auto generated when the server starts for the first time. NOTE: This value should be kept a secret.	Auto-generated
authentication.token.validity.seconds	The number of seconds that the token should be valid.	604800
authentication.token.cookie	The name of the cookie used to store the authentication cookie. Must be unique for each server instance on the host.	ptoken
authentication.token.cookie.httponly	This property determines how the browser will treat the cookie. If set to true , the cookie will be stored in the browser as a HttpOnly cookie and will not be available to the JavaScript. If set to false (default), the cookie will be stored in the browser as https and will be accessible to the JavaScript.	false
authentication.token.cookie.secure	This property determines how the browser will treat the cookie depending on the security of the connection. If set to true , when the browser	false

	receives a secure cookie (HttpOnly cookie), you will not be able to transmit it unless the connection is secure.	
authentication.token.in.login.response .body	This property determines if the REST login response body should contain a token info. NOTE: Does not affect the SOAP login response body.	false

TOMCAT REALM

Panopticon Real Time can be configured to use the Tomcat Realm when performing authentication. The Tomcat Realm is configured in the server.xml file in the Tomcat conf folder. The Tomcat Realm itself can be configured to authenticate towards a variety of different types of authentication source, such as Tomcat user base and LDAP. The sub chapters in this chapter will give examples on how to configure the Tomcat Realm.

Panopticon Real Time needs to be configured to use the BASIC type in order to do the authentication towards the Tomcat Realm. To enable Tomcat Realm authentication, set this property in the Panopticon.properties file:

authentication.type=BASIC

NOTE

- Reading the Apache Tomcat documentation is recommended:
 https://tomcat.apache.org/tomcat-9.0-doc/realm howto.html. Abbreviations used: CN = Common Name, OU =
 Organizational Unit, DC = Domain Component.
- It is a common approach to wrap your Tomcat Realm with the LockOutRealm. This is used to prevent brute-force attacks.

```
<Realm
className="org.apache.catalina.realm.LockOutRealm">
     <!-Insert your own Tomcat Realm here  
     </Realm>
```

Tomcat User Base

The Tomcat User Base Realm is using a JNDI resource to store user information. By default, the JNDI resource is configured in an XML file. The default file is tomcat-users.xml in the Apache Tomcat conf folder.

We strongly recommend using this authentication approach for your test or local environment. It is easy to setup and configure. However, it is not designed to be used for large-scale production or when you have a large number of users.

The following Realm should be added in the server.xml file in the Apache Tomcat conf folder:

<Realm className="org.apache.catalina.realm.UserDatabaseRealm"
resourceName="UserDatabase"/>

NOTE

The Tomcat User Database Realm is used as the default. No configurations are

required in the server.xml file to be able to use the Tomcat Database Realm.

The users and roles are managed in the tomcat-users.xml file in the Apache Tomcat conf folder. In this file, you can add users and roles as well as assign roles to users.

Example 1

Add the following role and user to your tomcat-users.xml file:

```
<role rolename="administrator"/>
<user username="James" password="james" roles="administrator"/>
```

By adding these two lines you have achieved the following:

- Created a new role named administrator
- Created a new user with username James and password james
- Assigned the newly created user the role administrator

Example 2

```
<role rolename="admin"/>
<role rolename="designer"/>
<role rolename="user"/>
<user username="viewer" password="viewer" roles="user"/>
<user username="John" password="john" roles="user,admin"/>
<user username="Paul" password="paul" roles="user,designer"/>
<user username="Austin" password="austin" roles="user,designer,admin"/>
```

By adding these seven lines, you have achieved the following:

- ☐ Created three new roles named admin, designer, user
- ☐ For the role **user**, created four users:
 - with username viewer and password viewer
 - with username John and password john
 - with username Paul and password paul
 - with username Austin and password austin
- ☐ For the role **admin**, created two users:
 - with username John and password john
 - with username Austin and password austin
- For the role **designer**, created two users:
 - a user with username Paul and password paul
 - with username Austin and password austin

User Austin has both administrator and designer roles and is considered a super user.

A sample tomcat-users_example.xml is provided in the AltairPanopticonVisualizationServerWAR_<version number>.zip file. You can modify or add new users and roles in this file.

In Panopticon 2020 and onwards, the Administrators.txt and AdministratorGroup.txt files are no longer used to authorize administrator users. The function provided by these files has been replaced by a set of properties in Panopticon.properties:

```
access.default.roles=VIEWER
access.administrator.groups=admin
access.designer.groups=designer
access.list.delimiter=,
access.viewer.groups=
```

The access.default.roles property defines the default roles assigned to any user accessing the server, defaulting to VIEWER. The administration (access.administrator.groups property) and content creation (access.designer.groups property) on the server are mapped by default to the admin and designer user groups.

Group sets can be added for a role, by default separated by a comma.

Encrypting Passwords in tomcat-users.xml

Tomcat supports encrypted user credentials via the Digested Passwords feature:

https://tomcat.apache.org/tomcat-9.0-doc/realm-howto.html#Digested Passwords

To secure passwords saved in tomcat-users.xml, do the following:

- 1. Stop Tomcat.
- Open [tomcat home]/conf/server.xml.
- 3. In server.xml, find the Engine XML element.

Nested inside the Engine element, there is a Realm element named LockOutRealm. Nested inside the LockOutRealm is another Realm element named UserDatabaseRealm that looks like this:

```
<Realm className="org.apache.catalina.realm.UserDatabaseRealm"
    resourceName="UserDatabase"/>
```

4. Edit the UserDatabaseRealm element into the following:

You must add the closing element "</Realm>" for the UserDatabaseRealm and edit out the closing forward slash "/" at the end of the original Realm element.

5. Generate hash from plain text passwords using the command below:

Linux example:

```
[tomcat_home]/bin/digest.sh -a SHA-256 -h
org.apache.catalina.realm.MessageDigestCredentialHandler [password]
```

Windows example:

[tomcat_home]/bin/digest.bat -a SHA-256 -h
org.apache.catalina.realm.MessageDigestCredentialHandler [password]

NOTE

If your Apache Tomcat installation has the ${\tt JAVA_HOME}$ environment variable set only in the file catalina.sh (Linux) or catalina.bat (Windows) and not generally on the system, you will also need to set the ${\tt JAVA_HOME}$ variable before running the digest command.

Linux example:

export JAVA HOME=/path/to/JavaInstallation

Windows example:

set JAVA HOME=/path/to/JavaInstallation

The digest command will return the password supplied, followed by a colon, and then a hash of the password. Example, for a password **asd123**:

asd123:74807befd6bdc1c937dc931a3dfadf015da1df1b99b74cd8d91210788e0141a5\$1\$f21cb2dd667209d6 39f6be48cf83826a657730032bdacb04465262d221bfc509

- 6. Replace the plain text password in tomcat-users.xml with the generated password hash and save the tomcat-users.xml file. NOTE: When you have defined a MessageDigestCredentialHandler in the UserDatabaseRealm, then ALL passwords stored in tomcat-users.xml are treated as hash values. You will no longer be able to log in using passwords that are saved as clear text.
- 7. Start Tomcat.

LDAP

Panopticon Real Time can be configured to authenticate towards a Lightweight Directory Access Protocol (LDAP) or source. By configuring the Apache Tomcat Realm, the server can authenticate users and extract their roles by querying the LDAP source.

The realm's connection to the directory is defined by the <code>connectionURL</code> attribute. Each user that can be authenticated must be represented in the directory with an individual entry that corresponds to an element in the initial <code>DirContext from the connectionURL</code>. This user entry must have an attribute containing the username that is presented for authentication.

You can add a dedicated user with <code>connectionName</code> and <code>connectionPassword</code> in a Realm to define a user with a Read access to the user database and roles. If for example the admin <code>cn</code> name is set as admin and the admin <code>password</code> is set as admin, then you need to add these properties as shown in the example below.

The userPattern attribute may be used to specify the DN, with " $\{0\}$ " marking where the username should be substituted.

The role is usually an LDAP group entry with one attribute containing the name of the role and another one whose values are distinguished names or usernames of the users in that role. The following attributes configure a directory search to find the names of roles associated with the authenticated user:

roleBase: The base entry for the role search. If not specified, the search base is the top-level directory context
 roleSearch: The LDAP search filter for selecting role entries
 roleName: The attribute in a role entry containing the name of that role
 roleNested: Includes nested roles if set to true. This means every newly found roleName and distinguished

The following is an example on how the Realm can be configured when using LDAP, in conf/server.xml. Please note that the values should be replaced with details from your own LDAP source.

Name will be recursively tried for a new role search. The default behavior is false.

```
<Realm className="org.apache.catalina.realm.JNDIRealm"
    connectionURL="ldap://localhost:389"
    connectionName="cn=admin,dc=test,dc=com"
    connectionPassword="admin"
    userPattern="uid={0},ou=users,dc=test,dc=com"
    roleBase="ou=groups,dc=test,dc=com"
    roleName="cn"
    roleSearch="(uniqueMember={0})"
    rolenested="true"</pre>
```

Using this configuration, the realm determines the user's distinguished name by substituting the username into the userPattern, authenticates by binding to the directory with this DN and the password received from the user, and searches the directory to find the user's roles.

NOTE

If you opt not to have a dedicated user, remove <code>connectionName</code> and <code>connectionPassword</code>, and then have each user extract information about itself. You do this by adding <code>userSearchAsUser</code> and <code>roleSearchAsUser</code> in a Realm and setting both values to true. The recommended usage, however, is to have a dedicated user. This allows you to always have the rights to query a LDAP, unlike using <code>userSearchAsUser</code> and <code>roleSearchAsUser</code> where there is no guarantee that each user is authorized to extract these details.

You can specify more than one LDAP domain by defining a **Combined Realm**. This is done by putting more than one Realm configuration within a parent CombinedRealm:

```
(realm details...) />
</Realm>
```

LockOutRealm (mentioned at the start of this chapter) is an implementation of the Tomcat Realm interface that extends the CombinedRealm. For futher information, please see Apache Tomcat 9 documentation on https://tomcat.apache.org/tomcat-9.0-doc/realm-howto.html.

Using LDAPS

To use TLS/SSL encrypted communication between Panopticon Real Time and the LDAP directory, we need to make the following changes in configuration:

- □ Change the protocol in the LDAP URL to **Idaps**
- ☐ Change the port in the LDAP URL to an SSL enabled port, typically 636
- If the LDAP directory is configured with a self-signed certificate; the certificate needs to be imported into a TrustStore.

See an example of a Tomcat Realm using LDAPS below:

```
<Realm className="org.apache.catalina.realm.JNDIRealm"
    connectionURL="ldaps://ldap-server:636"
    connectionName="cn=admin,dc=test,dc=com"
    connectionPassword="admin"
    userPattern="uid={0},ou=users,dc=test,dc=com"
    roleBase="ou=groups,dc=test,dc=com"
    roleName="cn"
    roleSearch="(uniqueMember={0})"
    rolenested="true"
/>
```

There are two options for trusting a self-signed LDAP certificate:

☐ Import the certificate into the JVM TrustStore

The JVM TrustStore is located at ${\tt JAVA_HOME/lib/security/cacerts}$. Use the command below to add a new trusted certificate to the TrustStore:

keytool -import -alias ldap -keystore cacerts -trustcacerts -file ldap.crt
-noprompt -storepass changeit

- ☐ Create an application TrustStore
 - 1. Import the chain certificate:

```
keytool -import -alias root -keystore ldaptruststore.jks -trustcacerts -file ca.pem -noprompt -storepass changeit
```

2. Import the LDAP server certificate:

```
keytool -import -alias ldap -keystore ldaptruststore.jks -file ldap.crt
-noprompt -storepass changeit
```

Check the TrustStore.

```
keytool -list -keystore ldaptruststore.jks -storepass changeit
```

- 4. Configure Tomcat to use the new TrustStore by editing setenv.bat/.sh:
 - setenv.bat (Windows)

```
set JAVA_OPTS=%JAVA_OPTS% "-Djavax.net.ssl.trustStore=[path to
ldaptruststore.jks]" "-Djavax.net.ssl.trustStorePassword=changeit"
```

setenv.sh (Linux)

```
export JAVA_OPTS="$JAVA_OPTS -Djavax.net.ssl.trustStore=[path to
ldaptruststore.jks]-Djavax.net.ssl.trustStorePassword=changeit"
```

With either approach, Tomcat need to be restarted for the changes to have effect.

Active Directory

Panopticon Real Time can be configured to authenticate towards an Active Directory server. Panopticon Real Time is using LDAP to interact and communicate with the Active Directory server. Therefore, the configuration is very similar to the LDAP configuration in the previous section.

The following is an example on how the Realm can be configured when using Active Directory. Please note that the values should be replaced with details from your own LDAP source.

```
<Realm className="org.apache.catalina.realm.JNDIRealm"</pre>
    adCompat="true"
    connectionURL="ldap://ad.test.com:3268"
    alternateURL="ldap://ad.test.com:389"
    authentication="simple"
    referrals="follow"
    connectionName=admin@test.com
    connectionPassword="admin"
    userBase="cn=Users,dc=test,dc=com"
    userSearch="(sAMAccountName={0})"
    userSubtree="true"
    roleBase="cn=Users,dc=test,dc=com"
    roleName="cn"
    roleSearch="(member={0})"
    roleSubtree="true"
    roleNested="true"
/>
```

- Similar with LDAP, you can opt not to have a dedicated user by removing connectionName and connectionPassword and instead let each user extract information about itself by adding userSearchAsUser and roleSearchAsUser in a Realm. Set both values to true. As mentioned in the LDAP section, the recommended usage is to have a dedicated user since there is no guarantee that each user is authorized to extract these details.
- For the userSearch attribute you can use either
 "(sAMAccountName={0})" or "(UserPrincipalName={0})".
 - sAMAccountName supports clients and servers pre-Windows 2000 and expects the input format DomainName\userName.
 - UserPrincipalName is a modern, internet-style user name and expects input on the format userName@DomainName.com.

Example:

```
<Realm
className="org.apache.catalina.realm.JNDIRealm"
    adCompat="true"
    connectionURL="ldap://ad.test.com:3268"
    alternateURL="ldap://ad.test.com:389"
    userSearchAsUser="true"
    roleSearchAsUser="true"
    authentication="simple"
    referrals="follow"
   userBase="cn=Users,dc=test,dc=com"
   userSearch="(sAMAccountName={0})"
   userSubtree="true"
    roleBase="cn=Users,dc=test,dc=com"
    roleName="cn"
    roleSearch="(member={0})"
   roleSubtree="true"
    roleNested="true"
/>
```

A useful tool when configuring your Active Directory realm is Active Directory Explorer from Microsoft Sysinternals: https://docs.microsoft.com/en-us/sysinternals/downloads/adexplorer.

USEFUL TIP

Depending on how your Active Directory is set up, you may need to specify different attribute values for your userBase and your roleBase. For further info, see Apache Tomcat 9 documentation about realms: https://tomcat.apache.org/tomcat-9.0-doc/realm-howto.html.

Abbreviations used: CN = Common Name, OU = Organizational Unit, DC = Domain Component

WINDOWS AUTHENTICATION

Panopticon Real Time supports Windows authentication. Panopticon Real Time will authenticate a user towards the local machine and verify its credentials with the existing and configured users on the Windows machine. The Windows authentication operates similarly to the Basic authentication function. Both the username and the password are sent to Panopticon Real Time which they are then verified.

To enable Windows authentication, set this property in the Panopticon.properties file:

authentication.type=WINDOWS

NOTE

SSO is currently not supported with the Windows authentication. In addition, Windows authentication only supports authentication towards the local machine. This means that the machine where Panopticon Real Time is deployed on also must manage all of the users.

SAML

Panopticon Real Time supports Security Assertion Markup Language, SAML2. Upon a login request, Panopticon Real Time will redirect the user to an Identity provider (IdP). The IdP will authenticate the user and redirect the user back to Panopticon Real Time. The response message will be controlled and validated. Username and roles will be extracted from the response message and used within Panopticon Real Time.

Panopticon Real Time will redirect the user back to the IdP upon a logout request. The IdP logout service should then invalidate the SAML token.

Property	Description
authentication.saml.assertion.roles	User attribute for roles configured in the IdP.
authentication.saml.assertion.username	User attribute for username configured in the IdP.
authentication.saml.assertionconsumerservice.u rl	The URL to the Panopticon assertion consumer service. URL: [Protocol]://[Host]:[Port]/[Context]/server/rest/auth/login Example: http://localhost:8080/panopticon/server/rest/auth/login
authentication.saml.certificate.name	The name of the certificate used to validate signature and/or sign outgoing SAML messages
authentication.saml.certificate.password	The password of the certificate used to validate signature and/or sign outgoing SAML messages
authentication.saml.challenge.required	Determines whether the IdP-first authentication with SAML is enabled or not. To enable, set this property to false .
authentication.saml.identityprovider.logout.url	The URL to the IdP logout service.
authentication.saml.identityprovider.url	The URL to the IdP login service.
authentication.saml.keystore.file	The location of the Keystore file that contains the certificate.
authentication.saml.keystore.password	The password to the Keystore file.

authentication.saml.serviceprovider.id	The ID of the service provider configured in the IdP.
authentication.saml.identityprovider.certificate.fil e	Takes a file path to a certificate file that contains the IdP's public key.
authentication.saml.identityprovider.signature.val idation.required	Specifies whether to require a valid IdP signature to be present on the SAML response. Default value is false .
authentication.saml.provider	The IdP provider. Possible values are OPENSAML , OPENAM . Default value is OPENSAML .
authentication.saml.keystore.type	The key store type. Possible values are JKS , JCEKS , PKCS12 . Default value is JKS .
authentication.saml.login.redirect.url	Redirects the user to the specified URL after successfully logging in. This property can be left blank, in which case the user is redirected to the URL they requested to access.
authentication.saml.logout.redirect.url	Redirects the user back to the specified URL after logging out. This is mainly used with a proxy. In which case, Panopticon Real Time does not know the endpoint which the user is going towards to, and therefore cannot redirect the user back to the Overview page. If you are using OpenAM this is required, otherwise this property can be left blank.
authentication.saml.openam.meta.alias	The meta alias for the IdP if you are using OpenAM.

Using SAML Through OpenAM

To enable roles mapping with OpenAM, perform the following configuration in the IdP:

- 1. Add value **isMemberOf** to the LDAP User Attributes list in your Data Store.
- 2. Add value **isMemberOf** to the attributes mapping in your IdP configuration.
- 3. Set authentication.saml.assertion.roles=isMemberOf in the Panopticon.properties.

OAUTH 2.0

This section discusses how to configure Panopticon Real Time to use OAuth 2.0 for authorization. Upon a logon request, Panopticon Real Time will redirect the user to the Login page provided by OAuth 2.0.

Note that OAuth 2.0 does not normally provide support on how to authenticate the user, Panopticon Real Time will only know if the user is authorized or not. To authenticate the user, Panopticon Real Time can be configured to use a REST service to extract the user identity with an access token retrieved from the OAuth 2.0 provider. In addition to the standard OAuth 2.0 configurations, the server includes properties (i.e., authentication.oauth2.*) that are specifically used to extract the user details.

If user roles are configured, the user identity attribute (i.e., authentication.oauth2.identity.attribute.roles=<Name of role attribute in OAuth2 server>) will expect a list of roles that enable role based access restrictions on workbook folders.

For example: "roles": ["VIEWER", "DESIGNER"]

If this attribute is not set, the default role VIEWER is used.

To use OAuth2.0, change the authentication type:

 $\verb"authentication.type=OAUTH2"$

Afterwards, go through the following properties to be configured with respect to your OAuth server configuration.

Property	Description
authentication.oauth2.client.id	The ID of the OAuth 2.0 client.
authentication.oauth2.client.se cret	The secret used by the OAuth 2.0 client.
authentication.oauth2.identity. attribute.roles	The attribute that will be extracted from the identity response and used as the role.
authentication.oauth2.identity. attribute.roles.pattern	Takes regex used to extract the roles from the OAuth 2.0 server identity response. For example, the returned string:
	<pre>cn=admin,ou=groups,dc=openam,dc=openidentityplatform,dc= org,cn=designer,ou=groups,dc=openam,dc=openidentityplatf orm,dc=org</pre>
	contains two roles, admin and designer
	The regex to extract the roles is cn=([^,]+) .
authentication.oauth2.identity. attribute.username	The attribute that will be extracted from the identity response and used as the username.
authentication.oauth2.identity. url	The URL to the REST service that provides details about the authenticated user.
authentication.oauth2.login.call back.url	The callback URL. The URL should be the same as one of the specified callback URLs used by the client. The URL should refer to Panopticon Real Time.
authentication.oauth2.login.res ponse.type	The response type. The only response type that is currently supported is code . The value can also be left blank.
authentication.oauth2.login.red irect.url	Redirects the user to the specified URL after successfully logging in. This property can be left blank, in which case the user is redirected to the URL they requested to access.
authentication.oauth2.login.sc ope	The requested scope. The property can be left blank.
authentication.oauth2.login.url	The URL to the OAuth 2.0 login resource. This field can be left blank.
authentication.oauth2.logout.re direct.url	Logging out revokes the token from the authentication server if the property authentication.oauth2.logout.url is set to the revocation URL. If this property is not set, the server will only remove its own token.
	If none of these properties are set, the server will attempt to redirect to the start page of the Panopticon when logging out.
authentication.oauth2.logout.ur	The URL to the OAuth 2.0 logout resource. This property can be left blank.
authentication.oauth2.token.m ethod	The method on how the token should be retrieved. Supported values are QUERY , BODY , and HEADER .
authentication.oauth2.token.url	The URL to the OAuth 2.0 token resource.

access.default.roles	The default role that will be assigned to everyone to execute a specific service. The field can be left blank. If left blank, VIEWER role is used.
access.administrator.groups	The list of administrator roles authenticated by the OAuth2.0 server.
access.designer.groups	The list of designer roles authenticated by the OAuth2.0 server.
access.viewer.groups	The list of viewer roles authenticated by the OAuth2.0 server.

Example

For an example of OAuth2.0 server configuration, here are some roles and users:

Roles/Groups available:

- admin-backend
- admin-all
- server-designers
- server-viewers
- server-viewer-groupX

Users:

```
    username:testuser, roles:["server-viewers"]
    username:testuser2, roles:["server-viewers", "server-designers", "admin-all"]
```

For the OAuth2.0 server authentication, you would have to generate ClientID and ClientSecret.

To be authenticated by the OAuth2.0 server, the following Panopticon properties will be set:

```
authentication.oauth2.client.id=ClientId
authentication.oauth2.client.secret=ClientSecret
authentication.oauth2.identity.attribute.roles=roles
authentication.oauth2.identity.attribute.username=username
authentication.oauth2.identity.url=https://oauth2/me
authentication.oauth2.login.callback.url=http://localhost:8080/panopt
icon/server/rest/auth/login
authentication.oauth2.login.redirect.url=
authentication.oauth2.login.response.type=code
authentication.oauth2.login.scope=
authentication.oauth2.login.url=https://oauth2/authorize
authentication.oauth2.logout.redirect.url=
authentication.oauth2.logout.url=
authentication.oauth2.token.method=QUERY
authentication.oauth2.token.url=https://oauth2/access token
authentication.type=OAUTH2
access.default.roles=
access.administrator.groups=admin-backend,admin-all
access.designer.groups=server-designers
access.viewer.groups=server-viewers,server-viewer-groupX
```

Using OAuth 2.0 Through OpenAM

To enable roles mapping and username retrieval with OpenAM, perform the following configuration in the IdP:

- 1. Add value **isMemberOf** to the LDAP User Attributes list in your Data Store.
- 2. Add values **uid|Username** and **isMemberOf|Groups** to the scopes mapping in your OAuth agent configuration. Example configuration in Panopticon.properties:

```
authentication.oauth2.client.id=panopticon
authentication.oauth2.client.secret=password123
authentication.oauth2.identity.attribute.roles=isMemberOf
authentication.oauth2.identity.attribute.roles.pattern=cn=([^,]+)
authentication.oauth2.identity.attribute.username=uid
authentication.oauth2.identity.url=http://localhost:9080/openam/oauth2/t
authentication.oauth2.login.callback.url=http://localhost:8080/panoptico
n/server/rest/auth/login
authentication.oauth2.login.redirect.url=
authentication.oauth2.login.response.type=code
authentication.oauth2.login.scope=uid isMemberOf
authentication.oauth2.login.url=http://localhost:9080/openam/oauth2/auth
authentication.oauth2.logout.redirect.url=http://localhost:8080/panoptic
authentication.oauth2.logout.url=http://localhost:9080/openam/oauth2/tok
en/revoke
authentication.oauth2.token.method=OUERY
authentication.oauth2.token.url=http://localhost:9080/openam/oauth2/acce
ss token
authentication.type=OAUTH2
```

OAuth 2.0 Integration with Azure Active Directory

Below is an example of configuration values in Panopticon.properties when doing SSO integration of Panopticon with Azure Active Directory. The example values are explained in this table:

Value	Explanation
https://myhost:8443/panopticon	The URL where Panopticon is accessed.
dfe52dce-6a65-4ebf-85c0-155c45782ad6	Panopticon client id from Azure app.
ptB8Q~lKsqdSOLEKDFKc0eUgsDazpE5aEgvFUebG3	Panopticon client secret from Azure app.
2bae5b57-0eb8-48fb-ba47-990259sk45kj	Azure tenant id.
https%3A%2F%2Fmyhost%2Flogout	URL-encoded https://myhost/logout.

Panopticon.properties example configuration:

```
authentication.oauth2.client.id=dfe52dce-6a65-4ebf-85c0-155c45782ad6
authentication.oauth2.client.secret=ptB8Q~lKsqdSOLEKDFKc0eUgsDazpE5aEgvFUebG3
authentication.oauth2.identity.attribute.roles.pattern=
authentication.oauth2.identity.attribute.roles=groups
authentication.oauth2.identity.attribute.username=email
authentication.oauth2.identity.method=HEADER
authentication.oauth2.identity.url=https\://graph.microsoft.com//oidc/userinf
authentication.oauth2.login.callback.url=https\://myhost\:8443/panopticon/ser
ver/rest/auth/login
authentication.oauth2.login.redirect.url=https\://myhost\:8443/panopticon
authentication.oauth2.login.response.type=code
authentication.oauth2.login.scope=openid profile
authentication.oauth2.login.url=https\://login.microsoftonline.com/2bae5b57-
Oeb8-48fb-ba47-990259sk45kj/oauth2/v2.0/authorize
authentication.oauth2.logout.redirect.url=
authentication.oauth2.logout.url=https://login.microsoftonline.com/2bae5b57-
0eb8-48fb-ba47-
990259sk45kj/oauth2/v2.0/logout?post logout redirect uri=https%3A%2F%2Fmyhost
%2Floqout
authentication.oauth2.token.method=
authentication.oauth2.token.url=https\://login.microsoftonline.com/2bae5b57-
0eb8-48fb-ba47-990259sk45kj/oauth2/v2.0/token
authentication.required=true
```

NOTE

- The value of the authentication.oauth2.logout.url property (i.e., https://login.microsoftonline.com/2bae5b57-0eb8-48fb-ba47-990259sk45kj/oauth2/v2.0/logout?post_logout_redirect_uri=https%3A%2F%2Fmyhost%2Flogout) must also be registered as the Logout URL value in the Azure app configuration.
- The parameter **post_logout_redirect_uri** is set to a URL different from the URL of the Panopticon server, this is because, if the user is redirected back to the Panopticon server at logout, there will be an immediate re-login of the user in the Panopticon application due to the SSO integration with Azure AD.

• For the authentication.oauth2.identity.attribute.roles property, Microsoft recommends that user roles are handled by creating app roles that map to AD user and/or groups, instead of using AD groups directly. The maximum number of groups that the AD will return is 50.

FILTER

Custom authentication filters can be applied to the server and the application when the default authentication settings are not sufficient. This type of authentication is referred to as **Filter authentication**. When Panopticon Real Time is configured to use filter authentication, it means that the incoming requests have already been authenticated and authorized before reaching the server. Follow the steps below to configure filter authentication:

- 1. Open the Panopticon.properties file in the AppData folder (C:\vizserverdata).
- 2. Enable authentication.type=FILTER in Panopticon.properties.
- 3. Apply the following URL pattern to your own filter: /*
- 4. Save the changes and restart Tomcat.

Creating a Custom Filter

The custom filter will be a basic authentication filter which will authenticate the user with hardcoded values. The Principal forwarded by the filter will be used to authenticate the user.

The filter will require the following dependencies:

- Javax Servlet
- Tomcat embed core

Steps:

1. Create a HTTP request wrapper.

The class will contain the following:

- the original incoming HTTP request
- the Principal which contains both the credentials and the roles for the authenticated user.

The HTTP wrapper will be forwarded to Panopticon Real Time instead of the original incoming HTTP request.

```
import org.apache.catalina.realm.GenericPrincipal;
import org.apache.catalina.users.MemoryUser;
import javax.servlet.http.HttpServletRequest;
import javax.servlet.http.HttpServletRequestWrapper;
import java.security.Principal;

public class FilterRequestWrapper extends HttpServletRequestWrapper {
    private final GenericPrincipal principal;
```

```
public FilterRequestWrapper(final HttpServletRequest request, final
GenericPrincipal principal) {
        super(request);
        this.principal = principal;
    }

    @Override
    public Principal getUserPrincipal() {
        return principal;
    }

    @Override
    public boolean isUserInRole(final String role) {
        if (principal != null) {
            return principal.hasRole(role);
        }
        return super.isUserInRole(role);
    }
}
```

Create a custom filter. The filter will create a new Principal which includes both the credentials and the groups/roles for the user.

In this example, the class <code>GenericPrincipal</code> contains username, password, and groups. Panopticon Real Time is only able to extract the groups from <code>GenericPrincipal</code> class or the <code>MemoryUser</code> class. Both the Principal and the original HTTP request will be wrapped in an instance of <code>FilterRequestWrapper</code>. The wrapper will then be forwarded towards Panopticon Real Time.

```
import org.apache.catalina.realm.GenericPrincipal;
import org.apache.catalina.users.MemoryUser;
import javax.servlet.*;
import javax.servlet.http.HttpServletRequest;
import javax.servlet.http.HttpServletResponse;
import java.io.IOException;
import java.security.Principal;
import java.util.Arrays;
import java.util.List;
public class ExampleFilter implements Filter{
    @Override
   public void init(FilterConfig filterConfig) throws ServletException {}
   @Override
   public void doFilter(final ServletRequest servletRequest, final ServletResponse
servletResponse, FilterChain filterChain) throws IOException, ServletException {
       if (!(servletRequest instanceof HttpServletRequest || !(servletRequest
instanceof HttpServletResponse))) {
            return;
        }
        final HttpServletRequest request = (HttpServletRequest) servletRequest;
        final HttpServletResponse response = (HttpServletResponse) servletResponse;
        final String username = "username";
        final String password = "password";
        final List<String> groups = Arrays.asList("Group1", "Group2");
        final GenericPrincipal principal = new GenericPrincipal (username, password,
        filterChain.doFilter(new FilterRequestWrapper(request, principal),
response);
```

```
}
@Override
public void destroy() {}
```

- 3. When these classes have been created, you can compile them and package them in a jar file.
- 4. Copy the jar file to the WEB-INF/lib folder in the panopticon war file (or the extracted folder).
- 5. Enable the filter by adding the following code to the web.xml file in panopticon WEB-INF folder:

```
<filter>
     <filter-name>ExampleFilter</filter-name>
     <filter-class>com.datawatch.server.filter.ExampleFilter</filter-class>
</filter>
<filter-mapping>
     <filter-name>ExampleFilter</filter-name>
        <url-pattern>/*</url-pattern>
</filter-mapping></filter-mapping>
```

HEADER

It is possible to use a web-facing Panopticon Real Time behind a proxy server that will handle the authentication of users. The proxy server forwards the name of the user and roles to Panopticon Real Time as HTTP headers for every request.

For requests where headers are blank or missing, they are treated like anonymous requests while requests where the user HTTP header are valid are treated like authenticated requests with that specific username.

Requests from the proxy server are fully trusted and checks are no longer performed at Panopticon Real Time about the validity of the username. The authorization on workbooks and administration will work as usual.

To activate the Header authentication, add or update the following properties in the Panopticon.properties file:

```
authentication.type=HEADER
authentication.header.role.delimiter=,
authentication.header.roles={roles header}
authentication.header.rolesdynamic={dynamic roles header}
authentication.header.username={userid header}

For example:
authentication.type=HEADER
authentication.header.role.delimiter=,
authentication.header.roles=X-Roles,X-Company
authentication.header.rolesdynamic=watcher,role for {X-Company}
```

authentication.header.username=X-User

[4] TOMCAT SECURITY CONFIGURATION

Any Apache Tomcat server used in production must be properly configured to meet the security requirements of your organization. This section describes security configuration options that should be covered before any security scan or penetration test is performed.

The first step in vulnerability mitigation is to always install the latest release version of Apache Tomcat 9.

REPLACING PARAMETER VALUES WITH HTTP HEADERS AND COOKIES

Panopticon Real Time can be configured to replace both the incoming and outgoing parameters with HTTP headers and cookies:

- Incoming Parameters are parameters sent to Panopticon Real Time when requesting data. These types of parameters are also referred to as request parameters.
- Outgoing Parameters are parameters which are returned to the Client when retrieving a workbook. These types of parameters are also referred to as response parameters.

This feature is used for employing the user identifier as a parameter and sending the user identifier as a *Header* and *Cookie*. The Server Administrator can configure these properties so that the incoming parameters employ the user identifier value when requesting data. Consequently, the requested HTTP *Header* and *Cookie* values will be tailored for each user. The Server Administrator can also update these properties so that the outgoing parameters get updated when loading a workbook. For example, if you want the user's identifier to be shown in the workbook as a Title.

Replacing the parameter values with Header and Cookie values is achieved by configuring certain properties in the Panopticon.properties file located in the Appdata folder or C:\vizserverdata).

Updating incoming parameters can be achieved by configuring the following properties:

Property	Request parameter mapping
Attribute	request.cookie.parameters.mapping.required
Description	The parameters that are required to be updated with certain cookie values. This property will only affect incoming parameters. The operation will fail if configured cookie values are not present in the request. The property should be formatted as follows: Parameter name (Value delimiter) Cookie name.
Default Value	
Property	Request parameter mapping
Attribute	request.cookie.parameters.mapping.optional
Description	The parameters that could be updated with certain cookie values. This property will only affect incoming parameters. The operation will not fail if the cookie values are not present in the request. The parameters will keep

	their default value instead of the configured cookie value if the cookie is not present. The property should be formatted as follows: Parameter name (Value delimiter) Cookie name.
Default Value	
Property	Request parameter mapping
Attribute	request.cookie.parameters.mapping.entry.delimiter
Description	The delimiter that separates the configuration entries. This property will only affect incoming parameters.
Default Value	, (Comma)
Property	Request parameter mapping
Attribute	request.cookie.parameters.mapping.value.delimiter
Description	The delimiter that separates the parameter name and the cookie name. This property will only affect incoming parameters.
Default Value	: (Colon)
Property	Request parameter mapping
Attribute	request.header.parameters.mapping.required
Description	The parameters that are required to be updated with certain header values. This property will only affect incoming parameters. The operation will fail if a configured header values are not present in the request. The property should be formatted as follows: Parameter name (Value delimiter) Header name.
Default Value	
Property	Request parameter mapping
Attribute	request.header.parameters.mapping.optional
Description	The parameters that could be updated with certain header values. This property will only affect incoming parameters. The operation will not fail if the header values are not present in the request. The parameters will keep their default value instead of the configured header value if the header is not present. The property should be formatted as follows: Parameter name (Value delimiter) Header name.
Default Value	
Property	Request parameter mapping
Attribute	request.header.parameters.mapping.entry.delimiter
Description	The delimiter that separates the configuration entries. This property will only affect incoming parameters.
Default Value	, (Comma)
Property	Request parameter mapping
Attribute	request.header.parameters.mapping.value.delimiter
Description	The delimiter that separates the parameter name and the header name. This property will only affect incoming parameters.
Default Value	: (Colon)

The following properties can be configured to update outgoing parameters:

Property	Response parameter mapping
Attribute	response.operation.parameters.mapping.required
Description	The parameters that are required to be updated with certain Header values. This property will only affect outgoing parameters. The operation will fail if configured Header values are not present in the request. The property should be formatted as follows: Parameter name (Value delimiter) Header name.
Default Value	
Property	Response parameter mapping
Attribute	response.operation.parameters.mapping.optional
Description	The parameters that could be updated with certain Header values. This property will only affect outgoing parameters. The operation will not fail if the Header values are not present in the request. The parameters will keep their default value instead of the configured Header value if the Header is not present. The property should be formatted as follows: Parameter name (Value delimiter) Header name.
Default Value	
Property	Response parameter mapping
Attribute	response.operation.parameters.mapping.entry.delimiter
Description	The delimiter that separates the configuration entries. This property will only affect outgoing parameters.
Default Value	, (Comma)
Property	Response parameter mapping
Attribute	response.operation.parameters.mapping.value.delimiter
Description	The delimiter that separates the parameter name and the Header name. This property will only affect incoming parameters.
Default Value	: (Colon)

Example

This section describes how incoming parameters are replaced with Header values. For example, Panopticon Real Time is required to update parameters **uid** and **uname**.

Parameter Name	Update With Header
uid	userIDHeader
uname	userNameHeader

The request will fail if the required *Headers* are not present in the incoming request.

For the next example, Panopticon Real Time will try to update the parameter **ulocation** with **userLocationHeader** header. The parameter value will only be updated if the Header is available.

In both configurations, comma was used as an entry delimiter and colon as a delimiter between the parameter name and the Header name.

However, for outgoing parameters, the property prefix (request) must be changed to **response** instead.

Configurations:

request.header.parameters.mapping.required=uid:userIdHeader,uname:userNameHeader

request.header.parameters.mapping.optional=ulocation:userLocationHeader request.header.parameters.mapping.entry.delimiter=, request.header.parameters.mapping.value.delimiter=:

NOTE

Mapping the same parameter in both the header and cookie will throw an exception on initialize.

CONFIGURING HTTP HEADER SECURITY FILTER

HTTP Header Security Filter settings are part of the Apache Tomcat configuration and by default, the HTTP Header Security Filter is disabled.

In some cases, it is necessary to prevent the possibility of Panopticon being loaded inside an iframe of a web page that is running on a different server. If a web application can be loaded in any iframe, it can become a target of a clickjacking attack. A web application that allows loading into an iframe is said to give a frameable response. The HTTP Header Security Filter can also be used for enabling HTTP Strict Transport Security and Cross-Site Scripting protection.

To enable a HTTP Header Security Filter in Apache Tomcat, select one of the following:

- ☐ To create a filter that applies to all web applications running on the same Tomcat server, configure the filter in the file \$CATALINA BASE/conf/web.xml.
- To create a filter that applies to Panopticon only, configure the filter in the file \$CATALINA_BASE/webapps/panopticon/WEB-INF/web.xml.

Apache Tomcat 9.0 documentation is available on https://tomcat.apache.org/tomcat-9.0-doc/config/filter.html#HTTP Header Security Filter.

The filter class name is org.apache.catalina.filters.HttpHeaderSecurityFilter and in the default \$CATALINA_BASE/conf/web.xml, you will find a commented-out filter of this kind by searching for that filter class name. It has a filter-name which is httpHeaderSecurity.

In addition to the filter configuration, mapping must also be enabled for the filter. The default \$CATALINA_BASE/conf/web.xml contains a commented-out filter mapping for the filter-name httpHeaderSecurity.

NOTE

- The filter and the filter mapping must match by the **filter-name**.
- Filter mapping comes after the filter definition.
- By simply de-commenting the filter named httpHeaderSecurity and the filter mapping for the same filter-name, and then restarting Tomcat, you will enable a HTTP Header Security Filter where:
 - o The parameter hstsEnabled is applied with a default value true.
 - The parameter hstsMaxAgeSeconds is applied with a default value 0.
 - The parameter hstsIncludeSubDomains is applied with a default value false.
 - o The parameter hstsPreload is applied with a default value false.
 - The parameter antiClickJackingEnabled is applied with a default value true.
 - The parameter antiClickJackingOption is applied with a default value DENY.
 - o The parameter blockContentTypeSniffingEnabled is applied with a default value true.
 - The parameter xssProtectionEnabled is applied with a default value true.
 - o The filter-mapping applies to all URLs on the server.

DISABLING SPECIFIC HTTP METHODS

For security reasons, you may want to disable or restrict one or several HTTP request methods on your Apache Tomcat server. A method which is often restricted is the HTTP OPTIONS request method. This is because a HTTP OPTIONS request can sometimes expose internal server configuration details and reveal vulnerabilities.

The HTTP OPTIONS method of course has a legitimate purpose, besides any abuse for malicious purposes. Browsers send an HTTP OPTIONS request to find out the supported HTTP methods and other options supported by the server before sending the actual request.

To restrict HTTP methods, such as **OPTIONS**, add a <security-constraints> element inside <tomcat>/conf/web.xml. Below is an example where the methods **OPTIONS** and **DELETE** are disabled. The tag <auth-constraint/> in the example means that no role can access the specified methods and the methods are completely disallowed.

PREVENTING CACHEABLE HTTP RESPONSE

Browsers may store a local cached copy of content received from web servers. Cached content could be retrieved by other users of the same computer later, and this could be a problem if the content contains sensitive information. A web server – or a specific web application on a server - can be configured to give directives to browsers to not store local cache copies of response content.

In Tomcat, you can control client-side caching by creating a filter of the type **ExpiresFilter**, which is a Java Servlet API port of Apache Module **mod_expires**. This filter controls the setting of the following properties in server responses:

Expires HTTP header	TTP header
---------------------	------------

Cache-Control: max-age HTTP header

The expiration date can be set relative to either the time the source file was last modified, or to the time of the client access. The Cache-Control header turns on client-side caching and sets the max-age of a resource before it is expired. The Expires header is used to specify a specific point in time the resource is no longer valid. In practice, when both the Expires header and the Cache-Control: max-age header are set, the max-age will take precedence.

An ExpiresFilter in Tomcat is created in the configuration file web.xml to do the following:

- ☐ Create a filter that applies to all web applications running on the same Tomcat server, you configure the filter in the file \$CATALINA BASE/conf/web.xml.
- □ Create a filter that applies to Panopticon only, you configure the filter in the file \$CATALINA_BASE/webapps/panopticon/WEB-INF/web.xml.

The Apache Tomcat 9 documentation on https://tomcat.apache.org/tomcat-9.0-doc/config/filter.html#Expires Filter has some examples of how such a filter could be constructed. In addition to the filter definition, there must also be a filter-mapping. The Tomcat documentation has examples of this as well.

In addition to the Apache Tomcat documentation examples, here is another one that shows how a filter can be constructed, which makes any content not specified explicitly to expire immediately:

```
<filter>
  <filter-name>ExpiresFilter</filter-name>
  <filter-class>org.apache.catalina.filters.ExpiresFilter</filter-class>
  <init-param>
    <!-- specific content type expiry rules go here -->
  </init-param>
  <!-- Let everything else expire immediately -->
    <param-name>ExpiresDefault</param-name>
    <param-value>access plus 0 seconds</param-value>
  </init-param>
</filter>
<filter-mapping>
  <filter-name>ExpiresFilter</filter-name>
  <url-pattern>/*</url-pattern>
  <dispatcher>REQUEST</dispatcher>
</filter-mapping>
```

NOTE

The filter-mapping comes after the filter definition.

Additional Cache-Control Directives

There are additional instructions about caching that can be given from the server to the client, through directives of the Cache-Control header. Here are some examples:

- Cache-Control: public means resources can be cached by any intermediate proxies along the way between server and end-client.
- Cache-Control: private means resources can only be cached by the end-client.
- □ Cache-Control: no-cache means that the resource may indeed be cached, but it is an instruction to the client that it must revalidate with the server every time before using a cached version of the resource.
- Cache-Control: no-store means that the client is now allowed to cache any resource. The resource must be requested, and a full response downloaded, from the server each time. This is a directive commonly used with sensitive data

Legacy HTTP Header Pragma

Pragma is the HTTP/1.0 implementation and cache-control is the HTTP/1.1 implementation (since 1999) of the same concept. They both are meant to prevent the client from caching the response. Older clients may not support HTTP/1.1 which is why that header is still in use. Pragma is a legacy of HTTP/1.0 and hasn't been needed since Internet Explorer 5, or Netscape 4.7.

Creating a Custom filter for Cache-control with Tomcat

To use Cache-Control directives in the Cache-Control header with Tomcat, you must write a custom filter. Below is an example of such a filter. It also sets the Expires header to a time in the past, assuring that any cached content is immediately expired. It also sets the legacy HTTP 1.0 Pragma header.

```
import javax.servlet.*;
import javax.servlet.http.HttpServletResponse;
public class CacheControlFilter implements Filter {
    @Override
    public void init(FilterConfig filterConfig) throws ServletException {
    @Override
    public void destroy() {
    public void doFilter(ServletRequest request, ServletResponse response,
                         FilterChain chain) throws java.io.IOException,
ServletException {
        HttpServletResponse resp = (HttpServletResponse) response;
        resp.setHeader("Expires", "Tue, 03 Jul 2001 06:00:00 GMT");
        resp.setDateHeader("Last-Modified", new java.util.Date().getTime());
        resp.setHeader("Cache-Control", "no-store, no-cache, must-revalidate,
max-age=0, post-check=0, pre-check=0");
        resp.setHeader("Pragma", "no-cache");
        chain.doFilter(request, response);
```

Copy the filter code to a file named CacheControlFilter.java, compile and package using the commands below:

```
javac -cp /tomcat/lib/servlet-api.jar CacheControlFilter.java
jar cf CacheControlFilter.jar CacheControlFilter.class
```

Place the .jar file in \$CATALINA_BASE/lib/

The filter is enabled by adding the below in <tomcat>/conf/web.xml:

[5] ADDITIONAL OR OPTIONAL STEPS

FILE UPLOAD SIZE LIMITS SETTINGS IN TOMCAT AND PANOPTICON

Starting with version 2020.0 and the introduction of web authoring, any connection to a file data source involves uploading the file first to the server then loading its data into Panopticon. The upload happens as part of using the data connector for the file.

Setting the limit of the file upload sizes are done in the following properties:

□ maxSwallowSize

This setting is part of the overall Tomcat configuration, particularly for the HTTP connector, and is found in the <tomcat>/conf/server.xml file.

maxSwallowSize controls how much data Tomcat will accept for upload before it is cancelled or terminated. If the file size is larger than the file.upload.size.max.bytes, and the limit of maxSwallowSize is hit, then Panopticon will never get a chance to send a proper error message about the file being too large. The upload will simply be terminated with a message about an unknown error. It is therefore recommended to set the maxSwallowSize value high enough to the file size that Panopticon users are expected to load.

Any minus value (e.g., -1), means unlimited. Setting a minus value for maxSwallowSize creates a risk of getting the Tomcat connection saturated by a very large file upload or being stuck in an infinite file upload. A reasonable setting would be something between one to two times of the Panopticon file.upload.size.max.bytes property value.

Example:

file.upload.size.max.bytes

This property is part of the Panopticon specific settings found in the $\underline{Panopticon.properties}$ file in the $\underline{PanopticonAppdata}$ folder (i.e., C:\vizserverdata).

This size limit property (in bytes) controls how large are the files Panopticon will accept to connect to for loading data.

If the file exceeds the size limit, there will be an informative error message that indicates the current size limit. The size limit check can only take place on the condition that the file has already been successfully uploaded to the server. The upload success depends on the limit set in maxSwallowSize.

TOMCAT MEMORY CONFIGURATION FOR LINUX

NOTE

It is recommended to increase the Java heap size of Tomcat to avoid the initiation of garbage collection when memory usage hits the set threshold.

The steps may vary depending on how Tomcat was deployed.

Steps:

- 1. Stop Tomcat.
- 2. Create a file named setenv.sh.
- 3. Place the file in the Tomcat bin folder.
- 4. Set the minimum and maximum heap size with the JVM -Xms and -Xmx parameters. A minimum of 1 GB is recommended. For example:

JAVA_OPTS="\$JAVA_OPTS -Dfile.encoding=UTF-8 -server -Xms512m -Xmx2g"

NOTE

Setting the maximum value should be dependent on your system. Ensure that the heap size is not larger than the available free RAM on your system. It is recommended to use 80% of the available RAM not taken by the operating system or other processes of your JVM.

- 5. Save the file.
- 6. Restart Tomcat to apply the increase in the heap.

TOMCAT MEMORY CONFIGURATION FOR WINDOWS

NOTE

It is recommended to increase the Java heap size of Tomcat to avoid the initiation of garbage collection when memory usage hits the set threshold.

Steps:

- 1. Stop Tomcat.
- 2. Create a file named setenv.bat.
- 3. Place the file in the Tomcat bin folder.
- 4. Set the minimum and maximum heap size with the JVM -Xms and -Xmx parameters. A minimum of 1 GB is recommended. For example:

set JAVA OPTS=%JAVA OPTS% -Dfile.encoding=UTF-8 -server -Xms512m -Xmx2g

NOTE


Setting the maximum value should be dependent on your system. Ensure that the heap size is not larger than the available free RAM on your system. It is recommended to use 80% of the available RAM not taken by the operating system or other processes of your JVM.

- 5. Save the file.
- 6. Restart Tomcat to apply the increase in the heap.

SET CLIENT AUTOMATIC RECONNECTION TO THE SERVER WHEN DISCONNECTED

When the client loses connection to the server, by default, it will no longer attempt to automatically reconnect to the server.

A notification message displays such as below. Clicking the Reconnect link will attempt to reconnect to the server.



The AppData folder of Panopticon Real Time has a subfolder named JavaScriptConfiguration which contains the file named workbook.json.

Below is an example default content of a \JavaScriptConfiguration\workbook.json file:

```
"baseUrl" : "..",
  "forceClientSelectionHandling" : true,
  "startUrl" : "../",
  "subscriptionCompression" : true,
  "dataLoading" : {
     "transport" : "websocket"
  },
  "webGlEnabled" : true,
  "pdfMultiplePagesEnabled" : true
}
```


To set automatic reconnection to the server, add the following parameter in the JavaScriptConfiguration\workbook.json file:

"automaticReconnectOnServerDisconnect" : true,

NOTE

After each change in the workbook.json file, the Panopticon application must be restarted.

A notification message is displayed below. Connection to server lost: attempting to reconnect...



AUTOMATIC LOGOUT OF USERS ON TIMEOUT TO SAVE UNUSED LICENSES

Users who have no activity and leave their browsers open may be logged out and their license units are checked out by setting the following properties in the Panopticon.properties file:

Property	Timeout Session
Attribute	timeout.session.enabled
Description	Boolean value stating if timeout functionality should be used or not.
Default Value	false
Property	Timeout Session
Attribute	timeout.session.exception.delimiter
Description	The delimiter to use for the usernames stated in the timeout.session.exception.usernames property.
Default Value	, (comma)
Property	Timeout Session
Attribute	timeout.session.exception.usernames
Description	Usernames that should be excluded from the timeout functionality. Separated by the delimiter stated in the timeout.session.exception.delimiter property.
Default Value	
Property	Timeout Session
Attribute	timeout.session.minutes
Description	Minutes of inactivity before a user session is terminated by logging out the user.
Default Value	480
Property	Timeout Session
Attribute	timeout.session.notification.minutes
Description	Minutes before a timeout that a notification about session timeout is sent to the user.
Default Value	1

NOTE

- The timeout functionality is only enabled if property timeout.session.enabled is set to true.
- Each time a user actively interacts with the server, the timeout timer for that user is reset. Just sitting idle on a tab in the UI or having a dashboard open will not

reset the timer.

• If timeout.session.notification.minutes has been set to a value > 0, a notification will be sent to the user on an established notification subscription on the websocket, X minutes before the timeout happens. This is the format of the timeout notification:

```
{"TimeoutNotification":{"minutesUntilTimeout":1}}
```

 When a session times out, a logout notification will be sent on an established notification subscription on the WebSocket. This is the format of the logout notification:

```
{"LogoutNotification":{"reason":"Logged out due to session timeout"}}
```

 To abort a session timeout, all that is required is that the user interacts with the server. To facilitate the process there is a new service that can be called using GET on URL /rest/user/timeout/reset that will reset the timeout for the calling user. The service itself does not do anything, but the layers the message interacts with before reaching the service will count it as a user activity and resets the timeout.

SETTING THE TRANSPORTATION PROTOCOL

In previous versions, you can control which transportation protocol the browser would use for subscriptions to the server by setting the value (WEBSOCKET or LONG_POLLING) in the client.data.load.transport property in the Panopticon.properties file.

Starting with version 2020.2, you can instead edit the workbook.json and admin.json in <appdata>/JavaScriptConfiguration/, where you add the section:

```
"dataLoading" : {
    "transport" : "websocket" or "long-polling"
}
```

NOTE

After each change in the workbook.json and admin.json files, the Panopticon application must be restarted.

PANOPTICON REAL TIME CONFIGURATIONS FOR EMAIL SEND OUTS AND ALERTS

NOTE

When triggering email send out via the REST API, scheduling email send outs, or sending email alerts, Panopticon Real Time needs to be configured with valid email server information.

The following values need to be configured in the Panopticon.properties file located in the AppData folder (e.g., C:\vizserverdata):

Attribute	Description
email.address	Email address where the alert will be sent from.
email.host	Host name used by the email server.
email.password	Email password, if available. NOTE: When using a Gmail account, you must use an app password to authenticate with the Gmail SMTP server. See Sign in with app passwords for more information.
email.port	Port number used by the email server.
email.security.mode	Security mode used when sending emails. Possible values: NONE , SSL , TLS . The value NONE will be used if there was no value configured for the property.
email.username	Email account username.

FONT INSTALLATION REQUIREMENT FOR PDFS AND IMAGE EXPORT WITH CJK CHARACTERS

When creating PDF reports or exporting images from workbooks that contain text in Chinese, Japanese or Korean (CJK), a font with CJK support is required. The font must be installed on the server operating system. Refer to your operating system documentation on how to install a new font.

The PDF and image export functionalities in Panopticon will use the font specified in the workbook <u>Theme</u>. While used in the browser, the workbooks and dashboards will get the suitable font by the browser if a font with CJK support is needed.

When creating a PDF or an image, the browser is not involved since it happens on the server-side, and correct characters depend on the availability of a font with CJK support on the local system of the server, plus the specification of that font (e.g., **Yu Gothic**), in the workbook Theme. For the list of CJK-supporting fonts, you may refer to https://en.wikipedia.org/wiki/List_of_CJK fonts.

SETTING SERVER PROPERTIES THROUGH THE ENVIRONMENT VARIABLES

Server properties set in the <u>Panopticon.properties</u> file in the <u>AppData</u> folder (i.e., C:\vizserverdata) are overridden by environment variables.

For example, you can supply a JSON object through the environment variable SPRING_APPLICATION_JSON that will be parsed during server start up:

NOTE

Ensure that you minify the JSON object before setting the environment variable.

This will override and set the following property values:

```
server.id=Test_Server
subscription.data.loading.pool.max.size=5
subscription.broadcasting.pool.max.size=6
```

As seen from the example above, you can use inline JSON annotations for properties that share the same prefix, which in this case is **subscription**.

To override a single property, create an environment variable with the same name, but replace each '.' with an '_' and use upper case.

Example: Override the property server.id
Name: SERVER_ID
Value: <some value>

You can also override individual properties with environment variables. Just set a variable with the same name as the property but with all letters in upper case and periods replaced with underscores. For example, **REPOSITORY STARTUP IMPORT PATHS** will override the repository.startup.import.paths in

Panopticon.properties.

[6] ADVANCED SERVER DEPLOYMENTS

USAGE IN SSL ENABLED ENVIRONMENTS

Enabling SSL for Panopticon Real Time

The steps shown in this guide use the keytool and OpenSSL commands for managing keystores and certificates. The keytool command is part of the Java distribution and can be found in <code>JAVA_HOME\bin</code>. Make sure you have the <code>JAVA_HOME\bin</code> folder in your <code>PATH</code> environment variable to run the command.

Details on the keytool command can be found here:

https://docs.oracle.com/javase/8/docs/technotes/tools/unix/keytool.html

Details on the OpenSSL command can be found here:

https://www.openssl.org/docs/manmaster/man1/openssl.html

Follow the steps below to configure SSL for Panopticon Real Time using JKS/PKCS12 formats. For using the PEM formats directly inside Connector, please refer to the Apache Tomcat SSL document link at the end of this section.

Steps:

1. Change directory to the CATALINA_HOME\conf folder, which is where we want to generate the Tomcat keystore.

Do one from the following options:

Option 1. If you don't have a certificate and private key file

NOTE

Java is strict when validating the certificate of a host.

If the domain name store in the certificate does not match the domain of the server, the connection will be rejected. Enter the target domain name (www.mydomain.com) when keytool asks for "your first and last name", when running this command.

Create a keystore file to store the private key and self-signed certificate used to identify the server:

keytool -genkey -alias myalias -keyalg RSA -keystore keystore.jks

Option 2. If you already have a certificate and private key

NOTE

You may need to have Administrator rights to run this command.

```
openssl pkcs12 -export -name cast -in [certname].cer -inkey [certname].key -out keystore.jks
```

If the above OpenSSL command gives an "Unable to load certificate" error, the certificate may be in binary format. Then use the below two commands, to generate the JKS file.

```
openssl x509 -inform DER -in [certname].cer -out [certname].crt openssl pkcs12 -export -name cast -in [certname].crt -inkey [certname].key -out keystore.jks
```

2. Add an SSL HTTP/1.1 Connector entry in \$CATALINA_BASE/conf/server.xml

NOTE

The keystorepass should be the password you used while creating the keystore in Step 1.

- 3. Disable HTTP ports.
 - a. If you don't want to allow plain HTTP protocol, disable unencrypted server access by commenting out the default HTTP connector for port 8080.

```
<!--
<Connector port="8080" protocol="HTTP/1.1"
connectionTimeout="20000"
redirectPort="8443" />
-->
```

b. If you want to redirect all HTTP traffic to HTTPS.

Then add a security constraint entry in \$CATALINA BASE/conf/web.xml.

4. After completing the configuration changes, you must restart Tomcat. When the process is back up you should be able to connect over SSL using the URL below:

```
https://localhost:8443/panopticon
```

Details on how to configure Apache Tomcat SSL can be found at:

https://tomcat.apache.org/tomcat-9.0-doc/ssl-howto.html

Defining a TrustStore

In scenarios that require TLS-enabled intra-service communication, we need to configure a trustStore. These scenarios include, for instance, LDAP, SAML or OAuth integration.

A trustStore is essentially a keyStore, but where the keyStore is used to store private keys used to identify the server, the trustStore is used to store public keys of trusted *Certificate Authorities* (CA). The trustStore is used to verify certificates presented to the server when establishing an SSL connection.

Follow the steps below to create a new trustStore, import a certificate and configure Java to use the new trustStore:

Steps:

1. Create a new keyStore called **truststore**:

```
keytool -genkey -alias truststore -keyalg RSA -keystore
truststore.jks
```

2. Export a certificate from a keyStore:

```
keytool -export -keystore keystore.jks -alias myalias -file [certname].cer
```

3. Import the certificate into the trustStore:

```
keytool -import -trustcacerts -alias myalias -file [certname].cer -keystore
truststore.jks
```

You can also re-use a keyStore as a trustStore in which case the certificate does not need to be exported and imported.

To configure a trustStore for Apache Tomcat you need to edit the JAVA_OPTS environment variable in the setenv script, located in the Tomcat conf folder.

On Windows, setenv.bat:

```
set JAVA_OPTS=-Djavax.net.ssl.trustStore="C:/location/to/truststore
/truststore.jks"
```

On Linux, setenv.sh:

export JAVA_OPTS="\$JAVA_OPTS Djavax.net.ssl.trustStore='/location/to/truststore/truststore.jks'";

[7] AUTHORIZATION

NOTE

Starting with version 2020.0, mapping of administrators through Administrators.txt and AdministratorGroups.txt is no longer supported. The property access.administrator.groups should be used instead.

If the customer's authentication method relied to the use of the Administrators.txt or AdministratorGroups.txt file, they can still do so by additionally using the tomcat-users.xml to replicate the usage of these administrator text files.

For example, in the tomcat-users.xml, they can assign groups from the administrator text files to specific users like this:

```
<user username="admin" password="admin" roles="role1,otherRole"/>
<user username="admin2" password="admin2" roles="role2"/>
```

Then in the <u>Panopticon.properties</u> file, use the access.administrator.groups property to map the admins (i.e., admin and admin2) to the administrator groups by adding their roles:access.administrator.groups=role1, role2

SECURE ACCESS

Panopticon workbooks published to the folders or subfolders in Panopticon Real Time can be secured by granting allowed or denied permissions.

NOTE

Beginning with version 16.1.0, new workbooks must be published to a folder or subfolder to use their access restrictions.

However, workbook access restriction is still available and supported on older workbooks that will be accessed in the current and later Panopticon Real Time versions.

Creating Folders

A user with an Administrator or Designer role can create folders.

NOTE


Users that log on with a Designer role will have their own personal folder created and displayed on the Workbooks page (e.g., ~designer).

The personal folders:


- Are displayed and can be accessed for users with an Administrator or Designer role.
- Are where Designers can create workbooks and build dashboards. For more information, refer to <u>Altair Panopticon Web Authoring Guide</u> on how to create workbooks on the Web client.

Steps:

1. On the **Workbooks** tab, right-click on the topmost folder, and select **New Folder**.




The Create Folder dialog displays.



- 2. Enter the Folder Name.
- 3. Proceed to defining the Authorization to <u>Allowed</u> or <u>Denied</u> groups and users.

4. Click Create

The new folder is displayed on the expanded Folder hierarchy list and on the Root Folder list.




Adding Groups and Users with Allowed Authorization


A user with an Administrator or Designer role can grant permissions for users or groups to a workbook folder or subfolder.

Steps:

1. Right-click on a folder (except the root folder) and select **Permissions** in the context menu.



The Permissions dialog displays.



2. Under the *Allowed* section, click the **Add** icon.

A new User/Group Allowed section is displayed.



3. Select **User** or **Group** to be given permission in the drop-down list.




- 4. Enter the user or group *Name*.
- 5. Select the permission level that will be granted to the user or group:
 - READ
 Permission to read the folder.
 - READ + WRITE

Permission to write to the folder and read.


MODIFY + WRITE + READ

Permission to read, modify, and write to the folder as well as create subfolders.




7. You can either:

check the Apply Permissions to Subfolders box



This means the permissions that will be used on all of the subfolders will be fetched from the root folder.



 leave the Apply Permissions to Subfolders box unchecked and modify the permission properties of the subfolders 8. Click Update to save the changes.


NOTE

You can copy the usernames in the *Permissions* dialog by highlighting the text then right-clicking and selecting **Copy** in the context menu.

Adding Groups and Users with Denied Access

Steps:

1. Right-click on a folder and select **Permissions** on the context menu.



The Permissions dialog displays.



2. Under the *Denied* section, click the **Add** icon.

A new User/Group Denied section is displayed.



- 3. Select User or Group that will be given denied permission in the drop-down list.
- 4. Enter the user or group Name.
- 5. Select the denied permission level that will be granted to the user or group:
 - MODIFY

Prevent user or group to modify and create subfolders.

WRITE + MODIFY

Prevent user or group to modify and write to the folder.

READ + WRITE + MODIFY

Prevent user or group to modify and create subfolders, modify and write to the folder, as well as read the folder.



6. Click . The user or group is added under the *Denied* list.




Repeat until all of the users with denied access are added.

7. Click to save the changes.


Creating Subfolders

Steps:

- 1. To create subfolders, you can either click a folder:
 - On the expanded Folder hierarchy list




On the Root workbooks/folders list




The Folders page is displayed.

2. Right-click on the folder and select **New Folder**.




Refer to <u>Creating Folders</u> for the steps in creating the subfolders. Also, <u>Adding Groups and Users with Allowed Authorization</u> and <u>Adding Groups and Users with Denied Access</u> for more information on adding Users and Groups with allowed or denied authorization.


The subfolder is added.



3. You can also opt to delete a subfolder by right-clicking on the folder and selecting **Remove** on the context menu as long as it does not contain published workbooks.



A confirmation message displays.






Updating Folder or Subfolder Properties

Steps:

- 1. To update folder properties, click a folder or a subfolder.
- 2. Right-click on the folder or subfolder and select **Permissions**.




The corresponding Permissions dialog displays.



- 3. Make the necessary changes such as new folder name, add or delete users and groups.
- 4. You can either:
 - Check the Apply Permissions to Subfolders box

This means the permissions that will be used on all of the subfolders will be fetched from the root folder.

 Leave the Apply Permissions to Subfolders box unchecked and modify the permission properties of the subfolders






Downloading a Workbook

A user with an Administrator or Designer role with READ + WRITE <u>permission</u> to the folder is allowed to download a copy of a workbook available in it.

Right-click on a workbook and select **Download** on the context menu.

Workbooks



A copy of the workbook is downloaded.


Exporting Workbook or Folder Bundle

NOTE

- Data files associated with workbooks will only be included in the download if they are available inside the repository.
- Users will only be able to download workbooks from folders where they have WRITE permission.

Steps:


1. Right-click on a workbook or folder and select **Export Bundle** on the context menu.



Workbook Folder or Subfolder Context Menu

Workbook Context Menu

A notification message displays.



- 2. Check the Include Data Files box to include the associated workbook data files in the download.
- 3. Click . A copy of the workbook or folder bundle is downloaded.


Importing Workbooks Bundle

NOTE

- Users will only be able to import a bundle to folders where they have WRITE permission.
- Existing workbooks with the same name as the uploaded workbooks will be archived, only if the new workbook differs from the current one.
 Consequently, the uploaded version will be the current one.
- The bundle must not exceed the value set in the property file.upload.size.max.bytes in the Panopticon.properties.

Steps:

1. Right-click on a folder and select **Import Bundle** on the context menu.




The Import Bundle dialog displays.



- 2. To import a bundle, you can either:
 - Drag it from your desktop and drop on the dialog, or
 - Click **Choose Bundle to Import** and select one on the *Open* dialog that displays.

The name of the selected bundle is displayed on the dialog box.



3. Check the **Keep Folder Structure** box.

This means the exported folder structure is maintained when uploading the bundle. If the folders do not exist on the server, they will be created.

4. To replace an existing workbook, check the **Replace existing workbook** box.




Data Level Secure Access

In this case the data being displayed is filtered to a particular authenticated user.

Data is filtered using the special parameter _user_id.

This _user_id parameter is replaced at run time by the authenticated user id in lower case.




This parameter can then be used to restrict the data being retrieved, though use in either:

- □ Connection Details to Data Sources
- ☐ Filter constraints on data queries (e.g., SQL WHERE Clauses)

[8] SYSTEM ADMINISTRATION

Panopticon Real Time system administration is done on the following pages of the System tab:



Page	Description
System Settings	Allows to view the license and server information.
Subscriptions	Allows to view and manage real-time plugin subscriptions.

Caches	Allows to view, refresh, clear, or delete caches that are currently running on the server.
Logs	Allows to set the logging level and view logs. Also, pause or resume logging, and copy or clear logs.
Scheduler	Allows scheduling of email send outs and extracting of data.
Logged In User	Allows to view and manage logged in users.
API Tokens	Allows to add, delete, and view API Tokens.
<u>Fonts</u>	Allows to add custom fonts that can be used in a part or workbook.

SYSTEM SETTINGS


The	System	Settings r	page include	the	following	panes or	sections:
1110	Oyotoiii	OCILII IGO F	Jago II lolado	uic	IOIIOVVIIIG	parios or	occiono.

- <u>License Information</u>
- Server Information


View License Information

If the licensing used is Altair Units license, the following license information are displayed:

- License server type
- □ License version
- □ Start Date and End Date of the license
- Total number of units available in the license



If the <u>licensing</u> used is the volume-based XML file (named **PanopticonLicense.xml**), the content and location (i.e., C:\vizserverdata) of the license are displayed.



View Panopticon Real Time Information


On the System Settings page, the following server information are displayed:

Server Property	Description
Operating System	The server host operating system.
Java Version	The version of the Java Runtime Environment.
Java Vendor	The vendor of the Java Runtime Environment.
Tomcat	Identifies the Tomcat hosting the server

Tomcat Version	The Tomcat version.
Tomcat Memory (Mb)	The total amount of memory available to the Java Virtual Machine.
Max Memory (Mb)	The maximum amount of memory that the Java Virtual Machine will attempt to use.
Free Memory (mb)	The amount of free memory in the Java Virtual Machine.
Available Cores	The number of cores available to the Java Virtual Machine.
Uptime	The time when Panopticon Real Time was last started.

VIEW PLUGIN SUBSCRIPTIONS

View all of the currently running real-time plugin subscriptions.




Including the following information:

- Data source with an installed plugin
- Workbook name
- Data table name
- Current size of the real-time table held by the plugin such as number of rows, columns, and time slices

For subscriptions created by ad hoc services, or those with no owner (workbook reference), they can be viewed on the *Preview Subscriptions* section.


You can also opt to do any of the following:

□ Click Cancel All to cancel all of the subscriptions on the Subscriptions section.



□ Cancel a plugin subscription by clicking ×

A notification message displays.






Move to other pages

WORKING WITH CACHES

On the Caches page, you can view, refresh, or delete caches that are currently running on the server.




The Caches list includes the following information:

Cache rendering type
Workbook Name
Data Table Title
Data Source Name
Read Count
Cell Count
Cache Age
Time to Live (Expires In)
Response Length


You can also do the following:

- □ Display Data Table Cache
- Display Data Source Cache
- Display Query Cache


Select a Cache Type to display in the list.




Data Table Cache Type



Data Source Cache Type



Query Cache Type




Refresh page



Delete individual caches

Select the checkbox of a cache or several caches, then click Delete. A notification displays.





■ Move to other pages

VIEW LOGS


View the latest 300 rows of a Logging Level in the Logs tab:

- FINEST (lowest level)
- ☐ FINER
- □ FINE
- CONFIG
- INFO (default level)
- WARNING

SEVERE (highest level)


Steps:


1. On the System page, click the Logs tab. Initially, the default level (INFO) logs are displayed.



2. Select another Logging Level in the drop-down.

For example, FINEST.






The latest 1000 rows of the selected log level or higher are fetched.


- 3. You can also click any of the following buttons:
 - to pause the logging, it changes to
 - to resume the logging
 - to copy log to clipboard
 - to clear the logs

SCHEDULING TASKS

On the Scheduler tab of the System Settings page, Panopticon Real Time allows scheduling of tasks.



A new scheduled task is added in the list with the properties.




Scheduler Property	Description
1	Run Task Manually run scheduler task.
2	Upload Task Upload scheduler task.
3	New Task Create a new scheduler task.
4	Delete Task Delete a scheduler task.
5	Download Task Download a scheduler task.
6	Task Properties The task properties include: Name of the task Activated status Type of the scheduled task Trigger type: Period or CRON Last user who made an update Date/Time when the task was created Date/Time when the task was last ran Last run result: Success or Failed For failed results, you can hover on the tooltip to view the error. NOTE: The result is not displayed for Extract Data scheduler type.

+ New Task

To create a new task, click **New Task** the following tasks:

. The $\ensuremath{\textit{New Task}}$ pane displays that allows you to define



Extracting Data



To allow scheduling of email send outs, Panopticon Real Time must be configured with valid email server information in the Panopticon.properties file located in the AppData folder (e.g., C:\vizserverdata).

See Panopticon Real Time Configurations for Email Send Outs and Alerts for instructions.


If any data load fails, such as when the data source is offline, the PDF/Image generation fails as well, and an email will not be sent.

Creating Task to Clear and Import Data Table to Data Store

Allows you to clear the earlier imported data and import again to the data store.

Steps:

- 1. On the New Task pane, enter the Name of the task. Ensure the name is unique.
- Tap the Activated slider to turn it on.
- Select the Trigger. You can either select:
 - Period then enter the Interval (in seconds), or



CRON then enter a *CRON Expression* on the format:

sec mins hours dayofmonth month dayofweek (e.g., 09 02 18 ? * MON-FRI)



- Select the task *Type*: Data Store Clear and Import.
- Enter the *Description* of the task. 5.
- Select the Data Table Name that will be cleared in the data store and imported again.






Click to go back to the *Tasks* pane. A new task is added to the list.

Creating Task to Import Data Table to Data Store

Allows you to store data closer to Panopticon server in an embedded database.

Steps:

- 1. On the New Task pane, enter the Name of the task. Ensure the name is unique.
- 2. Tap the Activated slider to turn it on.
- 3. Select the Trigger. You can either select:
 - Period then enter the Interval (in seconds), or



• **CRON** then enter a *CRON Expression* on the format:

sec mins hours dayofmonth month dayofweek (e.g., 09 02 18 ? * MON-FRI)



- Select the task Type: Data Store Import Data.
- 5. Enter the Description of the task.
- 6. Select the Data Table Name that will be imported in the data store.




- Once saved, you can opt to click to manually run the task.
- Click to go back to the *Tasks* pane. A new task is added to the list.

Creating Task to Send CSV Data via Email


Panopticon Real Time provides the functionality to create tasks to generate and email CSV data from a workbook, dashboard, or visualization.

Steps:

- 1. On the New Task pane, enter the Name of the task. Ensure the name is unique.
- 2. Tap the Activated slider to turn it on.
- 3. Select the Trigger. You can either select:
 - Period then enter the Interval (in seconds), or



- 4. Select the task Type: Email CSV Data.
- 5. Enter the Description of the task.
- 6. Upon selecting Email CSV Data, the Scheduler page changes to allow specification of the following:
 - Select the Workbook Name in the drop-down list. These are the published workbooks available in the Workbooks page.
 - Select dashboards or parts where to source the CSV data from, by checking their corresponding boxes in the *Dashboards & Parts* drop-down list.



You can also opt to enter the Parameter Values that will be added as parameters to the subject line of
emails or as dashboard values in the CSV Data.

Such as Parameter=Value, and are comma separated. For example:

Region=Europe, Industry=Financials

NOTE

- See Setting Parameter Values in Scheduler Tasks for more information on the different syntax you can use to enter parameters with multiple values, as well as parameter values that contain comma.
- The following Date/Time range querying parameters are also supported in the Email CSV Data task:
 - CurrentTime
 - LastWorkDay
 - WeekStart
 - QuarterStart

For example:

{CurrentTime:dd-MMM-yyyy}

However, when there is no Date/Time format supplied, the default format yyyy-MM-dd will be used instead.

enter comma-separated list of Output File Names.

NOTE

- The items in the list must be either unique or empty.
- Empty string items indicate that the default title should be used.
- By default, the text box is blank causing the implicit naming to be used.
- If the supplied names are fewer than the selected data sets, the default naming comes into effect for non-specified names.
- 7. You can opt to tap the **Zip CSV Data** slider to attach a zipped copy of the CSV data in the email.
- 8. Enter the email address of the recipient in the *To* field.
- You can opt to enter the following:
 - the CC and/or BCC recipients of the email separated by a comma.
 - the mail message subject to be used in the email notifications in the Subject field.

NOTE

Supports dashboard parameters.

the content of the email in the Body box.




- 10. Click
 - Run Once saved, you can opt to click to manually run the task.
 - to go back to the Tasks pane. A new task is added to the list.

Creating Task to Send an MS Excel File via Email

Panopticon Real Time provides the functionality to create tasks to generate and email MS Excel files.

Steps:

- 1. On the New Task pane, enter the Name of the task. Ensure the name is unique.
- 2. Tap the Activated slider to turn it on.
- 3. Select the Trigger. You can either select:
 - Period then enter the Interval (in seconds), or



• **CRON** then enter a *CRON Expression* on the format:


sec mins hours dayofmonth month dayofweek (e.g., 09 02 18 ? * MON-FRI)



4. Select the task *Type*: **Email Excel**.

Upon selecting **Email Excel**, the *Scheduler* page changes to allow specification of the following:

- Enter the Description of the task.
- Select the Workbook Name in the drop-down list. These are the published workbooks available in the Workbooks page.
- Select the dashboards to include in the MS Excel file by checking their corresponding boxes in the Dashboards drop-down list.



- 5. You can also opt to:
 - enter the Parameter Values that will be added as parameters to the subject line of emails or as dashboard values in the MS Excel file

Such as Parameter=Value, and are comma separated. For example:

Region=Europe, Industry=Financials

NOTE

- See <u>Setting Parameter Values in Scheduler Tasks</u> for more information on the different syntax you can use to enter parameters with multiple values, as well as parameter values that contain comma.
- The following Date/Time range querying parameters are also supported in the Email CSV Data task:
 - CurrentTime
 - LastWorkDay
 - WeekStart
 - QuarterStart

For example:

{CurrentTime:dd-MMM-yyyy}

However, when there is no Date/Time format supplied, the default format yyyy-MM-dd will be used instead.

- check the Hide Scrollbars box.
- 6. Enter the Width and Height of the MS Excel file. Default values are 1024px and 768px, respectively.
- 7. Enter the Table Style. Default is TableStyleMedium4.
- 8. Enter the email address of the recipient in the To field.
- 9. You can opt to enter the following:
 - the CC and/or BCC recipients of the email separated by a comma.
 - the mail message subject to be used in the email notifications in the Subject field.

NOTE Supports dashboard parameters.

• the content of the email in the Body box.



- Once saved, you can opt to click
 Run
 to manually run the task.
- Click to go back to the Tasks pane. A new task is added to the list.

Creating Task to Send an HTML Formatted Data via Email


Panopticon Real Time provides the functionality to create tasks to generate and email HTML-formatted table exported from a selected workbook and dashboards.

IMPORTANT

Use with caution! When emailing HTML formatted data, the email message size runs the risk of becoming very large if the data used in the visualization is too large and/or complex. The data volume will not stop Panopticon Real Time from creating the message and the HTML-formatted data, but email servers may struggle to send and/or receive the message.


Steps:

- 1. On the New Task pane, enter the Name of the task. Ensure the name is unique.
- 3. Tap the Activated slider to turn it on.
- 4. Select the Trigger. You can either select:
 - Period then enter the Interval (in seconds), or



• **CRON** then enter a *CRON Expression* on the format:

sec mins hours dayofmonth month dayofweek (e.g., 09 02 18 ? * MON-FRI)



5. Select the task *Type*: Email HTML Formatted Data.

Upon selecting **Email HTML Formatted Data**, the *Scheduler* page changes to allow specification of the following:

- Enter the Description of the task.
- Select the *Workbook Name* in the drop-down list. These are the published workbooks available in the *Workbooks* page.
- Select the dashboards and parts to include in the HTML formatted data file by checking their corresponding boxes in the *Dashboards & Parts* drop-down list.
- 6. You can also opt to enter the *Parameter Values* that will be added as parameters to the subject line of emails or as dashboard values in the MS Excel file.

Such as Parameter=Value, and are comma separated. For example:

Region=Europe, Industry=Financials

NOTE

- See <u>Setting Parameter Values in Scheduler Tasks</u> for more information on the different syntax you can use to enter parameters with multiple values, as well as parameter values that contain comma.
- The following Date/Time range querying parameters are also supported in the Email CSV Data task:
 - CurrentTime
 - LastWorkDay
 - WeekStart
 - QuarterStart

For example:

{CurrentTime:dd-MMM-yyyy}

However, when there is no Date/Time format supplied, the default format yyyy-MM-dd will be used instead.

- 7. Enter the email address of the recipient in the *To* field.
- 8. You can opt to enter the following:
 - the CC and/or BCC recipients of the email separated by a comma.
 - the mail message subject to be used in the email notifications in the Subject field.

NOTE Supports dashboard parameters.

the content of the email in the Body box.




- Once saved, you can opt to click
 Run
 to manually run the task.
- Click to go back to the *Tasks* pane. A new task is added to the list.

Creating Task to Send Image File via Email

Panopticon Real Time provides the functionality to create tasks to generate and email Image files.


In addition, hyperlinks can also be used in email dashboard images. Hyperlinks can redirect to a workbook and a dashboard in the server.



See the Email Data: Image section for more information.

Steps:

- 1. On the New Task pane, enter the Name of the task. Ensure the name is unique.
- 2. Tap the Activated slider to turn it on.
- 3. Select the *Trigger*. You can either select:
 - Period then enter the Interval (in seconds), or



• **CRON** then enter a *CRON Expression* on the format:

sec mins hours dayofmonth month dayofweek (e.g., 09 02 18 ? * MON-FRI)




4. Select the task *Type*: Email Image.

Upon selecting Email Image, the Scheduler page changes to allow specification of the following:

- Enter the Description of the task.
- Select the Workbook Name in the drop-down list. These are the published workbooks available in the Workbooks page.
- Select dashboards or parts to include in the image file by checking their corresponding boxes in the Dashboards & Parts drop-down list.

Inline Image




The selected dashboards or parts are inserted as parameterized text and inline images in the Body edit box.



Clicking the **Preview** icon displays the image placeholders for the selected dashboards or parts.

Body ∅

{Candlestick_title}
{Candlestick_image}
{Cross Tab Pivot Table_visualization.Tile2_title}
{Cross Tab Pivot Table_visualization.Tile2_image}
{Cross Tab Pivot Table_visualization.Tile1_title}
{Cross Tab Pivot Table_visualization.Tile1_timage}
{Donut Gauge_visualization.DonutGauge2_title}
{Donut Gauge_visualization.DonutGauge2_image}
{Donut Gauge_visualization.DonutGauge1_title}
{Donut Gauge_visualization.DonutGauge1_image}



 Select bookmarks in the workbook to include in the image file by checking their corresponding boxes in the Bookmarks drop-down list.

5. You can also opt to:

 enter the Parameter Values that will be added as parameters to the subject line of emails or as dashboard values in the Image file

Such as Parameter=Value, and are comma separated. For example:

Region=Europe, Industry=Financials

NOTE

- See <u>Setting Parameter Values in Scheduler Tasks</u> for more information on the different syntax you can use to enter parameters with multiple values, as well as parameter values that contain comma.
- The following Date/Time range querying parameters are also supported in the Email CSV Data task:
 - CurrentTime
 - LastWorkDay
 - WeekStart
 - QuarterStart


For example:

{CurrentTime:dd-MMM-yyyy}

However, when there is no Date/Time format supplied, the default format yyyy-MM-dd will be used instead.

- enter the Width and Height of the Image file. Default values are 1024 and 768, respectively.
- check the Hide Scrollbars box.
- check the **Hyperlinks** box. This makes the Image file in the email will be clickable.
- 6. Enter the email address of the recipient in the To field.

- 7. You can opt to enter the following:
 - the CC and/or BCC recipients of the email separated by a comma.
 - the mail message subject to be used in the email notifications in the Subject field.



the content of the email in the Body box.




- - Run Once saved, you can opt to click to manually run the task.
 - Click to go back to the *Tasks* pane. A new task is added to the list.

Creating Task to Send PDF File via Email

Panopticon Real Time provides the functionality to create tasks to generate and email PDF files.

Steps:

- 2. On the New Task pane, enter the Name of the task. Ensure the name is unique.
- Tap the Activated slider to turn it on.
- Select the Trigger. You can either select:
 - Period then enter the Interval (in seconds), or



CRON then enter a *CRON Expression* on the format:

sec mins hours dayofmonth month dayofweek (e.g., 09 02 18 ? * MON-FRI)



- 5. Select the task Type: Email PDF.
- 6. Upon selecting **Email PDF**, the *Scheduler* page changes to allow specification of the following:
 - Enter the Description of the task.
 - Select the Workbook Name in the drop-down list. These are the published workbooks available on the Workbooks page.
 - Select dashboards to include in the PDF by checking their corresponding boxes in the Dashboards dropdown list.

- 7. Select bookmarks in the workbook to include in the PDF by checking their corresponding boxes in the Bookmarks drop-down list.
- 8. You can also opt to:
 - enter the Parameter Values that will be added as parameters to the subject line of emails or as dashboard values in the PDF file.

Such as Parameter=Value, and are comma separated. For example:

Region=Europe, Industry=Financials

NOTE

- See Setting Parameter Values in Scheduler Tasks for more information on the different syntax you can use to enter parameters with multiple values, as well as parameter values that contain comma.
- The following Date/Time range querying parameters are also supported in the Email CSV Data task:
 - CurrentTime
 - LastWorkDay
 - WeekStart
 - QuarterStart

For example:

{CurrentTime:dd-MMM-yyyy}

However, when there is no Date/Time format supplied, the default format yyyy-MM-dd will be used instead.

- check the Enable Pagination box.
- check the Hide Scrollbars box.
- 9. Enter the email address of the recipient in the To field.
- 10. You can opt to enter the following:
 - the CC and/or BCC recipients of the email separated by a comma.
 - the mail message subject to be used in the email notifications in the Subject field.

Supports dashboard parameters. NOTE

the content of the email in the Body box.




- Run Once saved, you can opt to click to manually run the task.
- Click to go back to the Tasks pane. A new task is added to the list.

Creating Task to Extract Data

Tasks can be created to reload workbooks or global extracts.

Steps:

- 1. On the New Task pane, enter the Name of the task. Ensure the name is unique.
- 2. Tap the Activated slider to turn it on.
- 3. Select the *Trigger*. You can either select:
 - Period then enter the Interval (in seconds), or




• **CRON** then enter a *CRON Expression* on the format:

sec mins hours dayofmonth month dayofweek (e.g., 09 02 18 ? * MON-FRI).



- 4. Select the task *Type*: Extract Data.
- 5. Enter the *Description* of the task.
- Select the data extract to be scheduled in the Extract Name drop-down list box. The list is taken from the data extracts list on the Extracts tab.



- Once saved, you can opt to click to manually run the task.
- Click to go back to the Tasks pane. A new task is added to the list.

Setting Parameter Values in Scheduler Tasks

Use any of the following syntax to define parameter values in scheduler tasks:

For multiple values (array parameter), use bracket syntax

Example: parameter1=[Value1, Value2, Value3]

☐ For a parameter with a value containing comma, quote the value in double quotes

Example: parameter1="Parameter value, containing comma"

☐ The double quoting can also be used inside arrays

Example: parameter1=[Value1, "Value2, containing comma"]

Normal parameters, quoted parameters, and array parameters can be mixed


Example: parameter1=Normal, parameter2=[Val1, Val2], parameter3="Quoted Value"

Uploading a Scheduler Task

Users with an Administrator role can upload scheduler task definitions.


Steps:

On the Scheduler tab, click Upload
 Upload




- 2. To upload a task, you can either:
 - drag it from your desktop and drop on the dialog, or
 - click Choose task to upload and select one on the Open dialog that displays.

The name of the task is displayed on the uploaded task area and in the Name box.



- 3. You can opt to rename the task.
- 4. To replace an existing task, check the Replace task box.
- 5. Click Upload

You will be notified once the task is uploaded.



The task is added and displayed in the Scheduler list.

Downloading a Scheduler Task

Users with an Administrator role can download scheduler task definitions.

Click the **Download** icon of a task.

Other Scheduler Tasks Operations

On the **Scheduler** tab of the *System Settings* page, you can also perform the following:

Sort tasks

A task displays the following columns: Name, Activated, Type, Trigger, Last Updated By, Created, and Last Run.

Modify the sorting of the list by clicking the or button of any of these columns. The icon beside the column that was used for the sorting will indicate if it was in ascending or descending order.

Manually run tasks


Instead of waiting for the set Period interval or CRON Expression, you can manually execute the task by clicking



The Last Run and Last Run Result (Success or Failed) are displayed. For failed results, you can hover on the tooltip to view the error.

- Modify tasks
- Delete tasks

Click of a task. A confirmation message displays.



Modify a Scheduled Task

Steps:

- On the **Scheduler** tab, click the link of a task to modify.
 The properties of the task are displayed.
- 2. Apply the desired changes.



MANAGING PANOPTICON REAL TIME USERS

Users with an Administrator role can view the logged in users on Panopticon Real Time and log them out when necessary. The ability to manage users is beneficial in monitoring the utilization of Altair Units license.


On the **Logged In Users** tab of the *System* page, Administrators can perform the following:

\neg	/:	loaaed	:	
	$I \square M$	IOOOO	ırı	LICATO

- Sort logged in users
- Log out users
- Refresh the Logged In Users list

Viewing Logged In Users

On the System page, click the Logged In Users tab. The list of logged in users is displayed.



In the list, the following properties are displayed for each user:

Property	Description
Username	Username used to the login to Panopticon Real Time.
Roles	Roles assigned to the user.
Login Time	The Date/Time the user logged in.
Active Sessions	The number of tokens a user is using. For example, if the user is logged in from two different computers, he will have two active sessions. However, if the user has two tabs on one computer, they will share a token and the active sessions will be one.
Designing	Indicates if a logged in user is currently designing a workbook.

Sorting Logged In Users

Sorting the logged in users can be done through the *Username*, *Login Time*, or *Active Sessions* column name.

Steps:

- 1. On the System page, click the Logged In Users tab. The list of logged in users is displayed.
- 2. Click on the Username, Login Time, or Active Sessions column header then click the Sort Order.
 - Ascending
 - Descending

Logging Out Users

Logging out users on the server consequently deletes their tokens.

Logging Out All Users

Steps:



Altair Panopticon Workbooks Data Library System Webbooks Alerts Parameters Themes System Settings Logged In Users **B** Logout all ♂ Refresh Subscriptions Username ↑ Roles **Login Time Active Sessions** Designing Caches \Box admin ANONYMOUS, Viewer, Administrator Oct 19, 2021 1:12 PM Logs \Box ANONYMOUS, Viewer, Designer Oct 19, 2021 1:11 PM Scheduler designer 1 Logged In Users API Tokens Fonts


A notification message displays.



2. Click Yes

Except for the user (i.e., admin) who is calling out the logging out of the other users, all of the other users are logged out.

Also, the button of admin is disabled.



Logging Out Individual Users

Steps:

Click the button of a user in the list.
 A notification message displays.



2. Click Yes

The user is logged out and their token is deleted.

Refreshing the Logged In Users List



MANAGING API TOKENS


On the API Tokens page, an Administrator user can add API Tokens that returns a key used for authorizing requests to the server.


Steps:

1. Click + Create . The Create an API Token dialog displays.




- 2. Enter the Label.
- 3. Click . The New API Token Created dialog displays with the auto-generated key.





- 4. Click to ensure you have a copy of the key and paste in a secure location.
- 5. Click . The new API Token is displayed on the list.




In the list, the following properties are displayed for each API Token:

Property	Description
Label	Label of the API Token. NOTE: Select a label that is easy for you to remember.
Created By	The user who created the API Token. NOTE: Only Administrator users can create API Tokens. However, the keys can be used by anyone as long as they are not revoked.
Last Accessed	Date/Time when the API Token was last accessed.

Click on any of these column headers then click the Sort Order to sort the list.


- Ascending
- Descending

You can also opt to click to remove and revoke the API Token from the server.



ADDING CUSTOM FONTS

Users with an Administrator role are allowed to add fonts on the System tab in Panopticon Real Time.



The supported custom font files include the following:


□ ttf

otf

When available on the server, the client will automatically detect and load the font and consequently, can be used in a part or workbook. Otherwise, the client will fall back to the system installed fonts.

Steps:

+ Add Fonts1. Click- The Add Fonts dialog displays.




2. To add fonts, you can either:

- drag them from your desktop and drop on the dialog, or
- click **Choose Fonts** and select one or more fonts on the *Open* dialog that displays.


The names or the number of fonts is displayed on the uploaded font area.






3. Click Upload


A notification prompt will be displayed once the fonts are uploaded.



The added custom fonts are displayed on the Fonts page.



To delete a font, click . A notification is displayed.





[9] CONNECTIVITY AND INTEGRATION

THIRD PARTY SOFTWARE DEPENDENCY INSTALLATION

Some data connectors require additional third-party software installation to be enabled which typically requires adding JAR files to the Lib folder of the Tomcat installation and then restarting Tomcat.

Common additions include:

	ID	\mathbb{R}	Dri	vers
_	ישט	\mathbf{D}	$\boldsymbol{\nu}$	VCIO

□ Advanced Message Processing System (AMPS)

The latest version for AMPS can be downloaded from the 60East Technologies official website: http://www.crankuptheamps.com/amps/

Copy amps_client.jar, amps_client-javadoc.jar and amps_client-sources.jar into the Tomcat lib folder.

The pre-compiled JAR files are in the api\client\java\dist\lib\ directory, which contains the JAR files mentioned above.

All of the above-mentioned java dependency files can be found after downloading and installing the AMPS Java Evolution Kit.

If a user has Linux machine available, install the AMPS distribution. Otherwise, download the AMPS Evolution Virtual Machine.

NOTE

To effectively use the .jar files, unblock these files by right-clicking on the File and selecting **Properties**. On the **General** tab, click **Unblock**.

Elasticsearch connectors

Dependencies for each supported Elasticsearch version are included in Panopticon Real Time installation:

- Elastic_6X_Dependencies.zip
- Elastic_7X_Dependencies.zip

Select the target Elasticsearch version and unzip the contents of the appropriate dependency zip into the Tomcat lib folder.

JMX

Use the following java options to enable JMX monitoring for the JMX plugin:

Enable JMX remote connection: (-Dcom.sun.management.jmxremote)

Disable JMX authentication: (-Dcom.sun.management.jmxremote.authenticate=false)

Set remote port for jmx: (-Dcom.sun.management.jmxremote.port=number)

NOTE

Providing invalid parameters into JMX connection string may cause a number of exceptions and make the server inaccessible. Make sure you are using the syntax provided above.

OneMarketData OneTick / OneTick CEP

This connector requires that the following JAR be added:

jomd.jar

Which is retrieved from the OneTick bin folder:

For example:

C:\omd\one market data\one tick\bin

Additionally, the following environment variables **MUST** be configured:

PATH

To include the OneTick bin folder.

For example:

C:\omd\one market data\one tick\bin

ONE_TICK_CONFIG

To reference the OneTick configuration file.

For example:

C:\omd\client data\config\one tick config.txt

Plus, the Tomcat configuration should include the following Java option:

```
-Djava.library.path=C:\omd\one market data\one tick\bin
```

The OneTick configuration file should have entries for Windows OS time zone mapping and information.

Example:

WINDOWS_TZ_MAPPING_FILE="C:/OMD/one_market_data/one_tick/config/windows_tz _mapping.dat"

```
WINDOWS_ZONEINFO_PATH="C:/OMD/one market data/one tick/config/zoneinfo"
```

Additionally, the OneTick client folder should be set to have the same permissions as those running the Tomcat process. Please check that the OneTick Java API is operational, before accessing workbooks through the server that utilize OneTick connectivity. This can be easily achieved by running one of the OneTick Java API examples.

NOTE

- The OneTick JAR must be updated to match the version of the OneTick client installation.
- For version 16.7.0, the OneTick connector is built and tested against version 1.17 of the OneTick Client.

SAP Sybase ESP

Manually copy the following dependency files from the Sybase ESP installation folder (e.g., C:\Sybase\ESP-5 1\libj):

- commons-codec-1.3.jar
- log4j-1.2.16.jar
- streaming-client.jar
- streaming-system.jar
- ws-commons-util-1.0.2.jar
- xmlrpc-client-3.1.3.jar
- xmlrpc-common-3.1.3.jar

NOTE

Make sure the dependency files are copied to the appropriate ${\tt WEB-INF}$ folder in Apache Tomcat:

- For 64-bit: C:\Program Files\Apache Software
 Foundation\Tomcat 9.0\webapps\panopticon\WEB-INF\lib
- For 32-bit: C:\Program Files (x86)\Apache Software Foundation\Tomcat 9.0\webapps\panopticon\WEB-INF\lib

StreamBase CEP

This connector requires the following JAR to be added:

sbclient.jar

Which is retrieved from the StreamBase Lib folder.

For example: C:\TIBCO\sb-cep\7.5\lib

StreamBase LiveView

This connector requires the following JAR files to be added:

• sbclient.jar, lv-client.jar, lv-client-wwwdeps.jar

Which are retrieved from the StreamBase Lib folder.

For example: C:\TIBCO\sb-cep\7.5\lib

Plus, the JARS from the LiveView installation:

• lv-compiler.jar,jyaml-1.3.jar

Which are retrieved from the LiveView Lib folder.

For example: C:\TIBCO\sb-cep\7.5\liveview\lib

DATABASE

There are two ways of connecting to a database from Altair Panopticon Real Time.

a. Use the Listed Data Connector for the specific Database (if available).

Includes: Cassandra, Elasticsearch 6.x, Elasticsearch 7.x, InfluxDB, Kx kdb+, ksqlDB, LivySpark, MongoDB, OneTick, OneTick Cloud, Panopticon Data Extract, Splunk.

b. Use the JDBC connector.

This requires:

- 1. Addition of the JDBC JAR(s) for the required Database into Tomcat/Lib.
- 2. For JNDI:

Update of the server configuration file: panopticon.xml to include the new JNDI resource name.

JNDI Name	~	jdbc/Postresql	(JNDI resource name as defined inside Context eg. jdbc/MyDB
-----------	---	----------------	---

3. For URL: Use the <u>URL</u> specific to the database's JDBC driver, the <u>Driver Class Name</u> specific to the driver, and the *Username* and *Password*.

Password	•••••	Show characters
User Id	buyer	
Driver Class Name	org.postgresql.Driver	
URL ¥	Jdbc:postgresql://localhost:5432/s	tc

JDBC Driver Installation

Install the relevant JDBC driver(s) on the system where you are running Tomcat and Panopticon Real Time. The exact installation procedure depends on the JDBC driver. Follow the instructions given by the provider of the JDBC driver and by the provider of your Java application server (for example, Apache Tomcat). In almost every case, a JDBC driver is installed by placing one or several jar-files in the lib folder of your Tomcat installation.

JNDI Connection Details

JNDI Connection details are specified in Panopticon Real Time configuration file panopticon.xml.

Each connection has the following structure:

```
<Resource name="jdbc/[Unique Name]"
    auth="Container"</pre>
```

```
type="javax.sql.DataSource"
         maxActive="100"
         maxIdle="30"
        maxWait="10000"
         username="[User Name]"
         password="[Password]"
         driverClassName="[Class Name]"
         url="[URL]"
/>
Where:
    Unique Name: Defines the unique JNDI resource name to be used.
User Name: The username to authenticate to the database.
    Password: The password to authenticate to the database.
    Class Name: The Class Name specific to the Database's JDBC Driver.
URL: The URL specific to the Database's JDBC Driver, and selected Server instance and database.
Additionally, other key attributes of the JNDI resource are:
    maxActive: The maximum number of active connections that can be allocated from this pool.
    maxIdle: The maximum number of connections that will be kept active even when there are no requests.
    maxWait: Maximum time in milliseconds to wait for a database connection to become available.
```

Common Databases and their JNDI Configurations

Database	Description
Oracle 11	<pre>Using ojdbc6.jar driverClassName="oracle.jdbc.OracleDriver" url="jdbc:oracle:thin:@[HostName]:1521:[DatabaseName]"/></pre>
MS SQL Server	<pre>Using sqljdbc4.jar driverClassName="com.microsoft.sqlserver.jdbc.SQLServerDriver" url="jdbc:sqlserver://[Server]\[Instance];databaseName=[Database Name]"/></pre>
Sybase ASE	<pre>Using jconn4.jar driverClassName="com.sybase.jdbc4.jdbc.SybDriver" url="jdbc:sybase:Tds:[HostName]:5000/[DatabaseName]"</pre>
PostgreSQL	<pre>Using postgresql-9.4.1208.jar driverClassName="org.postgresql.Driver" url="jdbc:postgresql://[HostName]:5432/[DatabaseName]"</pre>
MySQL	<pre>Using mysql-connector-java-5.1.38-bin.jar driverClassName="com.mysql.jdbc.Driver" url="jdbc:mysql://[HostName]:3306/[DatabaseName]"/></pre>

R AND PYTHON TRANSFORM SUPPORT

R and Python connectivity and transforms occur over TCP/IP network links.

- For R, Rserve is used.
- ☐ For Python, Pyro (Python Remote Data Objects) is used.

R Integration

To enable R connectivity:

- 1. Download R, install it, and the R Console (http://cran.rstudio.com/).
- 2. Open the R Console.
- 3. Install Rserve using the following command from within the R Console:

```
install.packages("Rserve")
```

4. Initiatiate the Rserve library using the following command:

```
library(Rserve)
```

5. Run Rserve by executing the following command:

```
Rserve()
```

Only steps 2, 4 & 5 need to be repeated when R connectivity is required.

Example:

```
RGui (64-bit)
                                                                         Х
File Edit View Misc Packages Windows Help
- - X
R Console
R version 4.1.2 (2021-11-01) -- "Bird Hippie"
Copyright (C) 2021 The R Foundation for Statistical Computing
Platform: x86_64-w64-mingw32/x64 (64-bit)
R is free software and comes with ABSOLUTELY NO WARRANTY.
You are welcome to redistribute it under certain conditions.
Type 'license()' or 'licence()' for distribution details.
  Natural language support but running in an English locale
R is a collaborative project with many contributors.
Type 'contributors()' for more information and
'citation()' on how to cite R or R packages in publications.
Type 'demo()' for some demos, 'help()' for on-line help, or
 'help.start()' for an HTML browser interface to help.
Type 'q()' to quit R.
> library(Rserve)
> Rserve()
Starting Rserve...
 "E:\Work\R\R-4.1.2\library\Rserve\libs\x64\Rserve.exe"
```

NOTE

Connectivity by default is over Port 6311.

To enable authentication across the Rserve TCP/IP link

create a password file (pwdfile.pwd)

Each line of the file should have the user and then the password.

Example:

```
user1 password1
user2 password2
```

☐ Create a configuration file with following parameters (rconfig.conf)

```
auth required
pwdfile [path of password file]
```

Example:

```
remote enable
auth required
port 6311
pwdfile C:\\RIntegration\\pwdfile.pwd
```

load the created configuration file (the default Rserve configuration file is still loaded, but its settings have lower priority) and run Rserve:

```
Rserve(args="--RS-conf [path of configuration file]")

Example:
```

Rserve(args="--RS-conf C:\\RIntegration\\rconfig.conf")

Python Integration

Panopticon can use Python for both data transforms and as a primary data source. The server part of Panopticon will send requests to Python, with data and/or Python code, via Pyro4 - Python Remote Objects. Pyro4 installs as a Python package in your Python environment, and connectivity is enabled by starting a Pyro process with a shell script file (.BAT script file) which is included in the Panopticon distribution zip-archive.

To set up a Python environment that can be used from Panopticon, follow these steps:

- 1. Download and install Python.
- 2. Install Pyro4.
- 3. Install pandas.
- 4. Install additional packages.
- 5. Set the Pyro HMAC key.
- 6. Start Pyro4.

Downloading and Installing Python

Download Python from https://www.python.org/downloads/ and select the release version you require as well as the right version for the operating system of your server. Note that Linux systems often have Python included out of the box. Install Python as described by documentation from Python.org. You can install Python on the same host that runs the Panopticon server, or a different host, if firewall settings and port mapping allow communication between the two hosts. If you are running Panopticon for development, testing or personal use on your workstation, install Python on your workstation as well.

Installing Pyro4

When Python is installed, add Pyro4 by installing it like a Python package. The Pyro4 version must be 4.71 or higher. On the command prompt, type **python** and press **Enter** to start a Python prompt. Then run this command:

```
pip install Pyro4>=4.71
```

Installing Pandas

When working with a data table in Python, the pandas package and the pandas DataFrame object provides many useful advantages and is highly recommended. Panopticon's integration with Pyro4 will check if the object returned from Python is a pandas DataFrame and therefore the pandas package is required. On the Python prompt, run this command:

```
pip install pandas>=1.1.5
```

This will also automatically give you the NumPy package.

Installing Additional Packages

To be able to view and use the examples in the Panopticon example workbook "How to Python", you are also required to install a few additional packages using these commands:

```
pip install scikit-learn>=1.0.1
pip install pyarrow>=3.0.0
```

Setting the Pyro HMAC Key

When you send a request to Pyro4, you are required to supply the correct password which is called the Pyro HMAC Key. This password protects the Python environment from unauthorized remote calls via Pyro4. You should create an environment variable named PYRO_HMAC_KEY on the host where Python and Pyro4 are installed. However, if PYRO_HMAC_KEY is not found or created, the environment variable will be created by the script used for starting-pyro4. The default value is password. You have the option of either:

	creating the PYRO	_HMAC_KE	/ and setting a	password val	ue of your c	hoice
--	-------------------	----------	------------------------	--------------	--------------	-------

editing the start script and entering your password value instead of the default value password

When using Python from Panopticon, either as a transform or as a primary data source, you will supply the password as part of the connection settings in Panopticon. The password can also be saved in the Panopticon.properties file, by an Administrator, which will let Designer users create Python connections without knowledge of the password.

Starting Pyro4

Before you can use Python from Panopticon, you must start the Pyro4 process that will receive requests from Panopticon and pass them on to Python. This is done by running a script included with Panopticon on the host where Python and Pyro4 are installed.

On Linux, you run the file start_Python_connectivity.sh which in turn runs the file pyro.py.

On Windows, you run the file start Python connectivity.bat which in turn runs the file pyro.py.

Multiple Python Environments on Windows

On Windows, you can install multiple Python versions in parallel, resulting in installation folders like the following examples:

- C:\Program Files\Python38
- ☐ C:\Program Files\Python39
- C:\Program Files\Python310

Each of these versions has its own package installations. For example, you can have one version of a package installed for Python 3.9 and another package version for Python 3.10.

NOTE

When installing packages for different versions of Python on a host which will serve multiple users, make sure you install from a command prompt with elevated privileges (run As Administrator), otherwise, packages will be installed under your own Windows user profile folder.

With Python for Windows downloaded from Python.org, you also get **py.exe** which is a Python launcher. When installing Python for all users, it is placed in C:\Windows\py.exe or C:\Users\<username>\AppData\Local\Programs\Python.

With the Python launcher py.exe, you can start a specific Python version as follows:

py -3.9

To make a package installation for a specific Python version, open a command prompt as Administrator and run:

```
py -3.9 -m pip install <packagename>
```

To start a Pyro4 process with a specific Python version (in this example, 3.9) you can launch Pyro4 as follows:

start Python connectivity.bat -3.9

LOAD CUSTOM DATA PLUGINS

Panopticon Real Time will load a file named **Plugins.xml** during startup. The file contains class names of all the data plugins that will be loaded and applied to the server. However, the Plugins.xml file can be replaced in case the user wants to have a custom setup and load their own plugins or if they want to disable certain data plugins from being loaded. This is achieved by creating a new plugins.xml file and placing it in the AppData folder (e.g., C:\vizserverdata).

The original plugins.xml file is always distributed with the panopticon.war file. From the .war file, copy the plugins.xml file from the root folder to your AppData (i.e., C:\vizserverdata) folder. Then open plugins.xml and add or remove items to either enable or disable certain plugins.

NOTE

New data plugins are constantly being developed and distributed. Therefore, it is recommended that you revisit the shipped plugins.xml file after each release if you have replaced the default plugins.xml file.


[10] VIEWING AND MANAGING WORKBOOKS

ACCESSING WORKBOOKS


The Workbooks tab lists available folders and uploaded or published workbooks in Grid View.


- ☐ The *Folders* include their names and the number of available workbooks.
- ☐ The *Workbooks* include their titles, thumbnail images, and when they were last modified.

 Recently opened workbooks are also displayed under the *Quick Access* pane.



Clicking on the workbook thumbnail opens it on the web browser.






Searching for Workbooks

Search for particular workbooks that may be located in different folders and perform other operations like merge, copy, download, or remove.

Steps:


- 1. On the *Workbooks and Folders Summary* layout, click on a workbook folder then enter a workbook name or dashboard name in the *Search Workbook* box.
- 2. Click →



The following information are displayed for each workbook:

- Folder where the workbook is located
- What the search match was based on: workbook or dashboard name
- Date/Time when the workbook was last viewed
- Date/Time when the workbook was last modified


You can also enter one or more characters into the *Search Workbook* box then click **Enter**. The list of workbooks that matched the entries will be displayed.




Click on a workbook thumbnail to open and display it on the web browser.


To go back to the Workbooks and Folders Summary layout, click $\stackrel{\longleftarrow}{}$.

You may opt to right-click on a workbook or select several workbooks to display the context menu.





To display the workbook in its location, click **Show in Folder** on the context menu.




The other context menu options are discussed in the sections below.


Folders and Workbooks Display View

Workbooks can be displayed either on a List or Grid View.

On the *Toolbar*, click **List View** , the folders and workbooks are displayed in a standard listing.



Or click **Grid View** . The folders and workbooks are displayed as thumbnails.



On either display view style, clicking on a workbook title or thumbnail displays the workbook on the *Open Workbook in View Mode*. For more information on how to analyze interactive dashboards, refer to the <u>Client User Guide</u>.


Sorting Workbooks

Sorting workbooks can be done by Name, Last Viewed/Last Published, or Last Viewed by Me.

Steps:

On the Folders and Workbooks Summary layout, either:

click the **Sort By** option on the *Toolbar* of the *Grid View* By default, the sorting is by **Name**.




- Name
- Last Modified
- Last Viewed By Me

Then click the Sort Order.

- Ascending

 Descending
- click on the Name, Last Viewed By Me, or Last Published column header of the List View



Then click the Sort Order.

- Ascending
- Descending

Creating Workbooks


A user with a Designer role can create workbooks using the web authoring tool in Panopticon Real Time. This feature is extensively discussed in the <u>Panopticon Web Authoring Guide</u>.

Renaming Workbooks or Folders

A user with an Administrator or Designer role can rename workbooks and folders.


Steps:

1. Right-click on a workbook or folder then select **Rename** on the context menu.



The Rename Workbook or Rename Folder dialog displays.






2. Enter a new name then click

Uploading Workbooks


Users with an Administrator role can upload workbooks to the currently selected folder in the Workbooks page.

Steps:

1. On the Workbooks page, click on a folder or a personal folder and select Upload Workbook.




The Upload Workbook dialog displays.



- 2. To upload a workbook, you can either:
 - drag it from your desktop and drop on the dialog, or
 - click **Choose Workbook** and select one on the *Open* dialog that displays.


The name of the workbook is displayed on the uploaded workbook area and in the Name box.



- 3. You can opt to rename the workbook.
- 4. To replace an existing workbook, check the **Replace existing workbook** box.



You will be notified once the workbook is uploaded.



The workbook is added and displayed.

NOTE

- An error message is displayed if the data source schema of the uploaded workbook has not been updated or missing.
- The uploaded workbook will not include the data source. However, if Panopticon Real Time can reach the same folder of the data source, or the workbook has been designed in the same machine, then the data can be viewed.


Viewing Workbook History and Republishing

Aside from opening workbooks, a user with either an Administrator or Designer role can also perform the following:


- View the change history of workbooks
- ☐ Republish an archived workbook to the recent version of Panopticon Real Time
- Rename an archived workbook

Steps:

1. On the **Workbooks** tab, right-click on a workbook and select **History** on the context menu.




The History of Workbook <Name> dialog is displayed with the current version of the workbook indicated.



Sort the archival list either through the *Date Modified* or *Modified By* by clicking on the or button.

Also, move to the other pages of the list by clicking on a page or clicking the or button

- 2. You may opt to rename an archived workbook by entering a new one in the New Name box.
- 3. Click on an archived workbook in the list.







4. Click Yes


A confirmation message displays.

The earlier version of the workbook was successfully republished.

OK

5. Click OK

The republished workbook version is added in the history list.




Moving Workbooks


Users with Administrator or Designer role are allowed to move a workbook to another folder or subfolder they have permission to.

Steps:


1. Right-click on a workbook and select **Move** on the context menu.



The Move Workbook dialog displays with the folder or subfolders the user is allowed to move the workbook.



2. Select the folder or subfolder.



3. Click Move


The workbook is moved and displayed on the selected folder.

Copying Workbooks


Users with Administrator or Designer role are allowed to copy a workbook to another folder or subfolder they have permission to.

Steps:


1. Right-click on a workbook and select **Copy** on the context menu.



The Copy Workbook dialog displays with the folder or subfolders the user is allowed to copy the workbook to.



2. Select the folder or subfolder.



3. Click Copy

The workbook is copied and displayed on the selected folder.

PARAMETER VALUE PASSING INTO THE WEB CLIENT

The Web client uses JSON URL query string to pass parameters.

For example:

/params/{"param1":"value1", "param2":"value2"}

Again, parameter values must be URL encoded:

http://[host:port]/panopticon/workbook/#/[workbook_name]/[dashboard_name]/par
ams/{"param1":"value1","param2":"value2"}

Where:

- Parameters are passed in JSON format
- □ Every parameter's name should be enclosed in double quotes (i.e., "")
- /params/ sub-path should be placed in prior to JSON sections with parameters
- Special symbols in the parameter values should be URL-encoded. (Refer to <u>Special Symbols to Pass Parameter Values into the HTML5 Client</u> for more information.)

Here is an example URL with parameters that displays one of the example workbooks:

http://localhost:8080/panopticon/workbook/#/How%20to%20Auto%20Parameterize/Summary/params/%7B%22Region%22:%22Europe%22,%22Industry%22:%22Consumer%20Goods%22%7D



This workbook can also be displayed on the web browser using this URL:

```
http://localhost:8080/panopticon/workbook/#/How to Auto
Parameterize/Summary/params/{"Region":"Europe","Industry":"Consumer Goods"}
```

To filter specific values, the array of values can be passed again in a standard JSON format, enclosing the array elements into square brackets:

```
{"Region":["Europe", "North America"]}
```

For example:

```
http://localhost:8080/panopticon/workbook/#/How to Auto
Parameterize/Summary/params/{"Region":["Europe","North
America"],"Industry":"Consumer Goods"}
```

Special Symbols to Pass Parameter Values Into the HTML5 Client

When trying to pass parameters to the new HTML5 Client, you need to use URL-encoded characters.

```
For example, for {"Type": [Soft/Drinks"]} to work, it should be changed to {"Type": [Soft%252FDrinks"]}
```

Here is a list of double-encoded values you can use to replace their corresponding character.

Character	Double Encode Value
"<"	"%253C"
"J"	"%252F"
">"	"%253E"

[11] DATA LIBRARY


The *Data Library* page allows creation and management of reusable data tables outside workbooks. Data tables from the data library can be used by multiple workbooks server wide.

Some important concepts to remember:

- □ Bringing data inside workbooks is done through data tables.
- □ A data table contains metadata for data source connection settings, data query, schema definition, calculated columns, transforms, etc.
- One data table can use only one data connector to connect to a data source.
- ☐ Two or more data tables can be joined to create a new joined data table.
- Data table permissioning and sharing between users or groups is done similarly like workbooks (i.e., using folder tree).
- There are four types of data tables. The first three reside at the Data Library.

Data Table Type	Description
Data Store	Users can opt to store data closer to Panopticon server in an embedded database.
Live	Direct connection to source data.
Joined	Two or more different types of data tables joined together creating a new data table.
Uploaded	Uploaded files through any of the file connectors, that consequently becomes a Data Store, after importing to data store.

The Data Library page is composed of the following sections.



Data Library Page Sections and Descriptions

Section	Description
1	Folders
	List of folders where data tables can be saved, exported, or imported.
2	Folder Context Menu Allows you to: Create a data table and joined data table Assign folder permissions on your workspace Import or export data table bundles
	Create, rename, or remove folders
3	Search Data Table Entering text will filter data tables which can include: Those that are available in data store Live data tables Joined data tables Extracts
4	Toolbar Allows you to: Display the data tables list either on List View or Grid View Copy or move data tables to other folders Import data table to data store Clear and import data table to data store Delete data tables
5	New Legacy Extract Allows accessing data by retrieving only the required results into memory, by querying on demand, pushing aggregation, and filtering tasks to underlying big data repositories, or queryable data extracts.
6	New Joined Data Table Allows you to join data tables created in the data library.
7	New Data Table Allows you to create a data table.
8	Folders List Available folders.
9	List of Data Tables and Data Extracts Data tables and data extracts created in the data library.
10	Data Table Context Menu Allows you to: Export data table bundles Copy or move data tables to other folders Rename or remove data tables

Section	Description
	View details of the data table
	Set the data policy for data tables in the Data Library

For more information on using this page, see [4] The Data Library Page section in the Web Authoring Guide.

SETTING UP DATA STORE

To be able to use data store, you would need to set the following properties. By default, Panopticon supports MonetDB, so default values correspond to it.

Also. MonetDB JDBC driver is packaged with Panopticon server. For other data store types, refer to <u>JDBC Driver Installation</u> section.

Property	Data Store
Attribute	datastore.connection.schema
Description	Name of the database schema to be used for creating or managing objects inside database.
Default Value	dbo
Property	Data Store
Attribute	datastore.type
Description	Controls which data store connector should be used. Valid values are MonetDB", MSSQLServer and PostgreSQL.
Default Value	MonetDB
Property	Data Store
Attribute	datastore.connection.jndi
Description	JNDI resource name for the connection e.g., jdbc/MyDB . More details on how to configure JNDI is at <u>JNDI Connection Details</u> section.
Default Value	
Property	Data Store
Attribute	datastore.connection.url
Description	JDBC connection URL for the database e.g., jdbc:monetdb://localhost:49153/PanopticonDataStore This property value is discarded If datastore.connection.jndiproperty is set.
Default Value	
Property	Data Store
Attribute	datastore.connection.driverclassname

Description	Fully qualified Java class name of the JDBC driver used for the connection.
Default Value	org.monetdb.jdbc.MonetDriver
Property	Data Store
Attribute	datastore.connection.username
Description	Username for the connection. Only required when using connection URL.
Default Value	
Property	Data Store
Attribute	datastore.connection.password
Description	Password for the connection. Only required when using connection URL.
Default Value	

CACHING

Panopticon Real Time supports five levels of caching:

	Data Store
	Real-time subscription cache
	Data source cache
	Data table cache
	Query result cache
	of which are optional. If caching is specifically not desired, data requests can always be forwarded to the erlying data repository.
subs requ	subscription cache describes the cache used for streaming subscriptions. This cache is used to ensure scriptions are not duplicated by the server, and that instead the server manages duplicate end client subscription lests. Subscriptions are started when the server receives a valid client request and can be set to stop when are no longer watching data from them or be kept alive until the server is stopped.
the ι	data caches simply keep corresponding data sources and tables in memory to avoid unnecessary reloads from underlying data repositories. Neither is used for real-time data, but the data source cache helps with real-time is joined to standing data. The cache entries are keyed on:
	The workbook
	The data table
	The data source
	Parameter values

The query result cache stores the result of a query from an individual visualization, filter, or legend on a dashboard. It is useful if many users are viewing the same dashboard, when many identical queries will be sent in parallel to the

server. It also caches real-time data for this purpose.

The time-to-live (TTL) for entries is based on the auto refresh period set on the data table.


[12] WEBHOOKS

A webhook is a special URL that makes it possible to send a message from other systems into the system that issued the webhook. Webhook URLs should be treated with care and not shared publicly, since anyone with knowledge about the webhook URL will be able to use it.

Collaboration platforms such as Microsoft Teams, Slack and many others all have support for creating incoming webhooks. In Panopticon, outgoing webhooks can be added (based on incoming webhook URLs from other systems) and used as a channel for sending messages about triggered alerts, like how such messages can also be sent by email. Webhooks added to Panopticon are stored in the server folder structure and are subject to the same permissions model as workbooks.

An outgoing webhook in Panopticon can be used as the message channel for multiple different alerts in multiple different workbooks, due to the parameterization of the webhook request body. The exact structure and content that you should create in the request body of a webhook will be specified in the documentation of the system that issued the webhook.

NOTE Do not expect that the example <u>request body</u> shown below, will work as is.




Property	Description
Search Webhooks	Entering text will filter the webhooks.
<u>Toolbar</u>	Allows copying, moving, and removing of webhooks.
	Also, to display the webhooks list either on <i>List View</i> or <i>Grid View</i> .

Create Webhooks	Allows creating new webhooks.
Webhooks Context Menu	Allows <u>renaming</u> , <u>moving</u> , <u>copying</u> , <u>deleting</u> , and enabling of the <u>trigger</u> of webhooks.


Folders and Webhooks Display View

Webhooks can be displayed either on a List or Grid View.

On the *Toolbar*, click **Grid View** . The folders and webhooks are displayed as thumbnails.




Or click **List View** , the folders and webhooks are displayed in a standard listing.




On either display view style, clicking on a webhooks title or thumbnail displays the Webhooks page.

Searching for Webhooks

On the Webhooks tab, to search for a particular webhook, enter it in the Search Webhooks box.



You can also enter one of more characters into the *Search Webhooks* box then click **Enter**. The suggested list of webhooks that matched the entries will be displayed.



Click on a webhooks to open and display.

To clear the filter, delete the text entry in the Search Webhooks box.

CREATING WEBHOOKS

This section discusses the instructions and guidelines to create webhooks.


Steps:

On the Webhooks tab, click on a folder then
 The New Webhook dialog displays.




2. Enter the name of the webhook then click

The new webhook is displayed on the Webhook page.



3. Enter or select the following webhook properties:



The request body to be supplied to the HTTP call. For example: { 'Alert title': '{_alert_title}', 'Alert dashboard URL': '{_alert_dashboard_url}', 'Alert description': '{_alert_description}', 'Alert reason': '{_alert_reason}', 'Triggering items': '{_alert_triggering_items}', 'Timestamp': '{_current_time}', 'Folder': '{_workbook_folder}', 'Workbook': '{_workbook_name}', 'Dashboard': '{_dashboard_name}' }

NOTE

URL, *Headers*, and *Request Body* fields can be parameterized (i.e., special server parameters, alert parameters, and <u>global parameters</u>).



4. Click

to save the new webhook.

You may opt to click to trigger the webhook. Any parameter in the request body will be replaced by its value when triggering the webhook request.

For example:

```
{_current_time} - 2021-07-01T12:34:56Z
```

6. Click to go back to the Folders and Webhooks list. The new webhook is added on the list.

WEBHOOKS TOOLBAR AND CONTEXT MENU

Moving, copying, and removing webhooks can either be done using:

□ Context menu Rename Move Move Copy Copy Remove Remove Trigger Trigger **Webhooks Folder Context Menu Webhook Context Menu** □ Toolbar ↑ ∷ □ ⊕ 前 Name

The Webhooks toolbar options include:

List View

Toolbar Option	Description
Sort By / Sort Order	Allows sorting webhooks by Name, Last Modified, or Last Modified By.
<u>Display View</u>	Display webhooks either by List View or Grid View.
Сору	Copy webhooks to another folder or subfolder where the user has permission.
Move	Move webhooks to another folder or subfolder where the user has permission.
Remove	Remove webhooks.

Grid View

The Context Menu options include:

Toolbar Option	Description
Rename	Rename the webhook.
Move	Move webhooks to another folder or subfolder where the user has permission.
Сору	Copy webhooks to another folder or subfolder where the user has permission.
Remove	Remove webhooks.

Sorting Webhooks


Sorting webhooks can be done by Name, Last Modified, or Last Modified By.

Steps:

On the Webhooks tab, either:

□ click the **Sort By** option on the *Toolbar* of the *Grid View*.

By default, the sorting is by Name.




- Name
- Last Modified

Then click the Sort Order.



□ click on the Name, Last Modified, or Last Modified By column header of the List View.




Then click the Sort Order.

- Ascending
- Descending


Renaming a Webhook

Steps:

1. Right-click on a webhook then select **Rename** on the context menu.



The Rename Webhook dialog displays.




2. Enter a new name then click

Moving Webhooks


Users with an Administrator role are allowed to move webhooks to another folder or subfolder where they have permission.

Steps:

- 1. Select the checkbox of one or several webhooks either on the *Grid View* or *List View*.
- 2. Then select either:
 - Move icon on the toolbar, or
 - Move on the content menu.



The *Move Webhook* dialog displays with the folder or subfolders that the user is allowed to move the webhooks. Select the folder or subfolder.



3. Click Move


The webhooks are moved and displayed on the selected folder.

Copying Webhooks


Users with an Administrator role are allowed to copy webhooks to another folder or subfolder where they have permission.

Steps:

- 1. Select the checkbox of one or several webhooks either on the Grid View or List View.
- 2. Then select either:
 - Copy icon on the toolbar, or
 - Copy on the content menu.



The Copy Webhook dialog displays with the folder or subfolders the user is allowed to copy the webhooks to. Select the folder or subfolder.



3. Click Copy


The webhooks are copied and displayed on the selected folder.

Deleting Webhooks


Users with an Administrator role can remove webhooks.

Steps:

- 1. Select the checkbox of one or several webhooks either on the Grid View or List View.
- 2. Then select either:
 - Remove icon on the toolbar, or
 - Remove on the content menu.




A notification message displays.



Triggering Webhooks

To trigger a webhook, right-click on it and select **Trigger** on the context menu.



Any parameter in the request body will be replaced by its value when triggering the webhook request.

For example:

{_current_time} - 2021-07-01T12:34:56Z


[13] ALERTING

The Alerts function allows a notification to be sent when the data in a visualization has met the predefined settings.

If alerts are required to be sent via email, Panopticon Real Time must be configured with valid email server information in the Panopticon.properties file located in the AppData folder (e.g., C:\vizserverdata).

See Panopticon Real Time Configurations for Email Send Outs and Alerts for instructions.

Otherwise, when trying to enable an alert, this error will be displayed:




In addition, you can also set the alert.creation.only.by.administrators property to true for only the Administrators to create alerts.

SETTING UP ALERTS

Alerts can be defined against:


- □ Streaming data sources (including CEP Engines and message queues)
- □ Periodically refreshed data sources (like Oracle, SAP Sybase, SQL Server, and so on)

Alert definition can be done by right-clicking on a streaming numeric or text data in a visualization in the Web Client and setting the limits, duration, what will be included, how many and when an email will be sent.




Steps:


1. Open a workbook on the Web client and right-click on a streaming numeric or text data in a visualization. Select *New Alert* on the context menu.



The Alerts dialog displays with the name of the visualization where the alert will be set.



Sample Text Alerting



Sample Numeric Alerting


2. Enter or select the following properties:

Property	Description
Name	Name of the alert.
Description	Description of the alert.
Search	Search for columns.
Criteria	Criteria set of the alert. Can be multiple, in which case all criteria sets are evaluated in parallel, each triggering respective alerts. Additional criteria sets can be added by clicking You can also right-click a Criteria tab and select Rename to rename the criteria or select Remove to delete. The Remove option is disabled when only one criteria set is available.
Variable	Available variable columns in the visualization where the alert is set.

Condition	Allows setting the following <i>Limit</i> of all the available numeric variables in the visualization:
	Upper or Equal To (<=)
	Lower or Equal To (>=)
	Upper values (<)
	• Lower values (>)
	Between – values between the <i>Lower</i> and <i>Upper</i> values
	For text variables, there are four types of conditions:
	Equals - The string is equal to another string, e.g., Country=Sweden
	Not Equals – The string is not equal to another string
	 Wildcard: The string matches a wildcard expression, e.g., Country=Norwa* would match Country=Norway
	Regex: The string matches a regex expression, e.g., Country=I[a-zA-Z]+a would match Country=India and Country=Indonesia
For the Last	Checks if a value has reached the limit on the set Date/Time unit:
	• second(s)
	• minute(s)
	• hour(s)
	day(s)
Breakdown	Current breakdown of the visualization.
Parameters	Available parameters in the visualization.
Action Limit	The maximum number of times an alert will be sent on the set Date/Time unit:
	• second(s)
	• minute(s)
	• hour(s)
	day(s)
Send E-mail	Determines when an alert email will be sent:
	on enter
	on leave
	on enter/leave
	If unchecked, the notification will only be displayed on the Web client.
Include	Determines whether the image of the visualization or dashboard will be included in the alert email.
	For the included image of the visualization, check the Use current drill path box to generate a drilled image in the email.
CC	CC mailing groups that will receive the alert, separated by a comma.
Sound	The sound that will be played for a triggered alert. The available sounds are mp3 files placed in the AppData/Sounds folder (i.e., C:\vizserverdata\Sounds). Panopticon is shipped with one sound (i.e., bell_ping_1s.mps).



3. Check the Alert Hours box. The dialog changes to display:



By default, the duration is from 9:00 AM to 5:00 AM on Monday, Tuesday, Wednesday, Thursday, and Friday.

4. To modify the Active Hours, click $^{\bigcirc}$.

The Clock settings display.



- 5. Select the Hour, Minutes, and AM/PM settings.
- 6. To modify the Active Days, check the boxes of the desired days.
- 7. To apply the active hours in another time zone, select the desired value from the *Show in Timezone* drop-down list box.

Once set, the From and To limits will be applied for that time zone. If not set, the server default time zone will be used.

- 8. Tap the Activated slider to turn it on.
- 9. Click . The new alert is added on the *Alerts Definition* page.

NOTE

When creating alerts for grand total, ensure that no breakdown is set.

An alert displays with the following properties or settings:

Property	Description
Title	Name of the alert that was entered in the <i>Alerts</i> dialog.
Workbook	The path and name of the workbook where the alert was set.
Dashboard	The dashboard name where the alert was set.
Created By	The author of the alert.
Creation Time	The Date/Time when the alert was set.
Enabled	Determines if the alert is enabled (or active).
Status	Status of the alert.
Times Triggered	The number of times the alert was triggered.
Sent Emails	The number of emails sent.
Notifications	The number of notifications sent.

The number of triggered webhooks.


Sorting Alerts

By default, the list of alerts is sorted by Title in an ascending order. You can modify the sorting of the list by clicking


the or button of the *Title, Workbook, Dashboard, Created By, Creation Time, Enabled, Status, Times Triggered, Sent Emails, or Notifications* columns. The icon beside the column that was used for the sorting will indicate if it was in an ascending or descending order.

Searching for Alerts

To search for a particular alert, enter it in the Search box.





You can also enter one of more characters into the *Filter Applications* box and the suggested list of alerts that matched the entries will be displayed.



Enabling Alerts on the Alerts Page

Tap the **Enabled** slider to turn it on.






Enabling alerts can also be performed on a visualization's Alerts panel.


Other Alerts Operations can be modified, enabled, and deleted in the workbook where it was set.

Displaying Active Alerts

Tap the **Show only active alerts** slider to turn it on.



Only the active or enabled alerts are displayed on the Alerts tab.




Activating or Deactivating All Alerts

Alerts can be activated or deactivated in one click.

To activate all deactivated alerts, click Activate All




. All of the deactivated alerts are activated.



To deactivate all activated alerts, click Deactivate All



. All of the activated alerts are deactivated.






Viewing Triggered Alerts

View the details of all the triggered events of activated alerts.

Steps:

Click the Alert Events tab on the Alerts page.
 The Alerts Triggered Events page displays the following information.



Property	Description
Trigger Time	The Date/Time when the alert was triggered.
	Click to display a multi-select checkbox list. By default, all checkboxes are selected (Select All). Selecting or deselecting items in the list controls the filter.
Title	Title of the alert. Click to display a multi-select checkbox list. By default, all checkboxes are selected (Select All). Selecting or deselecting items in the list controls the filter.
Description	Description the alert.
Workbook Name	The workbook name where the alert was set.
Dashboard	The dashboard name where the alert was set.

NOTE

Alert events are recorded as long as the page is kept open in the web browser. Closing or navigating away from the page will clear the list.


- 2. You can also do any of the following options:
 - Click or of a column title to sort the list.
 - Click to delete a triggered alert.
 - Click to clear the list.
 - Click a **Title** link to go to the workbook where the alert was triggered.

Importing Alerts

Allows you to import alerts shared by other others.

Steps:

On the Alert Definitions tab, click the Import Alerts icon.
 The Upload Alert dialog displays.



- 2. To upload an alert, do one of the following:
 - Drag the file from your desktop and drop on the dialog, or
 - Click **Choose alert** and then browse and select one on the *Open* dialog that displays.



A notification displays once the alert is uploaded.



Exporting Alerts

You can download a copy of any of the alerts.


Steps:

- 1. On the Alerts list, select the checkbox of the alerts you want to export.
- 2. Click **Export Alerts** icon.

The selected alerts are downloaded.

Modifying Alert Settings

Steps:



2. Click an alert to modify.

The Alerts dialog displays.

3. Make the necessary changes then click

ok to save them.


Deleting Alerts

Alerts can be deleted on:

- the Alerts panel
- an Alerts dialog
- the Alerts tab


Deleting Alerts on the Alerts Panel:

Open a workbook with an alert and click on the Alerts icon.
 The Alerts panel displays with the list of alerts.



2. Check the box of an alert and click the **Delete** icon. You can also check several boxes to delete multiple alerts.

Deleting Alerts on an Alerts Dialog:



- 2. Click an alert. The Alerts dialog displays.
- 3. Click the **Delete** icon.


Deleting Alerts on the Alerts tab:

1. Go to the Alerts tab.

The Alerts tab displays the list of alerts.

Click the of an alert to delete.

A confirmation message displays.



4. Click


Enabling Alerts

Alerts can be enabled either on:

- the Alerts panel
- an Alerts dialog

Enabling Alerts on the Alerts Panel:


Open a workbook with an alert and click on the Alerts icon.
 The Alerts panel displays with the list of alerts.



2. Tap the Activated slider to turn it on.

Enabling Alerts on an Alerts Dialog:

Open a workbook with an alert and click on the Alerts icon.
 The Alerts panel displays with the list of alerts.




- 3. Click an alert. The Alerts dialog displays.
- 4. Tap the Activated slider to turn it on and click




Viewing and Managing Alerts for Non-Administrator users

There are three tabs that are available for non-Administrator users:



Click on the Alerts tab to view and manage the available alerts.



Also perform any of the following operations:

	<u>Sort alerts</u>
	Search for alerts
	Enable an alert
	<u>Delete alerts</u>
	Display active alerts
	Deactive/activate all alerts
	View Alerts Triggered Events
	Importing Alerts
	Exporting Alerts
Click	the user icon and click View Profile . Then enter email of the user or group who will receive the alert.
Us	er Profile
Ema	ail Address
m	villanueva@altair.com
(u	Update Email Address
Click	Cupdate Email Address.

SAMPLE EMAIL ALERTS

An alert is generated when the alert set state changes from **Off** to **On** and recorded in the alert history.

An alert is only issued by email if the alert has not already been sent in the last 'n' minutes as defined in the *Alert*s dialog.

When an alert is issued, an email is sent to the defined email address.

The email includes:

Link to the workbook or dashboard
Condition and limit value
Breakdown


□ Name of the visualization where the alert was set

PNG image of the visualization or dashboard

Dashboard: http://localhost:8080/panopticon/workbook/#/ecs kx/Visual

Condition: Sum(fills) >= 10.0


The alert was triggered by the following items: algotype:Opportunistic, algoname:Liquidity Driven, sym:O12989, ordername:SIX-NOVN SELL 797k




SAMPLE WEB CLIENT ALERTS

When an alert is triggered, aside from the email notifications, a visual indication or pop-up in active Web clients will draw attention to the alerting visualization or dashboard.

In the example below, an alert initially displays highlighted in blue:




The alert eventually fades away and the pop-up screen fills up with the four latest triggered alerts.




The pop-up stays on screen until it is closed by clicking the button.

Saved alert notifications can be opened on the *Notifications* panel by clicking the icon.



Clicking on a notification highlights the item in the workbook that triggered the alert.




Click the button to delete a notification or click to delete all of the notifications.

[14] GLOBAL PARAMETERS

The **Parameters** tab supports adding, modifying, and deleting global parameters that will pull and enter specific data into the different sets that are assigned to workbook folders, as well as user specific folders.

For example:




Parameters Set In	Description
Organization's root folder (i.e., Global)	Inherited by all of the available folders and applied to all workbooks
Public root folder (e.g., Global > Orders)	Inherited by the public root folder's subfolders and applied to all public workbooks.
User's root folder (i.e., Global > ~)	Inherited by the user root folder's subfolders and applied to all private workbooks.

ADDING PARAMETERS

Follow the steps below to add global parameters with an Administrator role.

Steps:

On the **Parameters** tab, click the Add icon of a global folder (root or subfolder).
 A new parameter entry displays.



- 2. Enter a Name for the new parameter.
- 3. Select the *Type*: **Text**, **Numeric**, or **Time**.
- 4. Enter the Default Value.


You can enter several default values, separated by a comma. Single quotes on parameter value/s are removed when saving global parameters. For the Time type, the following formats for the default value are accepted: "yyyy-MM-dd" "yyyy-MM-ddTHH:mm:ss" "yyyy-MM-ddTHH:mm:ss.SSS"

5. Check the *Encrypted* box to encrypt the value, if required.



6. Click . The new parameter is added in the list.


Global parameters added in the parent/root folder are inherited by the corresponding subfolders.




MODIFYING PARAMETERS


Steps:

On the **Parameters** tab, click the **Edit** icon of a parameter.
 The *Name*, *Value*, and *Encrypted* controls are enabled.



2. Make the necessary changes then click .







DELETING PARAMETERS

Steps:

On the **Parameters** tab, click the **Remove** icon
 of a parameter
 A confirmation message displays.




Refresh Parameters




Searching Parameters

To search for a particular parameter, enter it in the Search box.



You can also enter one of more characters into the *Search* box and the suggested list of parameters that matched the entries will be displayed.




[15] MANAGING WORKBOOK THEMES

Workbook themes are set of configurable settings that affect all colors and fonts of dashboards and visualizations in a workbook. This configuration also includes setting which among the <u>color palettes</u> will be available for the Color variable or shape palettes for the Shape variable in the visualizations. Furthermore, the general colors to be used in visualizations such as axis, background, border, and focus colors can be defined.


Theme files are independent of workbooks and can be uploaded to and downloaded from the server through the administration UI.

On an opened workbook, users can dynamically switch to one of the provided default workbook themes: **Light, Light2023**, **Dark,** or **Dark2023**.





The Themes tab allows management of these workbook themes which are stored in the repository on the server.



NOTE

In the previous versions of Panopticon, all of theme-related settings are part of the workbook style, making it difficult to dynamically switch styles (e.g., colors, fonts etc.)

When a workbook (created using versions before 17.5) is opened, all of the existing styles are extracted then saved as its inline workbook theme.


On the **Themes** tab, the following sections are available:

Property	Description
Search Theme	Entering text will filter the themes.
Toolbar	Allows copying, moving, and removing of themes. Also, to display the themes list either on <u>List View</u> or <u>Grid View</u> .
<u>Create Theme</u>	Allows creating new themes.
Theme Context Menu	Allows <u>uploading</u> , <u>renaming</u> , <u>moving</u> , <u>copying</u> , <u>downloading</u> , and <u>deleting</u> themes.


FOLDERS AND THEMES DISPLAY VIEW

Themes can be displayed either on a List or Grid View.

On the *Toolbar*, click **Grid View** . The folders and themes are displayed as thumbnails.




Or click **List View**, the themes are displayed in a standard listing.




On either display view style, clicking on a themes title or thumbnail displays the *Theme* page.

SEARCHING FOR THEMES

On the *Themes* tab, to search for a particular theme, enter it in the *Search Theme* box.



You can also enter one of more characters into the *Search Theme* box then click **Enter**. The suggested list of themes that matched the entries will be displayed.



Click on a theme to open the settings page.


To clear the filter, delete the text entry in the Search Theme box.

CREATING A NEW THEME

Creating a new theme allows setting the default or custom styles, color palettes, general colors, editor, and shape palettes to be used in workbooks and parts.


Steps:

On the *Themes* page, click
 The *New Theme* dialog displays.



2. Enter the name of the theme then click

The new theme is displayed on the *Theme* page.



- 3. When creating a new theme, you may specify the following properties:
 - <u>Default Styles</u> Define the default style settings of the workbook, parts, visualizations, filter box, action part title, legend title, and actions.
 - <u>Custom Styles</u> Define the settings of the custom styles.
 - <u>Color Palettes</u> Manage, import, or export Text, Sequential, and Diverging color palettes.
 - <u>General Colors</u> Define or create duplicate general color.
 - <u>Editor</u> Define the editor style settings.
 - <u>Shape Palettes</u> Define the settings of shape palettes and add, upload, download, duplicate, or remove them.
 - <u>Dashboard Templates</u> Update or delete default and new dashboard templates.

Defining the Default Style Settings of a Theme

When you define the default settings of a theme, you specify the colors and fonts of the workbook, visualizations, filter box, action part title, legend title, and action form.

Steps:

1. To define the default styles of the workbook, click **Workbook o**n the **Default Styles** tab. The *Workbook Settings* are displayed.

← StocksTheme Default Styles Custom Styles Color Palettes General Colors Editor Shape Palettes **Dashboard Templates Default Styles** Workbook Workbook Foreground #505050 Part Background #ffffff Visualization Primary #005776 Secondary Filter Box #2DCCD3 On Primary #FFFFFF Action Part Title Font Legend Title Noto Sans 12 Action Form Action Date Picker Action Button Action Dropdown **Action Text Box**


You may opt to modify the colors of the following properties:

Property	Description
Foreground	Foreground color of the workbook.
Background	Background color of the workbook.
Primary	Primary color of the workbook.
Secondary	Secondary color of the workbook.
On Primary	Foreground color within the primary color.


1.1. You can either:

Numeric Action Slider


• click the corresponding *Color* box to display the *Color* dialog to:




- o select the color, or
- click ★ to enter the valuesfor RGB



for HSL



for the Hex color code




or enter the Hex color code



1.2. Select the Font.



- 1.3. Specify the Font Size.
- 1.4. Specify whether **Bold** and **Italic**.
- 2. To define the default styles of the parts, click **Part** on the *Default Styles* pane. The *Part Settings* are displayed.



You may opt to modify the colors of the following properties:

Property	Description
Foreground	Foreground color of the parts.
Background	Background color of the parts.
Border	Border color of the parts.

- 2.1. Follow step 1.1 to define the visualization, title, and border colors.
- 2.2. Select the part's Font.
- 2.3. Specify the part's Font Size.
- 2.4. Specify whether Bold and Italic.
- 2.5. Specify the Padding of the parts.
 - 2.5.1. To modify the *Top*, *Right*, *Left*, and *Bottom* padding values, click


 The page updates to display the following fields:



- 2.5.2. Set the desired padding values. If the values are not the same, **Mixed** is displayed in the *Padding* field.
- 2.6. Specify the *Border Radius*. When set to **0px**, the border is displayed as a sharp corner. Setting to higher values makes the border more rounded.
- 2.7. Specify the Margin of the parts.
 - 2.7.1. To define the *Top*, *Right*, *Left*, and *Bottom* margin values, click



- 2.7.2. Set the desired margin values. If the values are not the same, **Mixed** is displayed in the *Margin* field.
- 3. To define the default styles of the visualizations, click **Visualization** on the *Default Styles* pane. The *Visualizations Settings* are displayed.



You may opt to modify the colors of the following properties:

Property	Description
Foreground	Foreground color of the visualizations and title.
Background	Background color of the visualizations and title.
Border	Border color of the visualizations.

- 3.1. Follow step 1.1 to define the visualization, title, and border colors.
- 3.2. Select the visualization and title's Font.
- 3.3. Specify the visualization and title's Font Size.

3.4. Specify whether **Bold** and **Italic**.

NOTE For the part title, **Bold** is selected by default.

- 3.5. Specify the Border Size of the visualizations.
- 3.6. Select the visualization title Alignment, Left, Center, or Right.
- 3.7. Specify the *Padding* of the visualizations.
 - 3.7.1. To modify the *Top*, *Right*, *Left*, and *Bottom* padding values, click


 The page updates to display the following fields:



- 3.7.2. Set the desired padding values. If the values are not the same, Mixed is displayed in the Padding field.
- 3.8. Specify the *Border Radius*. When set to **0px**, the border is displayed as a sharp corner. Setting to higher values makes the border more rounded.
- 3.9. Specify the Margin of the visualizations.
 - 3.9.1. To define the Top, Right, Left, and Bottom margin values, click



- 3.9.2. Set the desired margin values. If the values are not the same, **Mixed** is displayed in the *Margin* field.
- 3.10. You can opt to define the settings of the Title Rows.



By default, there are three title rows. You can do one of the following:

- Click Remove Style to delete, or
 Click + Add Title Row Style to add more title rows and define their settings.
- 4. To define the default styles of the filter box, click **Filter Box** on the *Default Styles* pane. The *Filter Box Settings* are displayed.



You may opt to modify the colors of the following properties:

Property	Description
Foreground	Foreground color of the filter box.
Background	Background color of the filter box.

- 4.1. Follow step 1.1 to define the colors of the filter box.
- 4.2. Select the filter box title's Font.
- 4.3. Specify the filter box title's Font Size.
- 4.4. Specify whether **Bold** and **Italic**.




- 4.5. Select the filter box title *Alignment*: **Left, Center,** or **Right**.
- 5. To define the default styles of the action part title, click **Action Part Title** on the *Default Styles* pane. The *Action Part Title Settings* are displayed.




- 5.1. Select the action part title's Font.
- 5.2. Specify the action part title's Font Size.
- 5.3. Specify whether **Bold** and **Italic**.

NOTE For the action part title, **Bold** is selected by default.

6. To define the default styles of the legend title, click **Legend Title** on the *Default Styles* pane. The *Legend Title Settings* are displayed.




- 6.1. Select the legend title's Font.
- 6.2. Specify the legend title's Font Size.
- 6.3. Specify whether **Bold** and **Italic**.



7. To define the default styles of the different actions (i.e., Action Form, Action Date Picker, Action Button, Action Dropdown, Action Text Box, Numeric Action Slider), click one and on the *Default Styles* pane to display their corresponding settings.


Most of these actions share the same settings as below:



You may opt to modify the colors of the following properties:


Property	Description
Foreground	Foreground color of the action, button, or slider.
Background	Background color of the action, button, or slider.

- 7.1. Follow step 1.1 to define the colors of the actions.
- 7.2. Select the action and button's Font.
- 7.3. Specify the action and button's Font Size.
- 7.4. Specify whether **Bold** and **Italic**.



- 7.5. Specify the action's border color and size.
- 7.6. Specify the Padding of the actions.
 - 7.6.1. To modify the *Top*, *Right*, *Left*, and *Bottom* padding values, click

 The page updates to display the following fields:



- 7.6.2. Set the desired padding values. If the values are not the same, **Mixed** is displayed in the *Padding* field.
- 7.7. Specify the *Border Radius*. When set to **0px**, the border is displayed as a sharp corner. Setting to higher values makes the border more rounded.
- 7.8. Specify the Margin of the actions.
 - 7.8.1. To define the *Top, Right, Left*, and *Bottom* margin values, click




- 7.8.2. Set the desired margin values. If the values are not the same, **Mixed** is displayed in the *Margin* field
- 8. Proceed to the **Custom Styles** tab to specify the <u>custom styles</u> of the theme.

Defining the Custom Style Settings of a Theme

Published custom style configuration of a part can be modified in the **Custom Styles** tab and can be applied to other parts.

Steps:

- 1. Click Custom Styles tab. The available published custom styles and properties are displayed.
 - ← StocksTheme




- 2. See <u>Define Default Styles</u> to specify the settings depending on the custom style part.
- 3. Proceed to the **Color Palettes** tab to define the <u>color palettes</u> of the theme.

Defining the Color Palettes Settings of a Theme

When you define the settings of the color palettes, you can manage, import, or export Text, Sequential, and Diverging color palettes.


Steps:

- 1. To select the *Diverging*, *Sequential*, and *Text* <u>color palettes</u> to use within the workbooks, click the **Color Palettes** tab
 - ← StocksTheme



- 2. Select the checkboxes of the provided color palettes that will be included for each category.
- 3. Click the radio button of the preferred Default color palette for each category.
- 4. To upload color palettes, click Import Palettes

 The Upload Color Palette dialog displays.



- 5. To export color palettes, you can either:
 - Click Export All Palettes

 for all color palettes. The ColorPalettes.excp file is exported.
 - Click the Export Palette icon of a color palette. The <ColorPaletteName>.excp file is exported.

You can move the exported file to the desired location.

- 6. To replace the color palettes, select the *Replace Color Palettes* checkbox.
- 7. Click Upload

A notification displays once the color palettes file is uploaded.

Click Cancel to close the dialog. The uploaded color palette is added in the list.

8. Proceed to the General Colors tab to specify the general colors of the theme.

Defining the General Color Settings of a Theme


You can specify new general colors or duplicate or remove them.

Steps:

1. To set the general colors to be used for visualizations, click the **General Colors** tab.


By default, the new *General Colors* is named **GeneralColorsLight**.

← StocksTheme




2. Click **Duplicate** \Box to make a duplicate copy of the new general colors.

← StocksTheme




- 3. You can enter a new name and click . Set Default is turned off and the Remove icon is now available.
- 4. Tap the **Set Default** slider to turn it on and the **Remove** icon is no longer available.

← StocksTheme



5. Click any of the color boxes to display the *Color* dialog.



Select or specify the new general colors: AxisColor, BackColor, BorderColor, FocusColor, ForeColor, MajorGridColor, MinorGridColor, MissingColor, SelectionColor. SnapshotColor,ZebraStripeColor.

Or enter the corresponding Hex color code.

6. Repeat steps 2 to 5 to add more general colors.

Once the new theme is saved and selected in the opened workbook, all of the defined *General Colors* will be added as options in the *General Colors* drop-down list of a *Color* variable in a visualization.

- 7. Select any of the general colors and tap the Set Default slider to make it the default.
- 8. Select any of the general colors that is not set as the default and click **Delete** to remove
- 9. Proceed to the **Editor** tab to specify the editor style of the **Dark** theme.


Defining the Editor Style Settings of a Theme

You can define the editor style settings of a dark theme.

Steps:

1. To set the Foreground, Background, Primary, On Primary, and Secondary colors for the editor style of the **Dark** theme, click the **Editor** tab.

← StocksTheme



- 2. Click on any of the color boxes to display the *Color* dialog and select or enter the preferred color.
- 3. Proceed to the **Shape Palettes** tab to specify the shape palettes of the theme.


Defining the Shape Palettes of a Theme

When you define the shape palettes of a theme, you specify the settings of shape palettes and add, upload, download, duplicate, or remove them.

Steps:

1. To set the shape palettes that can be used with the workbook theme, click the **Shape Palette** tab.

← StocksTheme



2. Proceed to the **Dashboard Templates** tab to specify the <u>dashboard templates</u> of the theme.


Defining the Dashboard Templates of a Theme

Default dashboard templates are provided in Panopticon. You can modify the name or delete default and new dashboard templates.


Steps:

To modify the dashboard templates that can be used with the workbook theme, click the Dashboard Templates
tab.

← StocksTheme




- 2. Click on a dashboard template, then you can either:
 - modify the Title, or
 - click to delete.
- 3. Click **Save** to save the new theme.
- 4. Clicking the displays the **Themes** tab page with the new theme added in the list.



THEMES TOOLBAR AND CONTEXT MENU

Moving, copying, and removing themes can either be done using:



The toolbar options include:

Toolbar Option	Description
Sort By / Sort Order	Allows sorting of themes by Name, Last Modified, or Last Modified By.
<u>Display View</u>	Display themes either by List View or Grid View.
Сору	Copy themes to another folder or subfolder where the user has permission.
Move	Move themes to another folder or subfolder where the user has permission.
Remove	Remove themes.

The context menu options include:

Toolbar Option	Description
<u>Upload Theme</u>	Upload theme.
Rename	Rename the theme.
Move	Move themes to another folder or subfolder where the user has permission.
Сору	Copy themes to another folder or subfolder where the user has permission.
Remove	Remove themes.

Sorting Themes


Sorting themes can be done by Name, Last Modified, or Last Modified By.

Steps:

On the Themes tab, either:

□ click the **Sort By** option on the *Toolbar* of the *Grid View*.

By default, the sorting is by Name.




- Name
- Last Modified

Then click the Sort Order.



□ click on the Name, Last Modified, or Last Modified By column header of the List View.




Then click the Sort Order.

- Ascending
- Descending


Renaming a Theme

Steps

1. Right-click on a theme then select **Rename** on the context menu.



The Rename Theme dialog displays.



2. Enter a new name then click

Rename


Moving Themes

Users with a Designer role are allowed to move themes to another folder or subfolder where they have permission.

Steps:

- 1. On the List or Grid view, select one or several themes then:
 - right-click and select Move on the context menu, or
 - click the **Move** icon on the toolbar.

The *Move Theme* dialog displays with the folder or subfolders that the user is allowed to move the themes. Select the folder or subfolder.



2. Click Move

The themes are moved and displayed on the selected folder.


Copying Themes

Users with a Designer role are allowed to copy themes to another folder or subfolder where they have permission.

Steps:

- 1. On the *List* or *Grid* view, select one or several themes then:
 - right-click and select Copy on the context menu, or
 - click the **Copy** icon on the toolbar.

The Copy Theme dialog displays with the folder or subfolders the user is allowed to copy the themes to. Select the folder or subfolder.




2. Click Copy

The themes are copied and displayed on the selected folder.

Downloading Themes

On the List or Grid view, right-click on a theme and selected **Download** on the context menu to download a copy.




You can copy this file to the desired location.

Uploading Themes


Users can upload their own workbook themes and also replace existing ones.

Steps:

1. Click on a folder of subfolder where the user has permission to upload a theme then select **Upload Theme** on the context menu.




The Upload Theme dialog displays.



2. To upload a workbook theme, either:

- drag the file from your desktop and drop on the dialog, or
- click Choose theme to upload and then browse and select one on the Open dialog that displays


The name of the workbook theme is displayed on the uploaded workbook palette area and in the *Name* box.



You can opt to rename the uploaded workbook theme.

- 3. To replace the workbook theme, check the *Replace Theme* box.
- 4. Click Upload

A notification displays once the file is uploaded.




The uploaded theme is added in the *Theme* list.

Deleting Themes

The default themes (Dark, Dark2023, Light, and Light2023) cannot be removed.


Steps:

- 1. Right-click on one or two themes then either:
 - select Remove on the context menu, or



• click the **Remove** icon on the toolbar.


A notification message displays.




2. Click Yes

COLOR PALETTES

The <u>single</u>, <u>sign</u>, <u>text</u>, <u>sequential</u>, and <u>diverging</u> color palettes that is used in text or numeric color variables in visualizations can be created, imported, exported, <u>modified</u>, <u>duplicated</u>, or <u>deleted</u> in the **Color Palettes** tab of a *Theme* page.



Text							+
Include	Name						
~	Coffee Bean	0	1	Ф	ŵ	=	
✓	Fourteen Colors	0	1	Ф		=	
~	Panopticon BI	0	1	Ф		=	
~	Seven Light Colors	0	1	4		=	
~	Seven Standard Colors	0	1	Ф		=	
~	Spectral	0	1	4	Ŵ	=	
~	Sunshine	0	1	Ф		=	
~	Twenty Eight Colors	0		Ф		=	
	Twenty Eight Colors Print	0	A STATE OF THE PARTY OF THE PAR	4		=	
✓	Vintage	0	1	Ф		=	
Sequentia							+
Include	Name						
~	Gray	0	1	4		=	
~	Purple-Orange	0	1	4	ŵ	=	
~	White-Blue		1	4		=	
	White-Blue-Print	0	A PORT	4		=	
~	White-Green	0	1	ď	i	=	
~	White-Orange	0	1	Ф		=	
~	White-Red	0	1	Ф		=	
	White-Red-Print	0	A Park	ß		=	
~	Yellow-Red	0	1	ď	i	=	




Importing a Color Palette

Users can upload their own color palettes.

Steps:

On the Color Palettes page click

On the Color Palettes pane, click
 The Upload Color Palette dialog displays.




- 2. To upload a color palette, either:
 - drag the file from your desktop and drop on the dialog, or
 - click Choose color palettes file to upload and then browse and select one on the Open dialog that displays

The name of the color palette is displayed on the uploaded color palette area.

3. To replace the color palettes, check the *Replace Color Palettes* box.




A notification displays once the color palettes file is uploaded.



Exporting Color Palette

You can either:



You can move the downloaded file to the desired location.

Creating a New Single Color Palette

These are the single colors that will be shared in a workbook for:

- records in Table and Record visualizations for the background, text, or shape
- visual members in Combination visualizations for the background or text

Light and medium single color palettes are provided in Panopticon Real Time, but you can also add new ones.


Steps:

On the Single section, click the Add Palette + icon.
 The New Single Palette dialog displays.



- 2. Enter the Title then click .
- 3. Click the Color box to display the Color dialog and set the palette color or enter the Hex color code.
- 4. Click Ok

The new single color palette is added in the list (e.g., **Medium Yellow**). Note that it is already included and can be <u>modified</u>, <u>duplicated</u>, and <u>deleted</u>.




Creating a New Sign Color Palette

The Sign color palette is used to signify the positive or negative values in numeric visual members.

Steps:

On the Sign section, click the Add Palette + icon.
 The New Sign Palette dialog displays.



- 2. Enter the *Title* then click .
- 3. To set the *Positive Color* (default is **Gray**) and the *Negative Color* (default is **Red**), click the **Color** box to display the *Color* dialog and select the palette color or enter the Hex color code.
- 4. Click Ok

The new Sign color palette is added in the list (e.g., **Red-Green**). Note that it is already included and can be <u>modified</u>, <u>duplicated</u>, and <u>deleted</u>.

Sign					+
Include	Name				
~	Light Orange-Blue	0		Ф	
~	Light Orange-Green	0	· A	凸	
~	Light Red-Blue	0	A.	凸	
~	Light Red-Green	0		Ф	
~	Medium Orange-Blue	0	A.	Ф	
~	Medium Orange-Green	0	A.	凸	
~	Medium Red-Blue	0	d'	4	
~	Medium Red-Green	0	, A.	Ф	
~	Red-Gray	O	d'	4	
~	Red-Green	0	, At	4	


Creating a New Text Color Palette

The configuration pane for the Color variable changes depending on the column data type.


In the Web Authoring, when a text column is added to the *Color* variable, the configuration pane displays the color associated with each categorical item, as specified with a default color palette (e.g., **Twenty Eight Colors**).

Steps:


On the Text section, click the New + icon.
 The Next Text Palette dialog displays.




- 2. Enter the *Title* then click .
- Select the *Number of Colors* in the drop-down list. Default is 28 colors.
 The *Other* list is updated accordingly.
- 4. To set the colors:
 - click the corresponding Color box to display the Color dialog to:




- select the color, or
- click ato enter the values
 for RGB



for HSL



for the Hex color code




• or enter the Hex color code





The new text color palette is added in the list (e.g., **Sixteen Colors**). Note that it can be <u>deleted</u>.



Creating a Sequential or Diverging Numeric Color Palette

Panopticon visualizations support two types of Numeric Color Palettes: Sequential and Diverging.

Sequential Color Palettes

Sequential palettes use a two-color gradient between a minimum and a maximum value. Numeric column containing only positive values default to a Sequential Palette using the **White-Blue** color palette.

In this case the range *Mid* point is disabled, and the *Min* and *Max* points are populated with defaults from the data set.

Diverging Color Palettes


Diverging Palettes use a three-color gradient between a minimum, middle and a maximum value. Numeric columns containing both positive and negative values default to the Diverging Palette with the **Red White Blue** color palette selected.

Diverging Palettes use the **Range Midpoint**. The *Min*, *Mid* and *Max* points are populated with defaults from the data set.

To create a new sequential numeric color palette:

1. On the Sequential section, click the **New** + icon.

The New Sequential Palette dialog displays.




- 2. Enter the Title and click .
- 3. Select the *Number of Colors* in the drop-down list. Default is **4** colors.

The number of colors from *Min* to *Max* is updated accordingly.

4. Set the Outliers, Min, and Max colors. Refer to step 4 of Creating a New Text Color Palette for more information.




The new sequential numeric color palette is added in the list and can be deleted (e.g., Green-Red).



To create a new diverging numeric color palette:

1. On the *Diverging* section, click the **New** + icon.

The New Diverging Palette dialog displays.




- 2. Enter the *Title* and click ...
- 3. Select the *Number of Colors* in the drop-down list. Default is **7** colors.

The number of colors from Min, Mid, to Max is updated accordingly.

4. Set the *Outliers*, *Min*, *Mid*, and *Max* colors. Refer to step 4 of <u>Creating a New Text Color Palette</u> for more information.



The new diverging numeric color palette is added in the list and can be deleted (e.g., Yellow-White-Red).



Modifying Color Palettes


Any of the included or checked color palettes can be modified.

NOTE

- For the selected default color palette, only the *Number of Colors* and assigned colors can be modified.
- Color palettes that are not selected cannot be modified.

Steps:


Click the Edit icon of an included or checked color palette.
 The corresponding dialog box displays.



- 2. Modify the Title, Number of Colors, and assigned colors.
- 3. Click to commit the changes or to revert to the original settings.

Creating a Duplicate of a Color Palette

Click the **Duplicate** icon of a color palette. A copy of the color palette is added in the list (e.g., **Seven Light Colors 1**).



You can opt to modify the settings.


Deleting Color Palettes

New or duplicate color palettes can be deleted. Click the **Delete** icon to remove the color palette in the list.

SHAPE PALETTES

Shape palettes that can be used with the workbook theme can be <u>created</u>, <u>uploaded</u>, <u>downloaded</u>, <u>modified</u>, <u>duplicated</u>, rearranged, or <u>deleted</u> on the <u>Shape Palettes</u> page.


← Light



Creating a New Shape Palette


Steps:

Click Add Palette + .
 A new shape palette displays (i.e., ShapePalette.0).




2. Click ShapePalette.<Number>.

The page changes to allow the definition of the new shape palette.



- 3. Enter the shape palette *Title* and click ...
- 4. To make this shape palette the default for the workbook theme, tap the **Default Palette** slider to turn it on.




5. To add the shapes, click +



You can either:

- click on a shape.
- click Add SVG
 Select one or more SVG files in the Open dialog box that displays.

The added shapes are displayed.




To delete a shape, click its corresponding **Delete** icon

- 6. Select the Default Shape in the drop-down list.
- 7. Click the Save

Uploading a Shape Palette


Users can upload their own shape palettes.

Steps:



- 2. To upload a shape palette, either:
 - drag the file from your desktop and drop on the dialog, or
 - click Choose shape palette file to upload and then browse and select one on the Open dialog that displays.


The name of the shape palette is displayed on the uploaded shape palette area and in the Name box.



You can opt to rename the uploaded shape palette.

3. Click Upload

A notification displays once the file is uploaded.



Click

to close the dialog. The uploaded shape palette is added in the list.

Downloading a Shape Palette

You can download a copy of any of the shape palettes.

Click the **Download** icon of a shape palette.

Modifying Shape Palettes

Any of the shape palettes can be modified.

Steps:

- 1. Click on a shape palette to display its settings.
- 2. You can modify the following properties:
 - Title
 - Default Palette. Tap to enable or disable.
 - Add or delete shapes
 - Default Shape
- 3. Click the **Save** icon to save the changes.

Creating a Duplicate of a Shape Palette

Click the **Duplicate** icon of a shape palette. A copy of the shape palette is added in the list (e.g., **Default Shape Palette 1**).



You can opt to modify the settings.


Rearranging Shape Palettes

The order of the shape palettes can be rearranged.


Steps:

- 1. Click on a shape palette you want to move.
 - The **Hand Hover** Y icon displays along with the blue marker before or after a shape palette where you can drop the item.
- 2. Drag and drop the shape palette to the desired position.


← Dark



← Dark



3. Click the Save



Deleting Shape Palettes

Any shape palette can be deleted except the default. Click the **Delete** icon to remove the shape palette in the list.

[16] PCLI: COMMAND UTILITIES FOR PANOPTICON REAL TIME

Panopticon Real Time is supplied with a command line utility PCLI.jar.

After extracting all of the contents of the pcli archive (pcli-java.zip), it is necessary to copy all of the JAR files from ...\apache-tomcat\webapps\panopticon\WEB-INF\lib\ to ...\pcli-java\lib\.

NOTE

Ensure to overwrite any existing files when copying all of the JAR files from ...\apache-tomcat\webapps\panopticon\WEB-INF\lib\ to ...\pcli-java\lib\.

This supports the following:

clearcache	Clears the cache on a Panopticon Real Time.
plugins	Troubleshoot the plugins that this program utilizes.
publish	Publishes a workbook to a <u>server</u> or <u>folder</u> .
version	Prints program (and optionally server) version and exits.
<u>help</u>	Use 'help <command/> ' to get help on a specific command.
<u>upgrade</u>	Upgrades specified workbook to the newest version.
schemify	Updates workbook data tables with missing schema information.
<u>exportdatasource</u>	Export workbook data sources.
convertpermissions	Converts old permission files to the new format.
<u>migratedatabasetojdbc</u>	Migrates all usages of the Database connector to JDBC Legacy connector in the given workbook/directory of workbooks.
<u>mockdata</u>	Updates workbook data tables with mock data based on the stored schema.
encrypt	Allows encryption of either a single text or an entire .properties file.
decrypt	Allows decryption of either a single text input or an encrypted .properties file.

Summary help is displayed through: [pcli-java folder]>java -jar pcli.jar help

More detailed help is displayed through: [pcli-java folder]>java -jar pcli.jar help [command]

Clearcache

Clears the cache in Panopticon Real Time.

Option	Description
-w,workbook	Workbook name. Syntax example: java -jar pcli.jar clearcache -w "workbook" -u "http://username:password@host:port/app_name/"
-d,datatable	Datatable name. Syntax example: java -jar pcli.jar clearcache -w "workbook" -d "datatable" -u "http://username:password@host:port /app_name/"
-u,url	URL to Panopticon Real Time, syntax: java -jar pcli.jar clearcache -u http://username:password@host:port/app_name/.

Command example: java -jar pcli.jar clearcache -w "How To Actions" -d

Plugins

Troubleshoot the plugins that this program utilizes.

Option	Description
-v,verbose	Print all information normally traced by the plugin manager.

Publish

You can either publish a workbook to a Panopticon Real Time or to a specific folder.

Publishing a Workbook to Panopticon Real Time

Publishes a workbook to Panopticon Real Time.

Option	Description
-f,force	Overwrite existing workbook on server. Syntax example: java -jar pcli.jar publish -w "workbook" -d -u "http://username:password@host:port/app_name/" -n "name" -f
-w,workbook	The workbook file to publish.

[&]quot;StocksTimeSeriesFilteredTimeParameters" -u

[&]quot;http://username:password123@localhost:8080/panopticon"

	Syntax example: java -jar pcli.jar publish -w "workbook" -u "http://username:password@host:port/app_name/"
-d,dataFiles	Find and upload data files used by workbook.
-u,url	URL to Panopticon Real Time, syntax: java -jar pcli.jar publish -w "workbook" -d -u "http://username:password@host:port/app_name/"
-n,name	Publish workbook with a different name. Syntax example: java -jar pcli.jar publish -w "workbook" -d -u "http://username:password@host:port/app_name/" -n "name"
local	Publishes workbook by file copy, instead of HTTP, for use when server exists on the local system. Specifies target file location path including file name. If the server is running, the application pool must be recycled after publication.
-ср	Java classpath. Syntax example: 'java -cp pcli.jar; [plugin dir]/* com.panopticon.dashboards.pcli.Pcli publish -w "workbook" -u "http://username:password@host:port/app_name/"

Command example: java -cp pcli.jar; lib/* com.panopticon.dashboards.pcli.Pcli publish -w "How To Actions.exw" -d -u "http://username:password123@localhost:8080/panopticon" -n "Published by pcli" -f

Publishing a Workbook to a Folder

Publishes a workbook to a specific folder.

Option	Description
-w,workbook	The workbook file to publish. Syntax example: java -jar pcli.jar publish -w "workbook" -u "http://username:password@host:port/app_name/"
-u,url	URL to Panopticon Real Time, syntax: java -jar pcli.jar publish -w "workbook" -d -u "http://username:password@host:port/app_name/" NOTE: The username in the -u command must have permission to the folder. Just being in the list of Administrators is not enough.
-n,name	Publish workbook to a folder on the server with a different name. Syntax example: java -jar pcli.jar publish -w "workbook" -d -u "http://username:password@host:port/app_name/" -n "folder\name"
-d,dataFiles	Find and upload data files used by workbook.

Command example: java -jar pcli.jar publish -w "E:\Temp\How to Actons.exw" -u
"http://username:password123@localhost:8080/panopticon" -n "test\How to
Actions.exw"

Publishing a Workbook Folder to Panopticon Real Time

Publishes a workbook folder to Panopticon Real Time.

Option	Description
-tf,targetFolder	The target folder to which workbooks will be published. Use -r to publish all workbooks to the ROOT folder. This is only applicable with -wf
	Syntax example: java -jar pcli.jar publish -u "http://username:password@host:port/app_name/" -wf "folder containing workbooks"-tf "server folder name" -r
-r,root	Publish workbooks to the ROOT folder. This is only applicable with -wf Syntax example: java -jar pcli.jar publish -u "http://username:password@host:port/app_name/" -wf "folder containing workbooks"-tf "server folder name" -r "default or root folder"
-u,url	URL to Panopticon Real Time, syntax: java -jar pcli.jar publish -w "workbook" -u "http://username:password@host:port/app_name/"
-wf,workbookFolder	The workbook folder from which workbooks will be picked to publish. Use -w to publish single workbook.
	Syntax example: java -jar pcli.jar publish -u "http://username:password@host:port/app_name/" -wf "folder containing workbooks"-tf "server folder name" -r

Command example: java -cp pcli.jar publish
"http://username:password123@localhost:8080/panopticon" -wf
"C:\Serverdata\Data" -tf "C:\Streamsdata\Data" -r

Version

Prints program (and optionally server) version and exits.

Option	Description
-u,url	URL to Panopticon Real Time, syntax: java -jar pcli.jar version -u "http://username:password@host:port/app_name/"

Command example: java -jar pcli.jar version -u
"http://username:password123@localhost:8080/panopticon"

Help

Lists all commands or options for a single command.

Command example: java -jar pcli.jar help access

Upgrade

Upgrades specified workbook to the newest version.

Option	Description
-w,workbook	Workbook path to upgrade. Syntax example: java -jar pcli.jar upgrade -w workbook.exw
-o,output	Output workbook path. Syntax example: java -jar pcli.jar upgrade -w workbook.exw -o workbook1.exw

Schemify

Updates workbook data tables with missing schema information.

Option	Description
dd,data-directory	Data directory path. Syntax example: java -jar pcli.jar schemify -wd "workbook directory" -od "output directory" -dd "C:\Users\Public\Documents\Datawatch Desktop\Data"
-D	Default parameter. This can be supplied either by using: -dp command to pass the path to Parameters.json which is the default parameter file Syntax example: java -jar pcli.jar schemify -w "workbook path" -o "output path" -l "license file path" -dp "default parameters file" -D switch to specify parameters Syntax example: java -jar pcli.jar schemify -w "workbook path" -o "output path" -l "license file path" -D "parameter=value"
-od,output-directory	Output directory path. Syntax example: java -jar pcli.jar schemify -wd "workbook directory" -od "C:\Users\Public\Documents\Datawatch Desktop\NewWorkbooks" -dd "data directory"
-w,workbook	Workbook to schemify.
-I,license-file	License file path. Syntax example: java -jar pcli.jar schemify -wd "workbook path" -o "output path" -l "C:\vizserverdata\PanopticonLicense.xml"
-wd,workbook-directory	Directory of the workbooks to schemify.
-o,output	Output path.

Exportdatasource

Export workbook data source.

Option	Description
-dd,data-directory	Data directory path.
-od,output-directory	Output directory path.
-w,workbook	Export data sources of workbook.
-l,license-file	License file path.
-wd,workbook-directory	Directory of workbooks.

Command example: java -jar pcli.jar exportdatasource -l "E:\projects\Dashboards
.NET\PanopticonLicense.xml" -w "E:\workbooks\exportdb.exw" -dd
"E:\Serverdata\export" -od "E:\Streamsdata\export" -wd "E:\workbooks"

Convertpermissions

Takes an old Workbooks folder and scans it for GroupAccessPermissions.xml files, collects them, and outputs a single file that can then be consumed by the server.

Option	Description
-wf, - workbookFolder	Path to old Workbooks folder, defaults to the current folder.
-o, - outputFile	Path to file where the result will be output. Default is stdout .
-wa, - writersAdmin	If users that had write permission on the old server should additionally get admin permission on the new server, defaults to not. The old server only had read and write , the new one has read , write , and admin .
-tf, - targetFolder	Path to subfolder on target server where you intend to import the workbooks, if not the root folder.

• Special treatment of empty input folders: If a workbook folder did not have a GroupAccessPermissions.xml file, the old server would treat it as if the "Everyone" group had both read and write access to it. This is made explicit in the PCLI verb, which adds this permission to the output. For example: pcli convertpermissions -wf /appdata17/Workbooks/ -o perms.json -wa -tf /migrated/ This creates perms.json which can then be used to restore the

- permissions from the old server on the new server if you import the old workbooks into the "migrated" workbook folder.
- See also the Panopticon.properties parameter repository.startup.apply.permissions.path.

MigrateDatabaseToJDBC

Migrates all usages of the Database connector to JDBC Legacy connector to enable editing in the Web Client.

Option	Description
-w, - workbook	Full path of workbook to migrate.
-o,output	Output path. Can be used together with the '-w' option, when a new name to migrated workbook is needed. Output directory should exist.
-od,output-directory	Output directory path. Output directory should exist.
-wd,workbook-directory	Directory of workbooks to upgrade.

Command example: java -jar pcli.jar migratedatabasetojdbc -w "E:\
\Workbooks\Database.exw" -o "E:\MigratedWorkbooks\JDBC.exw"

Mockdata

Updates workbook data tables with mock data based on the stored schema.

Option	Description
-w, - workbook	Workbook to mock the data table data.
-o,output	Output path.

Command example: java -jar pcli.jar mockdata -w "z Custom Index - v4
(2).exw" -o MockData.exw Workbooks\z Custom Index - v4: saved updated
workbook to MockData.exw

Encrypt

Allows encryption of either a single text or an entire .properties file.

Option	Description
-t,text	Text to encrypt.
-p,properties	Input Panopticon.properties file.
-o,output	Output property file.
-f,filter	Property filter regex.

Command examples:

.properties file

```
java -jar pcli.jar encrypt -p
/url/share/vizserverdata/Panopticon.properties -o Define.properties -f
.*password
```

text string

java -jar pcli.jar encrypt -t passwordName

Decrypt

Allows decryption of either a single text input or an encrypted .properties file.

Option	Description	
-t,text	Text to encrypt.	
-p,properties	Input Panopticon.properties file.	

Command examples:

.properties file

```
java -jar pcli.jar decrypt -p /usr/share/vizserverdata/Define.propertie$
```

text string

```
java -jar pcli.jar decrypt -t a7DUF0E0NaFBAqNI2W4NoA==
```

[17] REST INTERFACE

DISCLAIMER

As part of the deprecation of Desktop Designer and related legacy visualization- and data pipelines, we have unfortunately had to retire a set of previously documented REST service endpoints. The endpoints below will no longer be available in the product:

- GET media/image/dashboard
- GET media/image/dashboard/part

All Panopticon APIs should be considered proprietary, internal and subject to change. Going forward, all REST endpoints will be classified into private and publicly supported APIs. Please let us know if your implementation relies on REST API, to ensure that the functionality is made available in future public API

API

Panopticon Real Time exposes services through a REST API. You can use this for scripting and automation, and other tasks like review query statistics and monitor performance.

NOTE

You can use PCLI for some common tasks like upload a workbook and example workbooks to view server performance too.

There are two API groups: the public API which is being built out starting in version 2022.1, and the legacy API. Going forward, new services will only be added to the public API, and old services may migrate there. Other than that, the main differences are:

The public API	The legacy API
Is officially supported by Altair	Is "unsupported" in the sense that we cannot guarantee that an endpoint will stay unchanged or even remain between releases
Will evolve predictably in the future	
Is designed specifically for REST	Was designed when the server had both REST and SOAP APIs, so is a bit cumbersome from a REST perspective
Has endpoints that begin with /api, e.g., http://localhost:8080/panopticon/api/user/data/profile	Has endpoints that begin with /server/rest
Has documentation in OpenAPI 3 (see https://openapis.org) at /v3/api-docs/public, e.g., https://localhost:8080/panopticon/v3/api-docs/public	Has documentation in OpenAPI 2 (see https://swagger.io/specification/v2/) at / v2/api-docs

- Has a Swagger UI (see https://swagger.io/tools/swaggerui/) at /swagger-ui.html, e.g.,
 http://localhost:8080/panopticon/swagger-ui.html
- Has a Swagger UI at /swaggerui.html, but you need to select the legacy definition in the top bar

NOTE

The API documentation endpoints and Swagger UI are disabled by default. You need to set documentation.enabled=true in

<u>Panopticon.properties</u> (and restart the server) to use them. The REST endpoints and services themselves are always enabled. You should never enable the documentation on a production server.

EXPORT DATA

CSV

Panopticon Real Time provides the functionality to export data from a visualization to a CSV file.

Use the following URL to download the CSV file from the Server:

URL: http://[server]/[path]/server/rest/media/data/dashboard/part

Each URL has the following properties:

- Mandatory arguments
 - Workbook Workbook name without an extension.
 - Dashboard Dashboard name in the workbook.
 - Part The visualization part ID

The following examples show how to export the data of a visualization from a local server. For these examples, we have used the example workbook **How To Actions**.

- Export data as a CSV file
 - Syntax: http://[server]/[path]/server/rest/media/data/dashboard/part?workbook={Workbook name}&dashboard={Dashboard name}&part={Visualization part id}
 - Example:

 $\label{local-bound} $$ $$ http://localhost:8080/panopticon/server/rest/media/data/dashboard/part?workbook=How+To+Actions&dashboard=Data+Entry&part=visualization.Treemap1$

Dashboard Parameters

The CSV file can be generated based on the workbook data table parameters. The parameter and its values can be specified to determine the context of the exported data.

Syntax:

http://[server]/[path]/server/rest/media/data/dashboard/part?workbook={Workbo
ok name}&dashboard={Dashboard name}&part={Visualization part
id}&{dashboardParameterName1=value1}&{dashboardParameterName2=value2}

Adding Region=Europe and Industry=Financials parameters

Example:

http://localhost:8080/panopticon/server/rest/media/data/dashboard/part?workbook=How+To+Actions&dashboard=Scatter+of+Filtered+Universe&part=visualization.ScatterPlot1&Region=Europe&Industry=Financials

Adding Region=Asia Pacific, or Region=Europe and Industry= Financials parameters produces a CSV file that is focused on Asia Pacific & European Financials. In this case the Region parameter is repeated for each of the supplied regions.

Example:

http://localhost:8080/panopticon/server/rest/media/data/dashboard/part?workbook=How+To+Actions&dashboard=Scatter+of+Filtered+Universe&part=visualization.ScatterPlot1&Region=Asia+Pacific&Region=Europe&Industry=Financials

PDF

Panopticon Real Time provides the functionality to generate and download PDFs. Use the following URL to download PDFs from the server:

□ URL: http://[server]/panopticon/server/rest/media/pdf

The URL can be accessed through scheduled batch tasks to retrieve and process generated PDFs. (e.g., email to predefined mailing list).

Each URL has the following properties:

- Mandatory arguments
 - Workbook Workbook name without an extension.
- Optional arguments
 - Dashboard Dashboard name in the workbook.
 - HideScrollbars Show/Hide the visualization scrollbar in the PDF. Possible values are true/false. The
 default value is true.
 - EnablePagination Enable pagination in the PDF. Possible values are true/false. The default value is true.

The following examples show how to export a PDF from a local server. For these examples, we have used the example workbook **How To Actions**.

- ☐ Generate PDF report of the entire workbook
 - Syntax: http://[server]/[path]/server/rest/media/pdf?workbook={Workbook name}
 - Example: http://localhost:8080/panopticon/server/rest/media/pdf?workbook=How+To+Actions
- Generate PDF report of the entire workbook in a folder
 - Syntax: http://[server]/[path]/server/rest/media/pdf?workbook={Folder name%5CWorkbook name}
 - Example:

http://localhost:8080/panopticon/server/rest/media/pdf?workbook=my+folder%5CHow+To+Actions

NOTE

When the workbook name specifies any folder or subfolders, the path delimiter must be backslash (URL-encoded as %5C) and not forward slash (URL-encoded as %2F).

- Generate PDF report of a single dashboard in the workbook
 - Syntax: http://[server]/[path]/server/rest/media/pdf?workbook={Workbook name}&dashboard={Dashboard name}
 - Example:

Example (Multiple dashboards):

http://localhost:8080/panopticon/server/rest/media/pdf?workbook=How+To+Actions&dashboard=How+To+Actions&dashboard=Data+Entry

- Hide scrollbars from visualizations in the PDF
 - Syntax: http://[server]/[path]/server/rest/media/pdf?workbook={Workbook name}&hideScrollbars={true/false}
 - Example:

http://localhost:8080/panopticon/server/rest/media/pdf?workbook=How+To+Actions&hideScrollbars=true

- Enable or disable pagination of visualizations with vertical scrollbars in the PDF report
 - Syntax: http://[server]/[path]/server/rest/media/pdf?workbook={Workbook name}&enablePagination={true/false}
 - Example:

http://localhost:8080/panopticon/server/rest/media/pdf?workbook=How+To+Actions&enablePagination=true

Dashboard Parameters

The PDF report can be generated based on the workbook data table parameters. The parameter and its values can be specified to determine the context of the generated PDF report.

Syntax: http://[server]/[path]/server/rest/media/pdf?workbook={Workbook
name}&{dashboardParameterName1=value1}&{dashboardParameterName2=value2}

 $\begin{tabular}{ll} Adding \ {\tt Region=Europe} \ \ and \ {\tt Industry=Financials} \ \ parameters \end{tabular}$

Example:

http://localhost:8080/panopticon/server/rest/media/pdf?workbook=How+To+Actions&dashboard=Scatter+of+Filtered+Universe&Region=Europe&Industry=Financials

Adding Region=Asia Pacific, or Region=Europe and Industry= Financials parameters produces an output PDF that is focused on Asia Pacific & European Financials. In this case the Region parameter is repeated for each of the supplied regions.

Example:

http://localhost:8080/panopticon/server/rest/media/pdf?workbook=How+To+Action s&dashboard=Scatter+of+Filtered+Universe&Region=Asia+Pacific&Region=Europe&In dustry=Financials

Authentication

In order to generate certain workbooks, the user might need to be authenticated. The user will be prompted with a login window if the user tries to export a PDF from a web browser. The user can also send the credentials via a header to be authenticated. This could be necessary if the user is using commands like <code>wget</code> to invoke the server to generate PDFs.

The credentials are sent as basic authorization. The user provides the credentials in the Authorization header. The value is formatted in the following way: Basic username: password. Please note that the username and password must be Base64 encoded. Example: MyUsername: MyPassword = TX1Vc2VybmFtZTpNeVBhc3N3b3Jk Wget example: wget -0 "Output.pdf" --header="Authorization: Basic TX1Vc2VybmFtZTpNeVBhc3N3b3Jk" "http://localhost:8080/panopticon/server/rest/media/pdf?workbook=How+To+Action The PDF generator supports the following authentication mechanisms: **BASIC** LDAP \Box Filter authentication Header authentication Windows authentication

Excel Workbook

Panopticon Real Time provides the functionality to export a Panopticon workbook as an Excel workbook. All of the dashboards in the Panopticon workbook will be inserted into their own corresponding Excel sheet. In addition, all of the visualizations in the dashboard will be exported as a PNG image and inserted into an Excel sheet.

The images will be laid out as visualizations on the dashboard. However, the table visualizations will not be exported as images. The visualization tables will instead be exported as Excel tables. The Excel table will always be laid out under all of the exported visualization images.

Please note that only one table will be exported for each dashboard.

Use the following URL to download the Excel workbook from Panopticon Real Time:

URL: http://[server]/[path]/server/rest/media/excel

Each URL has the following properties:

- Mandatory arguments
 - Workbook Workbook name without an extension.
- Optional arguments
 - Dashboard Dashboard name(s) in the Panopticon workbook. All of the dashboards will be exported if no dashboard names are provided. The dashboard argument can be used multiple times depending on how many dashboards should be exported.
 - Width The width of the exported dashboards. The default value is 1024px.
 - **Height** The height of the exported dashboards. The default value is **768px**.
 - Style The Excel table style of an exported table. The default value is TableStyleMedium7.

The following examples show how to export an Excel workbook from a local server. For these examples, we have used the example workbook How To Actions.

- Generate and export Excel workbook
 - Syntax: http://[server]/[path]/server/rest/media/excel?workbook={Workbook name }

• **Example**: http://localhost:8080/panopticon/ server/rest/media/excel?workbook=How+To+Actions

Set dashboards

• **Syntax**: http://[server]/[path]/server/rest/media/excel?workbook={Workbook name}&dashboard={Dashboard name1}&dashboard={Dashboard name2}

• Example:

http://localhost:8080/panopticon/server/rest/media/excel?workbook=How+To+Actions&dashboard=Data+Entry&Dashboard=Time+Parameters

Set height and width for Dashboard

• Syntax: http://[server]/[path]/server/rest/media/excel?workbook={Workbook name}&width={value}&height={value}

Example:

http://localhost:8080/panopticon/server/rest/media/excel?workbook=How+To+Actions&width=512&height=384

Set Excel table style

Syntax: http://[server]/[path]/server/rest/media/excel?workbook={Workbook name}&style={Style}

• Example:

http://localhost:8080/panopticon/server/rest/media/excel?workbook=How+To+Actions&style=TableStyleMedium6

Possible Excel Table Styles

	TableStyleLight1-	TableStyleLight21
--	-------------------	-------------------

- □ TableStyleMedium1 TableStyleMedium28
- □ TableStyleDark1 TableStyleDark11

Dashboard Parameters

The Excel workbook can be generated based on the workbook data table parameters. The parameter and its values can be specified to determine the context of the generated Excel workbook.

Syntax: http://[server]/[path]/server/rest/media/excel?workbook={Workbook
name}&{dashboardParameterNamel=valuel}&{dashboardParameterName2=value2}

Adding Region=Europe and Industry=Financials parameters

Example:

http://localhost:8080/panopticon/server/rest/media/excel?workbook=How+To+Actions&Region=Europe&Industry=Financials

Adding Region=Asia Pacific, or Region=Europe and Industry= Financials parameters produces an Excel workbook that is focused on Asia Pacific & European Financials. In this case the Region parameter is repeated for each of the supplied regions.

Example:

http://localhost:8080/panopticon/server/rest/media/excel?workbook=How+To+Actions&Region=Asia+Pacific&Region=Europe&Industry=Financials

EMAIL DATA

NOTE

To allow the triggering of the email send out via the REST API, Panopticon Real Time must be configured with valid email server information in the Panopticon.properties file located in the AppData folder (e.g., C:\vizserverdata).

See Panopticon Real Time Configurations for Email Send Outs and Alerts for instructions.

PDF

Panopticon Real Time provides the functionality to generate and email PDFs.

This feature works exactly as the URL PDF generation and uses the same URL parameters. The main difference between the two features is that this feature sends the PDF in an email rather than downloading it as a file. Another difference is this feature requires a POST request to the following URL:

http://[server]/[path]/server/rest/media/pdf/email.

Usage

The following properties can be configured:

- URL: http://[server]/[path]/server/rest/media/pdf/email
- Method: POST
- □ Content-Type: application/json
- Request body:
 - bodyText The text will appear in the message body. The text can be formatted in HTML. Special
 characters, such as double quotation marks (") should have a backslash preceding them in order for the
 Server to regard them as special characters.
 - to One or more email recipients. Comma is used as a delimiter to separate the email recipients.
 - cc One or more email recipients. Comma is used as a delimiter to separate the email recipients.
 - **bcc** One or more email recipients. Comma is used as a delimiter to separate the email recipients.
 - sender The sender's email address. This value will also be used as a username.
 - senderpassword The password to the sender's email account.
 - **subject** the subject of the email.

Example

For example, an On-Demand PDF will be emailed based on the following information:

Property	Description
Workbook	How to Actions
Dashboard Name	Scatter of Filtered Universe
Recipients (To)	to-mail1@mail.com to-mail2@mail.com
Sender	from-mail@mail.com
Password	password
Subject	Altair PDF Generator
Body Message	Hello. This is an auto-generated PDF.

As an example:

Panopticon configuration (Panopticon.properties):

```
email.host=smtp.server.com
email.port=587
email.security.mode=TLS
```

URL:

http://localhost:8080/panopticon/server/rest/media/pdf/email?workbook=How+To+Actions&dashboard=Scatter+of+Filtered+Universe

Body:

```
"bodyText": "<h1>Hello.</h1>This is an auto-generated PDF.",
   "to": "to-maill@mail.com, to-mail2@mail.com",
   "sender": "from-mail@mail.com",
   "senderPassword": "password",
   "subject": "Altair PDF generator"
}
```

Image

Panopticon Real Time provides the functionality to generate and email dashboard images.

This feature is similar with Email PDF discussed above and uses the same URL parameters. However, this feature sends dashboard images as part of the email body and not as a PDF attachment. In addition, it does not support pagination.

In addition, hyperlinks can also be used in email dashboard images. Hyperlinks can redirect to a workbook and a dashboard in the server.

NOTE

In cases when you <u>schedule the emailing of dashboard images</u> or when you are behind a proxy or load balancer, it is recommended to specify the server address in the <code>Panopticon.properties</code> file.

For example:

server.host=http://www.company.com/dashboards/

The email contains the following Body components:

Body message: The email starts with the provided body message in the request.
Dashboard Title: The title displays before the dashboard image and uses a h2 heading tag
Dashboard image: The image (.png) of the dashboard.

Usage

ш	URL: http://[server]/[path]/server/rest/media/image/dashboard/email
	Method: POST
	Content-Type: application/json
	Request body:

- **bodyText** The text will appear in the message body. The text can be formatted in HTML. Special characters, such as double quotation marks (") should have a backslash preceding them in order for the Server to regard them as special characters.
- to One or more email recipients. Comma is used as a delimiter to separate the email recipients.
- cc One or more email recipients. Comma is used as a delimiter to separate the email recipients.
- **bcc** One or more email recipients. Comma is used as a delimiter to separate the email recipients.
- sender The sender's email address. This value will also be used as a username.
- senderpassword The password to the sender's email account.
- **subject** The subject of the email.
- **useHyperlink** The property that determines whether the images should be hyperlinks. The hyperlink then opens the dashboard in the Thin Client. Hyperlinks will be used when set to true (default value). The images will be regular images and not a hyperlink when the property is set to **false**.

Example

Property	Value
Workbook	How to Actions
Dashboard Name	Scatter of Filtered Universe
Recipients (To)	to-mail1@mail.com to-mail2@mail.com
Sender	from-mail@mail.com
Password	password
Subject	Altair Image Generator

Body Message	Hello. This email contains dashboard images.
Use hyperlink	true

As an example:

```
Panopticon configuration (panoption.properties):
email.host=smtp.server.com
email.port=587
email.security.mode=TLS
URL:
http://localhost:8080/panopticon/server/rest/media/image/dashboard/email?work
book=How+To+Actions&dashboard=Scatter+of+Filtered+Universe
Body:
{
    "bodyText": "<h1>Hello.</h1>This email contains dashboard
images.",
    "to": "to-mail1@mail.com, to-mail2@mail.com",
    "sender": "from-mail@mail.com",
    "senderPassword": "password",
    "subject": "Altair Image generator",
    "useHyperlink": "true"
}
```

[18] LOGGING/MONITORING

SERVER LOGGING

Log	ging occurs:
	Within the platform
	In the underlying web / application server
	In the underlying OS
Pan	opticon Real Time logs are written to the Tomcat logs folder.
The	logging level can be set from:
	Error – Only Errors are logged (the Default)
	Info – Operational logging is enabled including logging of data queries.
	Finest – All possible debugging logging is enabled.
	ically, when support issues are raised, the user is requested to change the logging level to INFO , which itionally records:
	Data Plugin (Visualization and Data Connector) Initialization
	Data Cache Initialization
	Data Subscriptions
	Data Queries including:
	Database connection settings
	Database SQL query

Data query logging capabilities are specific to each data connector, with the most detailed logging available for the Database and kdb+ connectors.

Panopticon Real Time logging and auditing capabilities include Java JMX counters for usage and load monitoring, and additional logging around secured access to workbooks.

Configuring Server Logs

Panopticon Real Time is preconfigured with recommended logging settings for performance. All of the logging will be directed to a file prefixed by panopticon in the Tomcat logs folder. The Panopticon-specific logging configuration file is located inside the .war file at WEB-INF/classes/logging.properties. This configuration takes precedence over the general Tomcat logging configuration. If the logging is to be configured in Tomcat, the file WEB-INF/classes/logging.properties must be removed from the .war file.

Number of rows & columns retrieved, and response time

Configuring Apache Tomcat Logs¹

A wah application rupping on Apparla Tamort con-

The internal logging for Apache Tomcat uses **JULI**, a packaged renamed fork of <u>Apache Commons Logging</u> that is hard-coded to use the <code>java.util.logging</code> framework. This ensures that Tomcat's internal logging and any web application logging will remain independent, even if a web application uses Apache Commons Logging.

To configure Tomcat to use an alternative logging framework for its internal logging, follow the instructions provided by the alternative logging framework for redirecting logging for applications that use <code>java.util.logging</code>. Keep in mind that the alternative logging framework will need to be capable of working in an environment where different loggers with the same name may exist in different class loaders.

A w	eb application running on Apache Torrical carr.
	Use any logging framework of its choice
	Use system logging API, java.util.logging
	Use the logging API provided by the Java Servlets specification: javax.servlet.ServletContext.log()

The logging frameworks used by different web applications are independent. See <u>class loading</u> for more details. The exception to this rule is <code>java.util.logging</code>. If it is used directly or indirectly by your logging library, then the elements of it will be shared across web applications because it is loaded by the system class loader.

Java Logging API (java.util.logging)

Apache Tomcat has its own implementation of several key elements of <code>java.util.logging</code> API. This implementation is called **JULI**. The key component there is a custom LogManager implementation, that is aware of different web applications running on Tomcat (and their different class loaders). It supports private per-application logging configurations. It is also notified by Tomcat when a web application is unloaded from memory, so that the references to its classes can be cleared, preventing memory leaks.

This <code>java.util.logging</code> implementation is enabled by providing certain system properties when starting Java. The Apache Tomcat startup scripts do this for you, but if you are using different tools to run Tomcat (such as jsvc, or running Tomcat from within an IDE), you should take care of them by yourself.

Servlets Logging APICalls to javax.servlet.ServletContext.log(...) to write log messages are handled by internal Tomcat logging. Such messages are logged to the category named

```
org.apache.catalina.core.ContainerBase.[${engine}].[${host}].[${context}]
```

This logging is performed according to the Tomcat logging configuration. You cannot overwrite it in a web application.

The Servlets logging API predates the <code>java.util.logging</code> API that is now provided by Java. As such, it does not offer you much options. e.g., you cannot control the log levels. It can be noted, though, that in Apache Tomcat implementation the calls to <code>ServletContext.log(String)</code> or <code>GenericServlet.log(String)</code> are logged at the <code>INFO</code> level. The calls to <code>ServletContext.log(String, Throwable)</code> or <code>GenericServlet.log(String, Throwable)</code> are logged at the <code>SEVERE</code> level.

Console

When running Tomcat on unixes, the console output is usually redirected to the file named catalina.out. The name is configurable using an environment variable. Whatever is written to System.err/out will be caught into that file. That may include:

							uncaughtExce	
_	Uncaudin	EVCENTIONS	DITILEG D	v iava.i	anu. Hiiba	uGIUUD.	uncaudiileace	DUOLIU

¹ http://tomcat.apache.org/tomcat-9.0-doc/logging.html

☐ Thread dumps, if you requested them via a system signal

When running as a service on Windows, the console output is also caught and redirected, but the file names are different.

The default logging configuration in Apache Tomcat writes the same messages to the console and to a log file. This is great when using Tomcat for development, but usually is not needed in production.

Old applications that still use System.out or System.err can be tricked by setting swallowOutput attribute on a Context. If the attribute is set to true, the calls to System.out/err during request processing will be intercepted, and their output will be fed to the logging subsystem using the javax.servlet.ServletContext.log(...) calls.

Note, that the **swallowOutput** feature is actually a trick, and it has its limitations. It works only with direct calls to System.out/err, and only during request processing cycle. It may not work in other threads that might be created by the application. It cannot be used to intercept logging frameworks that themselves write to the system streams, as those start early and may obtain a direct reference to the streams before the redirection takes place.

Access Logging

Access logging is a related but different feature, which is implemented as a **Valve**. It uses self-contained logic to write its log files. The essential requirement for access logging is to handle a large continuous stream of data with low overhead, so it only uses Apache Commons Logging for its own debug messages. This implementation approach avoids additional overhead and potentially complex configuration. Please refer to the <u>Valves</u> documentation for more details on its configuration, including the various report formats.

Using java.util.logging (Default)²

The default implementation of <code>java.util.logging</code> provided in the JDK is too limited to be useful. The key limitation is the inability to have per-web application logging, as the configuration is per-VM. As a result, Tomcat will, in the default configuration, replace the default LogManager implementation with a container friendly implementation called <code>JULI</code>, which addresses these shortcomings.

JULI supports the same configuration mechanisms as the standard JDK <code>java.util.logging</code>, using either a programmatic approach, or properties files. The main difference is that <code>per-classloader</code> properties files can be set (which enables easy redeployment friendly webapp configuration), and the properties files support extended constructs which allows more freedom for defining handlers and assigning them to loggers.

JULI is enabled by default, and supports per classloader configuration, in addition to the regular global java.util.logging configuration. This means that logging can be configured at the following layers:

\sim	_	oal	и.
 (-	וראו	าวเ	

That is usually done in the \${catalina.base}/conf/logging.properties file. The file is specified by the java.util.logging.config.file System property which is set by the startup scripts. If it is not readable or is not configured, the default is to use the \${java.home}/lib/logging.properties file in the JRE.

In the web application

The file will be WEB-INF/classes/logging.properties

The default logging.properties in the JRE specifies a ConsoleHandler that routes logging to System.err. The default conf/logging.properties in Apache Tomcat also adds several FileHandlers that write to files.

² http://tomcat.apache.org/tomcat-9.0-doc/logging.html

A handler's log level threshold is **INFO** by default and can be set using **SEVERE**, **WARNING**, **INFO**, **CONFIG**, **FINE**, **FINER**, **FINEST** or **ALL**. You can also target specific packages to collect logging from and specify a level.

To enable debug logging for part of Tomcat's internals, you should configure both the appropriate logger(s) and the appropriate handler(s) to use the FINEST or ALL level. e.g.:

```
org.apache.catalina.session.level=ALL
java.util.logging.ConsoleHandler.level=ALL
```

When enabling debug logging it is recommended that it is enabled for the narrowest possible scope as debug logging can generate large amounts of information.

The configuration used by JULI is the same as the one supported by plain <code>java.util.logging</code>, but uses a few extensions to allow better flexibility in configuring loggers and handlers. The main differences are:

A prefix may be added to handler names, so that multiple handlers of a single class may be instantiated. A prefix is a String which starts with a digit and ends with '.'. For example, 22foobar . is a valid prefix.
$\textbf{System property replacement is performed for property values which contain $ \{ \texttt{systemPropertyName} \}. \\$
If using a class loader that implements the org.apache.juli.WebappProperties interface (Tomcat's web application class loader does) then property replacement is also performed for \${classloader.webappName}, \${classloader.hostName} and \${classloader.serviceName} which are replaced with the web application name, the host name and the service name respectively.
By default, loggers will not delegate to their parent if they have associated handlers. This may be changed per logger using the loggerName.useParentHandlers property, which accepts a Boolean value.

The root logger can define its set of handlers using the .handlers property.

By default, the log files will be kept on the file system forever. This may be changed per handler using the handlerName.maxDays property. If the specified value for the property is <=0 then the log files will be kept on the file system forever, otherwise they will be kept the specified maximum days.

There are several additional implementation classes, that can be used together with the ones provided by Java. The notable one is org.apache.juli.FileHandler.

org.apache.juli.FileHandler supports buffering of the logs. The buffering is not enabled by default. To configure it, use the bufferSize property of a handler. The value of 0 uses system default buffering (typically an 8K buffer will be used). A value of <0 forces a writer flush upon each log write. A value >0 uses a BufferedOutputStream with the defined value but note that the system default buffering will also be applied.

Example logging.properties file to be placed in \$CATALINA BASE/conf:

```
handlers = 1catalina.org.apache.juli.FileHandler, \
         2localhost.org.apache.juli.FileHandler,
         3manager.org.apache.juli.FileHandler, \
         java.util.logging.ConsoleHandler
.handlers = 1catalina.org.apache.juli.FileHandler, java.util.logging.ConsoleHandler
# Handler specific properties.
# Describes specific configuration info for Handlers.
1catalina.org.apache.juli.FileHandler.level = FINE
lcatalina.org.apache.juli.FileHandler.directory = ${catalina.base}/logs
1catalina.org.apache.juli.FileHandler.prefix = catalina.
2localhost.org.apache.juli.FileHandler.level = FINE
2localhost.org.apache.juli.FileHandler.directory = ${catalina.base}/logs
2localhost.org.apache.juli.FileHandler.prefix = localhost.
3manager.org.apache.juli.FileHandler.level = FINE
3manager.org.apache.juli.FileHandler.directory = ${catalina.base}/logs
3manager.org.apache.juli.FileHandler.prefix = manager.
3manager.org.apache.juli.FileHandler.bufferSize = 16384
java.util.logging.ConsoleHandler.level = FINE
java.util.logging.ConsoleHandler.formatter = java.util.logging.SimpleFormatter
# Facility specific properties.
# Provides extra control for each logger.
org.apache.catalina.core.ContainerBase.[Catalina].[localhost].level = INFO
org.apache.catalina.core.ContainerBase.[Catalina].[localhost].handlers = \
  2localhost.org.apache.juli.FileHandler
org.apache.catalina.core.ContainerBase.[Catalina].[localhost].[/manager].level = INFO
org.apache.catalina.core.ContainerBase.[Catalina].[localhost].[/manager].handlers = \
  3manager.org.apache.juli.FileHandler
# For example, set the org.apache.catalina.util.LifecycleBase logger to log
# each component that extends LifecycleBase changing state:
#org.apache.catalina.util.LifecycleBase.level = FINE
```

Example logging.properties for the servlet-examples web application to be placed in WEB-INF/classes inside the web application:

```
handlers = org.apache.juli.FileHandler, java.util.logging.ConsoleHandler
# Handler specific properties.
# Describes specific configuration info for Handlers.
org.apache.juli.FileHandler.level = FINE
org.apache.juli.FileHandler.directory = ${catalina.base}/logs
org.apache.juli.FileHandler.prefix = ${classloader.webappName}.
java.util.logging.ConsoleHandler.level = FINE
java.util.logging.ConsoleHandler.formatter =
java.util.logging.SimpleFormatter
org.apache.catalina.core.ContainerBase.[Catalina].[localhost].[/manager].leve
org.apache.catalina.core.ContainerBase.[Catalina].[localhost].[/manager].hand
lers = \
   3manager.org.apache.juli.FileHandler
# For example, set the org.apache.catalina.util.LifecycleBase logger to log
# each component that extends LifecycleBase changing state:
#org.apache.catalina.util.LifecycleBase.level = FINE
```

AUDIT LOGGING

Panopticon Real Time can also produce audit logs. All of the audit logging will be directed to a file prefixed 'panopticon-audit' in the Tomcat log folder. The audit logs can be configured just like the regular logs produced by Panopticon Real Time. Refer to Configuring Panopticon Real Time Logs for more information on how to configure logs.

Panopticon Real Time is pre-configured to generate audit logs on an **INFO** level. Most of the messages are logged with **INFO** level. However, there are certain actions that are logged at different levels, such as **FINE**.

The audit logs contain the following information:

Attribute	Description
Timestamp	Timestamp for when the executed action occurred. The format of the timestamp is YYYY-mm-ddTHH: MM: SS (e.g., 2015-12-24T15:30:40).
Log Level	The severity of the log level.
Username	The username of the user that executed the action. The username will be ANONYMOUS if the user is not authenticated.
IP-address	The user's IP address.
Action	Detailed message about the executed action.

Audit logs use comma (,) as a delimiter to separate these values.

DATA LOG ACCESS IN DASHBOARDS

The subscription.data_log.always_on server property has a false default value. When set to true, the data log is always passed from server to client if the user is a Designer or Admin on the server. Previously, the data log would only be passed for workbooks in design mode.

The data log will be passed also when the data request fails. The "Invalid Configuration" message shown in the visualization will show a "Data Log" button, which will display the relevant logs and error message.

NOTE

The actual passing of runtime exception is currently implemented in the Kdb+connector only.

The benefit of running a server with subscription.data.log.always_on=true is that, the data log is more easily accessed and can be viewed both as success and failure. The data log can also be viewed without having **Write** permissions on the folder where the workbook is used, which is helpful when connection failures need to be examined in production environments where you have restrictions on workbook editing.

NOTE

Viewer users are not able to view the Data Log, only Designers and Admins.

SERVER MONITORING

Panopticon	Real Ti	me publ	ishes th	e following	ı JMX	counters:

- ServerDataRequestCount
- □ ActiveDataRequestCount
- InfoMessageCount
- ErrorMessageCount
- ActiveRealtimeSubscriptionCount
- LoadedWorkbooksCount
- MemoryStoreObjectCount
- ObjectCount

These can be accessed through any JMX monitoring toolset, such as Jconsole from the Java Development Kit (JDK).

As a basic configuration:

- 3. Download and install Java Development Kit (JDK)


 http://www.oracle.com/technetwork/java/javase/downloads/jdk8-downloads2133151.htm
- 4. Add the following parameters to your Tomcat:
 - -Dcom.sun.management.jmxremote.port=8855
 - Dcom.sun.management.jmxremote.authenticate=false

- -Dcom.sun.management.jmxremote.ssl=false
- 5. Open Jconsole. The jconsole executable can be found in <code>JDK_HOME/bin</code>, where <code>JDK_HOME</code> is the directory in which the Java Development Kit (JDK) is installed.
- 6. When the connection dialog opens, you are also given the option of connecting to a remote process.
 - Host name: name of the machine on which the Java VM is running.
 - Port number: the JMX agent port number you specified when you started the Java VM (e.g., 8855)

WEB PORTAL INTEGRATION

NOTE Set the documentation.enabled property in Panopticon.properties to true to view the documentation.

Panopticon workbooks can be embedded into existing portals with minimal effort. Open [tomcat]/panopticon/panopticon-api-doc/index.html to view the documentation.



SETTING THE SERVER METRICS PUBLISHER

The server performance metrics can be used to report, monitor, and configure the server's health and limits. The collected metrics may include the following information:

- □ Long polling, WebSocket, and total number of connections
- CPU loading percentage
- Maximum, size, and used Heap Bytes
- Subscription alerts, users, and total

- Number of parallel data loading and live threads
- Average data load time or refresh rate

You can configure the following properties in the $\underline{\texttt{Panopticon.properties}}$ file located in the $\underline{\texttt{AppData}}$ folder or $C: \forall izserverdata:$

Droporty	Comion Matrica
Property	Server Metrics
Attribute	metrics.authorization.level
Description	Specifies the required authorization level to get server metrics. Available values are ANONYMOUS , VIEWER , DESIGNER , ADMINISTRATOR .
	NOTE: This property is case sensitive.
Default Value	ADMINISTRATOR
Property	Server Metrics
Attribute	metrics.collection.rate
Description	Specifies the rate at which metrics are collected in milliseconds.
Default Value	1000
Property	Server Metrics
Attribute	metrics.file.flush.rate
Description	Specifies how often metrics should be saved to disk in milliseconds. Only used if the metrics.publisher.type is set to FILE.
Default Value	10000
Property	Server Metrics
Attribute	metrics.memory.queue.size
Description	Specifies how many metric entries are stored in memory. When the number of metrics goes above the specified value, the oldest value is removed to make room for the newest one (FIFO). Only used if the metrics.publisher.type is set to MEMORY.
Default Value	100
Property	Server Metrics
Attribute	metrics.publisher.configuration
Description	Specifies the id for which metric publisher configuration to use.
Default Value	
Property	Server Metrics
Attribute	metrics.publisher.type
Description	Specifies the current metric publisher that is used. Available values are NONE , MEMORY , FILE , EMAIL , INFLUX_DB , JDBC , KAFKA , KDB , MQTT , REST , TEXT .
Default Value	MEMORY

SETTING THE LOGGING LEVEL

Changes to the logging level can be made by altering the value of logger.level.file in the Panopticon.properties file. The server will not log messages with a lower/finer level than this value. The separate logging configuration still applies to route whatever messages that the server does log. This means that if you have set the file handler's level to **INFO** in the configuration, setting the property to **FINE** has no effect.

The default value of the property is set to **INFO**. At this level, most information needed for troubleshooting is logged, including many data queries, timing, and parameters. With a lower/finer level performance will be affected due to the amount of information logged.

[19] TROUBLESHOOTING

RESOLVING INSTALLATION ISSUES

Issues are investigated and resolved through investigation and controlled reproduction. Several known issues are included in the next section and predominately relate to problematic installations of Panopticon Real Time.

If you experience an unknown issue, send complete details to: dasupport@altair.com

Be sure to send this important information to Altair Support in the event of a problem.

Server Log

Panopticon Real Time log files are located in the [tomcat home] \logs folder.

The level of detail for these log files are configured at the "level" sections of logging.properties file in [tomcat home] \conf folder.

By default, it is set to Error, while the most verbose is Info.

Steps:

1. Edit the value of "level" in the logging.properties file:

From:

org.apache.catalina.core.ContainerBase.[Catalina].[localhost].level = ERROR

To:

org.apache.catalina.core.ContainerBase.[Catalina].[localhost].level = INFO

NOTE

Modifying the level setting will consume more disk space, so make sure to only do this while troubleshooting.

2. Restart Tomcat after making these changes.

NOTE

Refer to **Configuring Server Logs** for more information.

When sending your issue, include your workbook and associated data sources if the issue is specific to a particular workbook.

NO APPROPRIATE PROTOCOL ERROR WHEN PUBLISHING SPLUNK DATA ON PANOPTICON REAL TIME

The Altair log written into Panopticon Real Time log can report errors similar to the following:

Caused by: javax.net.ssl.SSLHandshakeException: No appropriate protocol (protocol is disabled or cipher suites are inappropriate)

This is caused by having the SSLv3 disabled by default in the updated versions of JDK.


Steps:


- 1. Open the /lib/security/java.security file.
- 2. Comment the following line: #jdk.tls.disabledAlgorithms=SSLv3
- 3. Save the updated file.

PIE CHARTS AND SHAPES NOT DISPLAYING CORRECTLY IN CHROME

When Hardware Acceleration is enabled in Chrome, Pie Chart and Shape visualization may not display as expected.

For example:





To resolve this issue, follow the steps below to disable Hardware Acceleration in Chrome:

- 1. Open the Chrome web browser.
- 2. You can either:
 - click to the right of the Address box and select Settings
 - Or enter chrome://settings in the Address box.
- 3. Scroll to the bottom of the page and click Show Advanced Settings...
- 4. Uncheck Use Hardware Acceleration when Available box.

System

- ✓ Continue running background apps when Google Chrome is closed
- Use hardware acceleration when available (requires Chrome restart)
- 5. Restart Chrome.

SESSION TOKENS NOT WORKING IN CHROME

Setting the authentication.token.persistence property to SESSION in Panopticon.properties removes the token from the browser if it is shutdown.

In Google Chrome, you can override the session functionality if you select **Continue where you left off** option in the *On startup* section. However, if you opt to use session cookies, select **Open the New Tab page** option.

Steps

- 1. Open the Chrome web browser.
- 2. You can either:
 - click to the right of the Address box and select Settings
 - Or enter chrome://settings in the Address box.
- 3. Scroll to the bottom of the page and on the On startup section, you can either select:
 - Open the New Tab page
 - To use the session cookies.
 - Continue where you left off

To override the session functionality.

4. Restart Chrome.

MANAGED ALTAIR UNITS LICENSE SSL ERROR

If you encounter the following issue when using Managed Altair Units license:

"SSL_ERROR_SSL

error:14007086:SSL routines:CONNECT_CR_CERT:certificate verify failed

unable to get local issuer certificate" Detail: SSL/TLS handshake failed

Follow the steps below to resolve this error:

- 1. Make sure you have installed all updates and are using the latest version of the product. The latest version is always available from the Marketplace.
- 2. Work with your IT department to create an exception in your proxy for the traffic going to our servers:
 - https://client.hhwu.altair.com
 - https://auth.hhwu.altair.com
 - https://auth.login.solidthinking.com
 - https://auth.admin.altairone.com
 - https://alas.admin.altairone.com


[20] KNOWN ISSUES


OUT OF MEMORY EXCEPTION

If the data is too big, an out of memory exception may occur. To increase the memory of Panopticon Real Time in Tomcat for Linux, refer to <u>Tomcat Memory Configuration for Linux</u> for more information.

[21] PANOPTICON RESOURCES

Clicking the user profile icon on the top right section of the toolbar displays the other Panopticon online resources that users with an Administrator role can access.





Select the Language on the drop-down list: English or Japanese.



Resource	Description
Release Notes	List of new features and fixed issues in the release.
Technical Fact Sheet	Overview of the Panopticon components which consists of: system requirements features supported data connectivity and visualizations custom code data connections, transforms, and ML model scoring filtering and data capabilities
Real Time Reference Guide	Panopticon Real Time documentation for users with an Administrator role which consists of: installation, system requirements, and licensing options supported authentication mechanisms advanced and optional steps or deployments system administration of the server including the logs, subscriptions, caches, scheduled tasks, and logged in users viewing and managing of workbooks and data templates creating and managing of data templates, global parameters, alerts, workbook themes PCLI command utilities REST API examples troubleshooting guide Panopticon.properties discussion Available upon installation.
Analyst Client User Guide	Panopticon Real Time documentation for users with a Viewer role which consists of: • viewing and analysing of workbooks • creating, monitoring, and deleting of alerts Available upon installation.
User Community	Link to the Panopticon User Community page.
Data Analytics Documentation	Link to the Altair Data Analytics Documentation page.

[APPENDIX]

PROPERTIES: PANOPTICON

The majority of configuration options for the server are set in the Panopticon.properties file in the <appdata> directory (e.g., C:\vizserverdata\). If this file does not exist when the server starts, it will create it with all default values. When the server starts after an upgrade, it may add new properties and remove deprecated ones.

You can optionally move sensitive properties like passwords and URLs from this file, where they are stored in clear text, into a file named Secret.properties in the same directory. The Secret.properties file stores values encrypted, and you can manage it with PCLI. A property can only be defined in one of these files at a time.

The following properties can be set in the property files:

Property	Access
Attribute	access.administrator.groups
Description	The role that is mapped to the administrator group.
Default Value	admin
Property	Access
Attribute	access.administrator.users
Description	Normally administrator access should be handled with the access.adminstrator.groups mapping, but for scenarios where the authentication cannot provide roles or you want to make exceptions for specific users, you can list individual usernames in this property. Any user listed here will get administrator access, regardless of their roles. Separate multiple users with the access.list.delimiter.
Default Value	
Property	Access
Attribute	access.default.roles
Description	The default roles applied to all users of the server. For example, if access.default.roles=DESIGNER,ADMINISTRATOR and a user with a VIEWER role logs on to the server, then the user will simultaneously have a VIEWER, DESIGNER, and ADMINISTRATOR roles. However, if no default roles are wanted, then leave the property blank. NOTE: The roles that can be assigned in this property can only be ADMINISTRATOR, VIEWER, ANONYMOUS, and/or DESIGNER. This property is case sensitive.
Default Value	VIEWER
Property	Access

Attribute	access.designer.groups
Description	The role that is mapped to the designer group.
Default Value	designer
Property	Access
Attribute	access.designer.users
Description	Normally designer access should be handled with the access.designer.groups mapping, but for scenarios where the authentication cannot provide roles or you want to make exceptions for specific users, you can list individual usernames in this property. Any user listed here will get designer access, regardless of their roles. Separate multiple users with the access.list.delimiter.
Default Value	
Property	Access
Attribute	access.list.delimiter
Description	The value delimiter to use when parsing access groups. Examples: access.list.delimiter=, access.administrator.groups=group1,group2 The groups are mapped to {'group1', 'group2'} access.list.delimiter=, access.administrator.groups=group1;group2,group3 The groups are mapped to {'group1;group2', 'group3'} access.list.delimiter=; access.administrator.groups=group1;group2,group3 The groups are mapped to {'group1', 'group2,group3'}
Default Value	',' (comma)
Property	Access
Attribute	access.viewer.groups
Description	The role that is assigned to the viewer group.
Default Value	
Property	Access
Attribute	access.viewer.users
Description	Normally viewer access should be handled with the access.viewer.groups mapping, but for scenarios where the authentication cannot provide roles or you want to make exceptions for specific users, you can list individual usernames in this property. Any user listed here will get viewer access, regardless of their roles.

	Separate multiple users with the access.list.delimiter.
Default Value	
Property	Alert
Attribute	alert.creation.only.by.administrators
Description	Enable or disable whether only the Administrators can create alerts.
Default Value	false
Property	Alert
Attribute	alert.detailed.logging
Description	Enables or disables extra alert logging.
Default Value	false
Property	Service authentication level
Attribute	authentication.domain
Description	The default domain information for user authentication.
Default Value	
Property	Authentication: Filter Token
Attribute	authentication.filter.authenticate.token
Description	Applies only if authentication.type is set to FILTER or is blank. If this property is set to true, the server will validate the token on incoming requests. If set to false, it ignores the token and authenticates based on the rest of the request instead.
Default Value	false
Property	Authentication: Header
Attribute	authentication.header.role.delimiter
Description	The delimiter used to separate the roles. Example: role1,role2,role3
Default Value	, (Comma)
Property	Authentication: Header
Attribute	authentication.header.roles
Description	The name of the header that contains all the roles.
Default Value	
Property	Authentication: Header
Attribute	authentication.header.rolesdynamic
Description	Supports the ability to create dynamic roles using free form patterns or string replacement. To create dynamic roles, use '{header value to be used}'. Example: authentication.header.rolesdynamic={HEADER_ROLES},financials,role_for_company_{EADER_COMPANY}

	Given this table:		
	KEY	VALUE	
	HEADER_ROLES	designer, watcher	
	HEADER_COMPANY	industrials, consumers	
	Then the roles to create to designer watcher financials role_for_company_ingrole_for_company_consultations		be the following:
Default Value			
Property	Authentication: Header		
Attribute	authentication.he	eader.username	
Description	The name of the header	that contains the username	
Default Value			
Property	Authentication: Header		
Attribute	authentication.he	eader.validate.toker	n
Description		If set to true , the authentication will validate the token. If set to false , the authentication of every request will be based on headers.	
Default Value			
Property	Authentication: Logout		
Attribute	authentication.lo	gout.redirect.url	
Description		eter. Clicking the logout butto	on redirects the user to the specified
	URL. If this property is not set,	user will be returned to the s	start page of Panopticon.
Default Value			
Property	Authentication: OAuth 2.0)	
Attribute	authentication.oa	auth2.client.id	
Description	The ID of the OAuth 2.0 of	client.	
Default Value			
Property	Authentication: OAuth 2.0)	
Attribute	authentication.oaut	th2.client.secret	
Description	The secret used by the C	Auth 2.0 client.	
Default Value			
Property	Authentication: OAuth 2.0)	

igner, ou=groups, de=openam, de=openidentityplatform, de=org contains two roles, admin and designer The regex to extract the roles is cn=([^,]+). Default Value Property Authentication: OAuth 2.0 Attribute authentication: OAuth 2.0 Attribute The attribute that will be extracted from the identity response and used as the username. Default Value Property Authentication: OAuth 2.0 Attribute authentication: OAuth 2.0 Attribute authentication oauth2.identity.method Description The method on how the access token is passed along in the identity request. Supported values are QUERY, BODY, and HEADER. Default Value QUERY Property Authentication: OAuth 2.0 Attribute authentication: OAuth 2.0 Attribute authentication.oauth2.identity.url Description The URL to the REST service that provides details about the authenticated user. Default Value Property Authentication: OAuth 2.0 Attribute authentication.oauth2.login.callback.url Description The callback URL. The URL should be the same as one of the specified callback URLs used by the client. The URL should refer to Panopticon Real Time. Default Value Property Authentication: OAuth 2.0 Attribute authentication: OAuth 2.0 A	A 44 mile + +4 -	authortication couth? identity attribute
Default Value Property Authentication: OAuth 2.0 Attribute authentication. oauth2.identity.attribute.roles.pattern Description Takes regex used to extract the roles from the OAuth 2.0 server identity response. For example, the returned string:		<u> </u>
Property Authentication: OAuth 2.0 Attribute Description Takes regex used to extract the roles from the OAuth 2.0 sever identity response. For example, the returned string: cn=admin, ou=groups, dc=openam, dc=openidentityplatform, dc=org, on=destigner, ou=groups, dc=openam, dc=openidentityplatform, dc=org contains two roles, admin and designer The regex to extract the roles is cn={{***}}. Default Value Property Authentication: OAuth 2.0 Attribute QUERY Property Authentication: OAuth 2.0 Attribute authentication: OAuth 2.0 At	•	I ne attribute that will be extracted from the <i>identity response</i> and used as the role.
Attribute Description Takes regex used to extract the roles from the OAuth 2.0 server identity response. For example, the returned string: cn=admin, ou=groups, dc=openam, dc=openidentityplatform, dc=org, cn=designer, ou=groups, dc=openam, dc=openidentityplatform, dc=org contains two roles, admin and designer The regex to extract the roles is cn=([^1,]+). Default Value Property Authentication: OAuth 2.0 Attribute authentication in OAuth 2.0 Attribute Description The attribute that will be extracted from the identity response and used as the username. Default Value Property Authentication: OAuth 2.0 Attribute authentication in OAuth 2.0 Attribute Description The method on how the access token is passed along in the identity request. Supported values are QUERY, BODY, and HEADER. Default Value QUERY Property Authentication: OAuth 2.0 Attribute Property Authentication: OAuth 2.0 Attribute Authentication: OAuth 2.0 Attribute Property Authentication: OAuth 2.0 Attribute authentication: OAuth 2.0 Attribute authentication: OAuth 2.0 Attribute Property Authentication: OAuth 2.0 Attribute authentication: OAuth 2.0		
Description Takes regex used to extract the roles from the OAuth 2.0 server identity response. For example, the returned string: cn=admin, ou=groups, dc=openam, dc=openidentityplatform, dc=org, cn=designer, ou=groups, dc=openam, dc=openidentityplatform, dc=org contains two roles, admin and designer The regex to extract the roles is cn=([^*,]+). Default Value Property Authentication: OAuth 2.0 Attribute authentication: Oauth 2.1 dentity.method Description The method on how the access token is passed along in the identity request. Supported values are QUERY, BODY, and HEADER. Default Value QUERY Property Authentication: OAuth 2.0 Attribute authentication: Oauth 2.1 dentity.url Description The URL to the REST service that provides details about the authenticated user. Default Value Property Authentication: OAuth 2.0 Attribute authentication: Oauth 2.1 dentity.url Description The callback URL. The URL should be the same as one of the specified callback URLs used by the client. The URL should refer to Panopticon Real Time. Default Value Property Authentication: OAuth 2.0 Attribute Property Authentication: OAuth 2.0 Attribute Authentication: OAuth 2.0 Attribute Authentication: OAuth 2.0 Attribute Property Authentication: OAuth 2.0 Attribute Authentication: OAuth 2.0 Attribute Authentication: OAuth 2.0 Attribute Property Authentication: OAuth 2.0 Attribute Authentication: OAuth 2.0 Attribute Authentication: OAuth 2.0 Attribute Property Authentication: OAuth 2.0 Attribute Property Authentication: OAuth 2.0 Attribute Authentication: OAuth 2.0 Attribute Authentication: OAuth 2.0 Attribute	Property	Authentication: OAuth 2.0
For example, the returned string:	Attribute	authentication.oauth2.identity.attribute.roles.pattern
Property Authentication: OAuth 2.0 Attribute authentication.oauth2.identity.attribute.username Description The attribute that will be extracted from the identity response and used as the username. Default Value Property Authentication: OAuth 2.0 Attribute authentication.oauth2.identity.method Description The method on how the access token is passed along in the identity request. Supported values are QUERY, BODY, and HEADER. Default Value QUERY Property Authentication: OAuth 2.0 Attribute authentication.oauth2.identity.url Description The URL to the REST service that provides details about the authenticated user. Property Authentication: OAuth 2.0 Attribute authentication: OAuth 2.0 Attribute authentication.oauth2.login.callback.url Description The callback URL. The URL should be the same as one of the specified callback URLs used by the client. The URL should refer to Panopticon Real Time. Default Value Property Authentication: OAuth 2.0 Attribute authentication.oauth2.login.redirect.url Description Redirects the user to the specified URL after successfully logging in. This property can be left blank, in which case the user is redirected to the URL they requested to access. Default Value	Description	For example, the returned string: cn=admin, ou=groups, dc=openam, dc=openidentityplatform, dc=org, cn=des igner, ou=groups, dc=openam, dc=openidentityplatform, dc=org contains two roles, admin and designer
Attribute authentication.oauth2.identity.attribute.username Description The attribute that will be extracted from the identity response and used as the username. Default Value Property Authentication: OAuth 2.0 Attribute authentication.oauth2.identity.method Description The method on how the access token is passed along in the identity request. Supported values are QUERY, BODY, and HEADER. Default Value QUERY Property Authentication: OAuth 2.0 Attribute authentication.oauth2.identity.url Description The URL to the REST service that provides details about the authenticated user. Default Value Property Authentication: OAuth 2.0 Attribute authentication.oauth2.login.callback.url Description The callback URL. The URL should be the same as one of the specified callback URLs used by the client. The URL should refer to Panopticon Real Time. Default Value Property Authentication: OAuth 2.0 Attribute authentication.oauth2.login.redirect.url Description Redirects the user to the specified URL after successfully logging in. This property can be left blank, in which case the user is redirected to the URL they requested to access. Default Value	Default Value	
Description The attribute that will be extracted from the identity response and used as the username. Property Authentication: OAuth 2.0 Attribute Authentication: oauth2.identity.method Description The method on how the access token is passed along in the identity request. Supported values are QUERY, BODY, and HEADER. Default Value QUERY Property Authentication: OAuth 2.0 Attribute Description The URL to the REST service that provides details about the authenticated user. Default Value Property Authentication: OAuth 2.0 Attribute authentication: Oauth2.login.callback.url Description The callback URL. The URL should be the same as one of the specified callback URLs used by the client. The URL should refer to Panopticon Real Time. Default Value Property Authentication: OAuth 2.0 Attribute Description Redirects the user to the specified URL after successfully logging in. This property can be left blank, in which case the user is redirected to the URL they requested to access. Default Value	Property	Authentication: OAuth 2.0
Property Authentication: OAuth 2.0 Attribute authentication.oauth2.identity.method Description The method on how the access token is passed along in the identity request. Supported values are QUERY, BODY, and HEADER. Default Value QUERY Property Authentication: OAuth 2.0 Attribute authentication.oauth2.identity.url Description The URL to the REST service that provides details about the authenticated user. Default Value Property Authentication: OAuth 2.0 Attribute authentication.oauth2.login.callback.url Description The callback URL. The URL should be the same as one of the specified callback URLs used by the client. The URL should refer to Panopticon Real Time. Default Value Property Authentication: OAuth 2.0 Attribute authentication.oauth2.login.redirect.url Description Redirects the user to the specified URL after successfully logging in. This property can be left blank, in which case the user is redirected to the URL they requested to access. Default Value	Attribute	authentication.oauth2.identity.attribute.username
Authentication: OAuth 2.0 Attribute authentication.oauth2.identity.method Description The method on how the access token is passed along in the identity request. Supported values are QUERY, BODY, and HEADER. Default Value QUERY Property Authentication: OAuth 2.0 Attribute authentication.oauth2.identity.url Description The URL to the REST service that provides details about the authenticated user. Default Value Property Authentication: OAuth 2.0 Attribute authentication: OAuth 2.1ogin.callback.url Description The callback URL. The URL should be the same as one of the specified callback URLs used by the client. The URL should refer to Panopticon Real Time. Default Value Property Authentication: OAuth 2.0 Attribute authentication: OAuth 2.0 Attribute authentication: OAuth 2.0 Attribute authentication.oauth2.login.redirect.url Description Redirects the user to the specified URL after successfully logging in. This property can be left blank, in which case the user is redirected to the URL they requested to access. Default Value	Description	The attribute that will be extracted from the identity response and used as the username.
Attribute authentication.oauth2.identity.method Description The method on how the access token is passed along in the identity request. Supported values are QUERY, BODY, and HEADER. Default Value QUERY Property Authentication: OAuth 2.0 Attribute authentication.oauth2.identity.url Description The URL to the REST service that provides details about the authenticated user. Default Value Property Authentication: OAuth 2.0 Attribute authentication.oauth2.login.callback.url Description The callback URL. The URL should be the same as one of the specified callback URLs used by the client. The URL should refer to Panopticon Real Time. Default Value Property Authentication: OAuth 2.0 Attribute authentication.oauth2.login.redirect.url Description Redirects the user to the specified URL after successfully logging in. This property can be left blank, in which case the user is redirected to the URL they requested to access.	Default Value	
Description The method on how the access token is passed along in the identity request. Supported values are QUERY, BODY, and HEADER. Default Value QUERY Authentication: OAuth 2.0 Attribute Description The URL to the REST service that provides details about the authenticated user. Default Value Property Authentication: OAuth 2.0 Attribute authentication: OAuth 2.0 Attribute Description The callback URL. The URL should be the same as one of the specified callback URLs used by the client. The URL should refer to Panopticon Real Time. Default Value Property Authentication: OAuth 2.0 Attribute authentication: OAuth 2.0 Attribute Authentication: OAuth 2.0 Redirects the user to the specified URL after successfully logging in. This property can be left blank, in which case the user is redirected to the URL they requested to access. Default Value	Property	Authentication: OAuth 2.0
Property Authentication: OAuth 2.0 Attribute Description The URL to the REST service that provides details about the authenticated user. Property Authentication: OAuth 2.0 Attribute Description The URL to the REST service that provides details about the authenticated user. Property Authentication: OAuth 2.0 Attribute authentication.oauth2.login.callback.url Description The callback URL. The URL should be the same as one of the specified callback URLs used by the client. The URL should refer to Panopticon Real Time. Property Authentication: OAuth 2.0 Attribute authentication.oauth2.login.redirect.url Description Redirects the user to the specified URL after successfully logging in. This property can be left blank, in which case the user is redirected to the URL they requested to access.	Attribute	authentication.oauth2.identity.method
Authentication: OAuth 2.0 Attribute authentication.oauth2.identity.url Description The URL to the REST service that provides details about the authenticated user. Default Value Property Authentication: OAuth 2.0 Attribute authentication.oauth2.login.callback.url Description The callback URL. The URL should be the same as one of the specified callback URLs used by the client. The URL should refer to Panopticon Real Time. Default Value Property Authentication: OAuth 2.0 Attribute authentication: OAuth 2.0 Attribute Authentication: OAuth 2.0 Attribute authentication.oauth2.login.redirect.url Description Redirects the user to the specified URL after successfully logging in. This property can be left blank, in which case the user is redirected to the URL they requested to access.		
Attribute authentication.oauth2.identity.url Description The URL to the REST service that provides details about the authenticated user. Default Value Property Authentication: OAuth 2.0 Attribute authentication.oauth2.login.callback.url Description The callback URL. The URL should be the same as one of the specified callback URLs used by the client. The URL should refer to Panopticon Real Time. Default Value Property Authentication: OAuth 2.0 Attribute authentication.oauth2.login.redirect.url Description Redirects the user to the specified URL after successfully logging in. This property can be left blank, in which case the user is redirected to the URL they requested to access.	Description	
Description The URL to the REST service that provides details about the authenticated user. Default Value Property Authentication: OAuth 2.0 Attribute Description The callback URL. The URL should be the same as one of the specified callback URLs used by the client. The URL should refer to Panopticon Real Time. Default Value Property Authentication: OAuth 2.0 Attribute authentication: oauth2.login.redirect.url Description Redirects the user to the specified URL after successfully logging in. This property can be left blank, in which case the user is redirected to the URL they requested to access. Default Value		values are QUERY, BODY, and HEADER.
Property Authentication: OAuth 2.0 Attribute authentication.oauth2.login.callback.url Description The callback URL. The URL should be the same as one of the specified callback URLs used by the client. The URL should refer to Panopticon Real Time. Property Authentication: OAuth 2.0 Attribute authentication.oauth2.login.redirect.url Description Redirects the user to the specified URL after successfully logging in. This property can be left blank, in which case the user is redirected to the URL they requested to access. Default Value	Default Value	values are QUERY, BODY, and HEADER. QUERY
Property Authentication: OAuth 2.0 Attribute Description The callback URL. The URL should be the same as one of the specified callback URLs used by the client. The URL should refer to Panopticon Real Time. Property Authentication: OAuth 2.0 Attribute Description Redirects the user to the specified URL after successfully logging in. This property can be left blank, in which case the user is redirected to the URL they requested to access. Default Value	Default Value Property	values are QUERY, BODY, and HEADER. QUERY Authentication: OAuth 2.0
Attribute authentication.oauth2.login.callback.url Description The callback URL. The URL should be the same as one of the specified callback URLs used by the client. The URL should refer to Panopticon Real Time. Property Authentication: OAuth 2.0 Attribute authentication.oauth2.login.redirect.url Description Redirects the user to the specified URL after successfully logging in. This property can be left blank, in which case the user is redirected to the URL they requested to access. Default Value	Default Value Property Attribute	values are QUERY, BODY, and HEADER. QUERY Authentication: OAuth 2.0 authentication.oauth2.identity.url
Description The callback URL. The URL should be the same as one of the specified callback URLs used by the client. The URL should refer to Panopticon Real Time. Default Value Property Authentication: OAuth 2.0 Attribute authentication.oauth2.login.redirect.url Description Redirects the user to the specified URL after successfully logging in. This property can be left blank, in which case the user is redirected to the URL they requested to access. Default Value	Default Value Property Attribute Description	values are QUERY, BODY, and HEADER. QUERY Authentication: OAuth 2.0 authentication.oauth2.identity.url
Default Value Property Authentication: OAuth 2.0 Attribute Description Redirects the user to the specified URL after successfully logging in. This property can be left blank, in which case the user is redirected to the URL they requested to access. Default Value	Default Value Property Attribute Description Default Value	values are QUERY, BODY, and HEADER. QUERY Authentication: OAuth 2.0 authentication.oauth2.identity.url The URL to the REST service that provides details about the authenticated user.
Property Authentication: OAuth 2.0 Attribute Description Redirects the user to the specified URL after successfully logging in. This property can be left blank, in which case the user is redirected to the URL they requested to access. Default Value	Default Value Property Attribute Description Default Value Property	values are QUERY, BODY, and HEADER. QUERY Authentication: OAuth 2.0 authentication.oauth2.identity.url The URL to the REST service that provides details about the authenticated user. Authentication: OAuth 2.0
Attribute authentication.oauth2.login.redirect.url Description Redirects the user to the specified URL after successfully logging in. This property can be left blank, in which case the user is redirected to the URL they requested to access. Default Value	Default Value Property Attribute Description Default Value Property Attribute	values are QUERY, BODY, and HEADER. QUERY Authentication: OAuth 2.0 authentication.oauth2.identity.url The URL to the REST service that provides details about the authenticated user. Authentication: OAuth 2.0 authentication.oauth2.login.callback.url The callback URL. The URL should be the same as one of the specified callback URLs
Description Redirects the user to the specified URL after successfully logging in. This property can be left blank, in which case the user is redirected to the URL they requested to access. Default Value	Default Value Property Attribute Description Default Value Property Attribute Description	values are QUERY, BODY, and HEADER. QUERY Authentication: OAuth 2.0 authentication.oauth2.identity.url The URL to the REST service that provides details about the authenticated user. Authentication: OAuth 2.0 authentication.oauth2.login.callback.url The callback URL. The URL should be the same as one of the specified callback URLs
left blank, in which case the user is redirected to the URL they requested to access. Default Value	Default Value Property Attribute Description Default Value Property Attribute Description Default Value	values are QUERY, BODY, and HEADER. QUERY Authentication: OAuth 2.0 authentication.oauth2.identity.url The URL to the REST service that provides details about the authenticated user. Authentication: OAuth 2.0 authentication.oauth2.login.callback.url The callback URL. The URL should be the same as one of the specified callback URLs used by the client. The URL should refer to Panopticon Real Time.
	Default Value Property Attribute Description Default Value Property Attribute Description Default Value Property Property Property	values are QUERY, BODY, and HEADER. QUERY Authentication: OAuth 2.0 authentication.oauth2.identity.url The URL to the REST service that provides details about the authenticated user. Authentication: OAuth 2.0 authentication.oauth2.login.callback.url The callback URL. The URL should be the same as one of the specified callback URLs used by the client. The URL should refer to Panopticon Real Time.
Promonths Authorities Objets CO	Default Value Property Attribute Description Default Value Property Attribute Description Default Value Property Attribute Attribute Property Attribute	values are QUERY, BODY, and HEADER. QUERY Authentication: OAuth 2.0 authentication.oauth2.identity.url The URL to the REST service that provides details about the authenticated user. Authentication: OAuth 2.0 authentication.oauth2.login.callback.url The callback URL. The URL should be the same as one of the specified callback URLs used by the client. The URL should refer to Panopticon Real Time. Authentication: OAuth 2.0 authentication: OAuth 2.0 authentication.oauth2.login.redirect.url Redirects the user to the specified URL after successfully logging in. This property can be
Property Authentication: OAuth 2.0	Default Value Property Attribute Description Default Value Property Attribute Description Default Value Property Attribute Description	values are QUERY, BODY, and HEADER. QUERY Authentication: OAuth 2.0 authentication.oauth2.identity.url The URL to the REST service that provides details about the authenticated user. Authentication: OAuth 2.0 authentication.oauth2.login.callback.url The callback URL. The URL should be the same as one of the specified callback URLs used by the client. The URL should refer to Panopticon Real Time. Authentication: OAuth 2.0 authentication: OAuth 2.0 authentication.oauth2.login.redirect.url Redirects the user to the specified URL after successfully logging in. This property can be

Attribute	authentication.oauth2.login.response.type
Description	The response type. The only response type that is currently supported is code .
Default Value	
Property	Authentication: OAuth 2.0
Attribute	authentication.oauth2.login.scope
Description	The requested scope.
Default Value	
Property	Authentication: OAuth 2.0
Attribute	authentication.oauth2.login.url
Description	The URL to the OAuth 2.0 login resource.
Default Value	
Property	Authentication: OAuth 2.0
Attribute	authentication.oauth2.logout.redirect.url
Description	Logging out revokes the token from the authentication server if the property authentication.oauth2.logout.url is set to the revocation URL. If this property is not set, the server will only remove its own token.
	If none of these properties are set, the server will attempt to redirect to the start page of the Panopticon when logging out.
Default Value	
Property	Authentication: OAuth 2.0
Attribute	authentication.oauth2.logout.url
Description	The URL to the OAuth 2.0 logout resource.
Default Value	
Property	Authentication: OAuth 2.0
Attribute	authentication.oauth2.token.method
Description	The method on how the token should be retrieved. Supported values are QUERY , BODY , and HEADER .
Default Value	
Property	Authentication: OAuth 2.0
Attribute	authentication.oauth2.token.url
Description	The URL to the OAuth 2.0 token resource.
Default Value	
Property	Service authentication level
Attribute	Authentication.required
Description	The property that will make the authentication required. It will force the user to login in order to use any of the services provided by the server.

Default Value	true
Property	Service authentication level
Attribute	authentication.role
Description	The authentication role.
Default Value	
Property	Authentication: SAML
Attribute	authentication.saml.assertion.roles
Description	User attribute for roles configured in the IdP.
Default Value	
Example	authentication.saml.assertion.roles=roles
Property	Authentication: SAML
Attribute	authentication.saml.assertion.username
Description	User attribute for username configured in the IdP.
Default Value	
Example	authentication.saml.assertion.username=name
Property	Authentication: SAML
Attribute	authentication.saml.assertionconsumerservice.url
Description	The URL to the Panopticon assertion consumer service. URL: [Protocol]://[Host]:[Port]/[Context]/server/rest/auth/login Example: http://localhost:8080/panopticon/server/rest/auth/login
Default Value	
Example	authentication.saml.assertionconsumerservice.url=http://localhost:8080/panopticon/server/rest/auth/login
Property	Authentication: SAML
Attribute	authentication.saml.certificate.name
Description	The name of the certificate used to validate signature and/or sign outgoing SAML messages
Default Value	
Example	authentication.saml.certificate.name=saml-cert
Property	Authentication: SAML
Attribute	authentication.saml.certificate.password
Description	The password of the certificate used to validate signature and/or sign outgoing SAML messages.
Default Value	
Property	Authentication: SAML

Attribute	authentication.saml.challenge.required
Description	This property determines whether the IdP-first authentication with SAML is enabled or not. To enable, set this property to false .
Default Value	true
Property	Authentication: SAML
Attribute	authentication.saml.identityprovider.certificate.file
Description	Takes a file path to a certificate file that contains the IdP's public key.
Default Value	
Property	Authentication: SAML
Attribute	authentication.saml.identityprovider.logout.url
Description	The URL to the IdP logout service.
Default Value	
Property	Authentication: SAML
Attribute	authentication.saml.identityprovider.signature.validation.required
Description	Specifies whether to require a valid IdP signature to be present on the SAML response. Default value is false .
Default Value	false
Property	Authentication: SAML
Attribute	authentication.saml.identityprovider.url
Description	The URL to the IdP login service.
Default Value	
Example	<pre>authentication.saml.identityprovider.url=https://192.168.99 .100:443/simplesaml/saml2/idp/SSOService.php</pre>
Property	Authentication: SAML
Attribute	authentication.saml.keystore.file
Description	The location of the Keystore file that contains the certificate.
Default Value	
Example	authentication.saml.keystore.file=D:/SAML/mykeystore.jks
Property	Authentication: SAML
Attribute	authentication.saml.keystore.password
Description	The password to the Keystore file.
Default Value	
Property	Authentication: SAML
Attribute	authentication.saml.keystore.type
Description	The key store type. Possible values are JKS , JCEKS , PKCS12 .

Default Value	JKS
Property	Authentication: SAML
Attribute	authentication.saml.login.redirect.url
Description	Redirects the user to the specified URL after successfully logging in. This property can be left blank, in which case the user is redirected to the URL they requested to access.
Default Value	
Property	Authentication: SAML
Attribute	authentication.saml.logout.redirect.url
Description	Redirects the user back to the specified URL after logging out. This is mainly used with a proxy. In which case, Panopticon Real Time does not know the endpoint which the user is going towards to, and therefore cannot redirect the user back to the Overview page. If you are using OpenAM this is required, otherwise this property can be left blank.
Default Value	
Property	Authentication: SAML
Attribute	authentication.saml.openam.meta.alias
Description	The meta alias for the IdP if you are using OpenAM.
Default Value	
Property	Authentication: SAML
Attribute	authentication.saml.protocolbinding
Description	Protocol binding for the use of SAML authentication. Possible values are HTTP-Redirect , HTTP-POST , HTTP-Artifact , HTTP-POST-SimpleSign , or SOAP .
Default Value	HTTP-Redirect
Property	Authentication: SAML
Attribute	authentication.saml.provider
Description	The IdP provider. Possible values are OPENSAML , OPENAM .
Default Value	OPENSAML
Property	Authentication: SAML
Attribute	authentication.saml.serviceprovider.id
Description	The ID of the service provider configured in the IdP.
Default Value	
Example	authentication.saml.serviceprovider.id=DwchFrontLocal8080
Property	Service authentication login request
Attribute	authentication.timeout.callback
Description	The timeout (in milliseconds) for the user between initiated login and callback. The default value is five minutes.
Default Value	300000

Property	Authentication: Token
Attribute	authentication.token.cookie
Description	The name of the cookie used to store the authentication cookie. Must be unique for each server instance on the host.
Default Value	ptoken
Property	Authentication: Token
Attribute	authentication.token.cookie.httponly
Description	This property determines how the browser will treat the cookie. If set to true , the cookie will be stored in the browser as a HttpOnly cookie and will not be available to the JavaScript. If set to false (default), the cookie will be stored in the browser as https and will be accessible to the JavaScript.
Default Value	false
Property	Authentication: Token
Attribute	authentication.token.cookie.samesite
Description	Used by browsers to control the behavior of same or cross origin requests. There are three possible values. Lax , Strict , and None . Please refer to browser specific documentation for its usage.
Default Value	Lax
Property	Authentication: Token
Attribute	authentication.token.cookie.secure
Description	The property determines how the browser will treat the cookie depending on the security of the connection. If set to true , when the browser receives a secure cookie (HttpOnly cookie), you will not be able to transmit it unless the connection is secure.
Default Value	false
Property	Authentication: Token
Attribute	authentication.token.domain
Description	Specifies the token cookie domain.
Default Value	
Property	Authentication: Token
Attribute	authentication.token.in.login.response.body
Description	This property determines if the REST login response body should contain a token info. NOTE: Does not affect the SOAP login response body.
Default Value	false
Property	Authentication: Token
Attribute	authentication.token.persistence
Description	This property is used to determine if the token should persist if the browser is closed or if it should only last while the browser is open. There are two possible values: PERSISTENT and SESSION . PERSISTENT will persist the token in the browser even if

Interior Kind. After modifying the property value to SESSION, ensure to clear the AppData/Token folder before starting the server. Property Authentication: Token Attribute Description This property determines if the token can refresh itself. The Web client can identify if the token is about to expire and then request a new token with the existing token. A token is refreshable if the property is set to true. The token will expire and invalidate the user session if the property is set to true. The token will expire and invalidate the user session if the property is set to false. Default Value Property Authentication: Token Attribute authentication. token. Secret Default Value Auto-generated Property Authentication: Token Attribute authentication. token.validity.seconds Description The number of seconds that the token should be valid. Default Value 604800 Property Service authentication level Attribute authentication.type Description The type of the authentication mechanism that will be used on the Server. Default Value BASIC Property Bookmark Administration Attribute bookmark.administration.only.by.administrators Description Set to true if only Administrators should be able to manage bookmarks. Default Value Property Bookmark Administration Attribute bookmark.show_shared Description Altows private bookmarking. If set to true, all of the users will be able to view each other's bookmarks. If set to false, bookmarks will only be viewed by the one who created them. Default Value Property Cache Attribute Cache Attribute		the browser has been closed and reopened. SESSION will remove the token from the browser if it is shutdown. IMPORTANT:
Property Authentication: Token Attribute authentication.token.refreshable Description This property determines if the token can refresh itself. The Web client can identify if the token is about to expire and then request a new token with the existing token. A token is refreshable if the property is set to true. The token will expire and invalidate the user session if the property is set to false. Default Value true Property Authentication: Token Attribute authentication.token.secret Description The secret is used to sign the token. The secret will be auto-generated when the server starts for the first time. NOTE: This value should be kept a secret. Default Value Auto-generated Property Authentication: Token Attribute authentication.token.validity.seconds Description The number of seconds that the token should be valid. Default Value 604800 Property Service authentication level Attribute authentication.type Description The type of the authentication mechanism that will be used on the Server. Default Value BASIC Property Bookmark Administration Attribute bookmark.administration.only.by.administrators Description Set to true if only Administrators should be able to manage bookmarks. Default Value false Property Bookmark Administration Attribute bookmark.show_shared Description Allows private bookmarking. If set to true, all of the users will be able to view each other's bookmarks. If set to false, bookmarks will only be viewed by the one who created them. Default Value true Property Cache		After modifying the property value to SESSION, ensure to clear the AppData/Token
Attribute authentication.token.refreshable Description This property determines if the token can refresh itself. The Web client can identify if the token is about to expire and then request a new token with the existing token. A token is refreshable if the property is set to true. The token will expire and invalidate the user session if the property is set to false. Default Value true Property Authentication: Token Attribute authentication.token.secret Description The secret is used to sign the token. The secret will be auto-generated when the server starts for the first time. NOTE: This value should be kept a secret. Default Value Auto-generated Property Authentication: Token Attribute authentication.token.validity.seconds Description The number of seconds that the token should be valid. Default Value 604800 Property Service authentication level Attribute authentication.type Description The type of the authentication mechanism that will be used on the Server. Default Value BASIC Property Bookmark Administration Attribute bookmark.administration.only.by.administrators Description Set to true if only Administrators should be able to manage bookmarks. Default Value false Property Bookmark Administration Attribute bookmark.show_shared Description Allows private bookmarking. If set to true, all of the users will be able to view each other's bookmarks. If set to false, bookmarks will only be viewed by the one who created them. Default Value true Property Cache	Default Value	PERSISTENT
Description This property determines if the token can refresh itself. The Web client can identify if the token is about to expire and then request a new token with the existing token. A token is refreshable if the property is set to true. The token will expire and invalidate the user session if the property is set to true. The token will expire and invalidate the user session if the property is set to true. The token will expire and invalidate the user session if the property is set to true. The secret will be auto-generated when the server starts for the first time. Note: This value should be kept a secret. Default Value Auto-generated Property Authentication: Token Attribute authentication: token.validity.seconds Description The number of seconds that the token should be valid. Default Value 604800 Property Service authentication level Attribute authentication.type Description The type of the authentication mechanism that will be used on the Server. Default Value BASIC Property Bookmark Administration Attribute bookmark.administration.only.by.administrators Description Set to true if only Administrators should be able to manage bookmarks. Default Value false Property Bookmark Administration Attribute bookmark.show_shared Description Allows private bookmarking. If set to true, all of the users will be able to view each other's bookmarks. If set to false, bookmarks will only be viewed by the one who created them. Default Value Property Cache	Property	Authentication: Token
token is about to expire and then request a new token with the existing token. A token is refreshable if the property is set to true. The token will expire and invalidate the user session if the property is set to false. Default Value true Property Authentication: Token Attribute authentication.token.secret Description The secret is used to sign the token. The secret will be auto-generated when the server starts for the first time. NOTE: This value should be kept a secret. Default Value Auto-generated Property Authentication: Token Attribute authentication.token.validity.seconds Description The number of seconds that the token should be valid. Default Value 604800 Property Service authentication level Attribute authentication.type Description The type of the authentication mechanism that will be used on the Server. Default Value BASIC Property Bookmark Administration Attribute bookmark.administration.only.by.administrators Description Set to true if only Administrators should be able to manage bookmarks. Default Value false Property Bookmark Administration Attribute bookmark.show_shared Description Allows private bookmarking. If set to true, all of the users will be able to view each other's bookmarks. If set to false, bookmarks will only be viewed by the one who created them. Default Value true Property Cache	Attribute	authentication.token.refreshable
Property Authentication: Token Attribute authentication.token.secret Description The secret is used to sign the token. The secret will be auto-generated when the server starts for the first time. NOTE: This value should be kept a secret. Default Value Auto-generated Property Authentication: Token Attribute authentication.token.validity.seconds Description The number of seconds that the token should be valid. Default Value 604800 Property Service authentication level Attribute authentication.type Description The type of the authentication mechanism that will be used on the Server. Default Value BASIC Property Bookmark Administration Attribute bookmark.administration.only.by.administrators Description Set to true if only Administrators should be able to manage bookmarks. Default Value false Property Bookmark Administration Attribute bookmark.show_shared Description Allows private bookmarking. If set to true, all of the users will be able to view each other's bookmarks. If set to false, bookmarks will only be viewed by the one who created them. Default Value true Property Cache	Description	token is about to expire and then request a new token with the existing token. A token is refreshable if the property is set to true . The token will expire and invalidate the user
Attribute authentication.token.secret Description The secret is used to sign the token. The secret will be auto-generated when the server starts for the first time. NOTE: This value should be kept a secret. Default Value Auto-generated Property Authentication: Token Attribute authentication.token.validity.seconds Description The number of seconds that the token should be valid. Default Value 604800 Property Service authentication level Attribute authentication.type Description The type of the authentication mechanism that will be used on the Server. Default Value BASIC Property Bookmark Administration Attribute bookmark.administration.only.by.administrators Description Set to true if only Administrators should be able to manage bookmarks. Default Value false Property Bookmark Administration Attribute bookmark.show_shared Description Allows private bookmarking. If set to true, all of the users will be able to view each other's bookmarks. If set to false, bookmarks will only be viewed by the one who created them. Default Value true Property Cache	Default Value	true
Description The secret is used to sign the token. The secret will be auto-generated when the server starts for the first time. NOTE: This value should be kept a secret. Default Value Auto-generated Property Authentication: Token Attribute authentication.token.validity.seconds Description The number of seconds that the token should be valid. Default Value 604800 Property Service authentication level Attribute authentication.type Description The type of the authentication mechanism that will be used on the Server. Default Value BASIC Property Bookmark Administration Attribute bookmark.administration.only.by.administrators Description Set to true if only Administrators should be able to manage bookmarks. Default Value false Property Bookmark Administration Attribute bookmark.show_shared Description Allows private bookmarking. If set to true, all of the users will be able to view each other's bookmarks. If set to false, bookmarks will only be viewed by the one who created them. Default Value Property Cache	Property	Authentication: Token
starts for the first time. NOTE: This value should be kept a secret. Default Value Auto-generated Property Authentication: Token Attribute authentication.token.validity.seconds Description The number of seconds that the token should be valid. Default Value 604800 Property Service authentication level Attribute authentication.type Description The type of the authentication mechanism that will be used on the Server. Default Value BASIC Property Bookmark Administration Attribute bookmark.administration.only.by.administrators Description Set to true if only Administrators should be able to manage bookmarks. Default Value false Property Bookmark Administration Attribute bookmark.show_shared Description Allows private bookmarking. If set to true, all of the users will be able to view each other's bookmarks. If set to false, bookmarks will only be viewed by the one who created them. Default Value Property Cache	Attribute	authentication.token.secret
Property Authentication: Token Attribute authentication.token.validity.seconds Description The number of seconds that the token should be valid. Default Value 604800 Property Service authentication level Attribute authentication.type Description The type of the authentication mechanism that will be used on the Server. Default Value BASIC Property Bookmark Administration Attribute bookmark.administration.only.by.administrators Description Set to true if only Administrators should be able to manage bookmarks. Default Value false Property Bookmark Administration Attribute bookmark.show_shared Description Allows private bookmarking. If set to true, all of the users will be able to view each other's bookmarks. If set to false, bookmarks will only be viewed by the one who created them. Default Value true Property Cache	Description	starts for the first time.
Property Authentication: Token Attribute authentication.token.validity.seconds Description The number of seconds that the token should be valid. Default Value 604800 Property Service authentication level Attribute authentication.type Description The type of the authentication mechanism that will be used on the Server. Default Value BASIC Property Bookmark Administration Attribute bookmark.administration.only.by.administrators Description Set to true if only Administrators should be able to manage bookmarks. Default Value false Property Bookmark Administration Attribute bookmark.show_shared Description Allows private bookmarking. If set to true, all of the users will be able to view each other's bookmarks. If set to false, bookmarks will only be viewed by the one who created them. Default Value true Property Cache		-
Attribute authentication.token.validity.seconds Description The number of seconds that the token should be valid. Default Value 604800 Property Service authentication level Attribute authentication.type Description The type of the authentication mechanism that will be used on the Server. Default Value BASIC Property Bookmark Administration Attribute bookmark.administration.only.by.administrators Description Set to true if only Administrators should be able to manage bookmarks. Default Value false Property Bookmark Administration Attribute bookmark.show_shared Description Allows private bookmarking. If set to true, all of the users will be able to view each other's bookmarks. If set to false, bookmarks will only be viewed by the one who created them. Default Value true Property Cache		Auto-generated
Description The number of seconds that the token should be valid. Default Value 604800 Property Service authentication level Attribute authentication.type Description The type of the authentication mechanism that will be used on the Server. Default Value BASIC Property Bookmark Administration Attribute bookmark.administration.only.by.administrators Description Set to true if only Administrators should be able to manage bookmarks. Default Value false Property Bookmark Administration Attribute bookmark.show_shared Description Allows private bookmarking. If set to true, all of the users will be able to view each other's bookmarks. If set to false, bookmarks will only be viewed by the one who created them. Default Value true Property Cache	Property	
Default Value 604800 Property Service authentication level Attribute authentication.type Description The type of the authentication mechanism that will be used on the Server. Default Value BASIC Property Bookmark Administration Attribute bookmark.administration.only.by.administrators Description Set to true if only Administrators should be able to manage bookmarks. Default Value false Property Bookmark Administration Attribute bookmark.show_shared Description Allows private bookmarking. If set to true, all of the users will be able to view each other's bookmarks. If set to false, bookmarks will only be viewed by the one who created them. Default Value true Property Cache	Attribute	authentication.token.validity.seconds
Property Service authentication level Attribute authentication.type Description The type of the authentication mechanism that will be used on the Server. Default Value BASIC Property Bookmark Administration Attribute bookmark.administration.only.by.administrators Description Set to true if only Administrators should be able to manage bookmarks. Default Value false Property Bookmark Administration Attribute bookmark.show_shared Description Allows private bookmarking. If set to true, all of the users will be able to view each other's bookmarks. If set to false, bookmarks will only be viewed by the one who created them. Default Value true Property Cache	Description	The number of seconds that the token should be valid.
Attribute authentication.type Description The type of the authentication mechanism that will be used on the Server. Default Value BASIC Property Bookmark Administration Attribute bookmark.administration.only.by.administrators Description Set to true if only Administrators should be able to manage bookmarks. Default Value false Property Bookmark Administration Attribute bookmark.show_shared Description Allows private bookmarking. If set to true, all of the users will be able to view each other's bookmarks. If set to false, bookmarks will only be viewed by the one who created them. Default Value true Property Cache	Default Value	604800
Description The type of the authentication mechanism that will be used on the Server. Default Value BASIC Property Bookmark Administration Attribute bookmark.administration.only.by.administrators Description Set to true if only Administrators should be able to manage bookmarks. Default Value false Property Bookmark Administration Attribute bookmark.show_shared Description Allows private bookmarking. If set to true, all of the users will be able to view each other's bookmarks. If set to false, bookmarks will only be viewed by the one who created them. Default Value true Property Cache	Property	Service authentication level
Default Value BASIC Property Bookmark Administration Attribute bookmark.administration.only.by.administrators Description Set to true if only Administrators should be able to manage bookmarks. Default Value false Property Bookmark Administration Attribute bookmark.show_shared Description Allows private bookmarking. If set to true, all of the users will be able to view each other's bookmarks. If set to false, bookmarks will only be viewed by the one who created them. Default Value true Property Cache	Attribute	authentication.type
Property Bookmark Administration Attribute bookmark.administration.only.by.administrators Description Set to true if only Administrators should be able to manage bookmarks. Default Value false Property Bookmark Administration Attribute bookmark.show_shared Description Allows private bookmarking. If set to true, all of the users will be able to view each other's bookmarks. If set to false, bookmarks will only be viewed by the one who created them. Default Value true Property Cache	Description	The type of the authentication mechanism that will be used on the Server.
Attribute bookmark.administration.only.by.administrators Description Set to true if only Administrators should be able to manage bookmarks. Default Value false Property Bookmark Administration Attribute bookmark.show_shared Description Allows private bookmarking. If set to true, all of the users will be able to view each other's bookmarks. If set to false, bookmarks will only be viewed by the one who created them. Default Value true Property Cache	Default Value	BASIC
Description Set to true if only Administrators should be able to manage bookmarks. Default Value False Bookmark Administration Attribute bookmark.show_shared Allows private bookmarking. If set to true, all of the users will be able to view each other's bookmarks. If set to false, bookmarks will only be viewed by the one who created them. Default Value true Property Cache	Property	Bookmark Administration
Default Value Property Bookmark Administration Attribute bookmark.show_shared Description Allows private bookmarking. If set to true, all of the users will be able to view each other's bookmarks. If set to false, bookmarks will only be viewed by the one who created them. Default Value true Property Cache	Attribute	bookmark.administration.only.by.administrators
Property Bookmark Administration Attribute bookmark.show_shared Description Allows private bookmarking. If set to true, all of the users will be able to view each other's bookmarks. If set to false, bookmarks will only be viewed by the one who created them. Default Value true Property Cache	Description	Set to true if only Administrators should be able to manage bookmarks.
Attribute bookmark.show_shared Description Allows private bookmarking. If set to true, all of the users will be able to view each other's bookmarks. If set to false, bookmarks will only be viewed by the one who created them. Default Value true Property Cache	Default Value	false
Description Allows private bookmarking. If set to true , all of the users will be able to view each other's bookmarks. If set to false , bookmarks will only be viewed by the one who created them. Default Value true Cache	Property	Bookmark Administration
bookmarks. If set to false , bookmarks will only be viewed by the one who created them. Default Value	Attribute	bookmark.show_shared
Property Cache	Description	
	Default Value	true
Attribute cache.data.datasource.enabled	Property	Cache
	Attribute	cache.data.datasource.enabled

Description	Enable or disable the caching of the data source.
Default Value	true
Property	Cache
Attribute	cache.data.datasource.size
Description	The data source cache size.
Default Value	100
Property	Cache
Attribute	cache.data.datasource.type
Description	The data source cache type.Allowed values: MEMORY, NONE
Default Value	MEMORY
Property	Cache
Attribute	cache.data.datatable.enabled
Description	Enable or disable the caching of the data table.
Default Value	true
Property	Cache
Attribute	cache.data.datatable.size
Description	The data table cache size.
Default Value	100
Property	Cache
Attribute	cache.data.datatable.type
Description	The data table cache type.Allowed values: MEMORY, NONE
Default Value	MEMORY
Property	Cache
Attribute	cache.data.query.enabled
Description	Enable or disable the caching of data query.
Default Value	true
Property	Cache
Attribute	cache.data.query.size
Description	The data query cache size.
Default Value	100
Property	Cache
Attribute	cache.data.query.type
Description	The data query cache type.Allowed values: MEMORY, NONE

Default Value	MEMORY
Property	Cache
Attribute	cache.plugin.id
Description	The ID of the plugin that will be used to store data. Possible values: BinaryTableFile-Cache .
Default Value	BinaryTableFile-Cache
Property	Cache
Attribute	cache.purge.condition
Description	Defines the condition for when the cache will be purged. Allowed values: NONE, MEMORY
Default Value	MEMORY
Property	Cache
Attribute	cache.purge.condition.memory.threshold
Description	Defines a percentual memory threshold for cache purging, when the cache.purge.condition = MEMORY.
Default Value	80
Property	Cache
Attribute	cache.purge.enabled
Description	Enables scheduled cache purging.
Default Value	true
Property	Cache
Attribute	cache.schedule.clear.enabled
Description	Enable the cache clearing schedule. This is scheduling the clear cache operation which will remove all the expired cache entries.
Default Value	true
Property	Cache
Attribute	cache.service.enabled
Description	Enables or disables the service cache.
Default Value	true
Property	Cache
Attribute	cache.service.type
Description	The service cache mechanism being used.
Default Value	IN_MEMORY
Property	Client Cache
Attribute	client.cache.control.age.max

Description	Controls the cache-control max-age header for static content.
Default Value	31536000
Property	Client Data
Attribute	client.data.load.transport
Description	Configure the transportation protocol for loading data from the Web client. Possible values: WEBSOCKET, LONG_POLLING. NOTE: This property has been deprecated. Refer to Setting the Transportation Protocol
	for more information.
Default Value	WEBSOCKET
Property	Server Cluster
Attribute	cluster.bully.bind
Description	The URL of the server in bully mode. This should be the URL to the panopticon server web application on the server itself, by which is reachable from the other servers.
Default Value	
Property	Server Cluster
Attribute	cluster.bully.boot
Description	Comma-separated list of server URLs in bully mode. At least one of these servers should be running at all time for the bully mode to work correctly. The URLs should be the same as the cluster.bully.bind value on each boot server.
Default Value	
Property	Server Cluster
Attribute	cluster.bully.id
Description	The unique server ID in bully mode. Can be any string, but do not change it after the server has participated in a cluster the other servers will store it and expect it to identify the same server in the future. The running server with the lowest ID lexicographically will be leader.
Default Value	
Property	Server Cluster
Attribute	cluster.fixed.leader
Description	The leader URL in fixed mode. This should be the URL to the panopticon server web application on the preset leader server, by which it is reachable from the follower servers. Leave blank on the leader server itself.
Default Value	
Property	Server Cluster
Attribute	cluster.kubernetes.container_name
Description	Optionally name of the container that runs the Panopticon server, if the pod also runs other containers. If left blank, the first container will be used.

Default Value	
Property	Server Cluster
Attribute	cluster.kubernetes.id
Description	Set to the name of the pod that runs the container.
Default Value	(blank)
Property	Server Cluster
Attribute	cluster.kubernetes.label_selector
Description	Standard Kubernetes label selector that should only match the pods that are running the server.
Default Value	
Property	Server Cluster
Attribute	cluster.kubernetes.peer_path
Description	Path to the web application on each server. For example, "panopticon/", or "/" if you have deployed to Tomcat's root.
Default Value	
Property	Server Cluster
Attribute	cluster.mode
Description	NONE (default), FIXED, BULLY, or KUBERNETES
Default Value	
Property	Server Cluster
Attribute	cluster.shared.secret
Description	Any alphanumeric string. Secret used to encrypt a challenge in peer-to-peer communication handshake. Needs to be the same, and non-empty, on all connected servers.
Default Value	
Property	Server Cluster
Attribute	cluster.shared.store.shared_directory.path
Description	Shared store location in SHARED_DIRECTORY mode. This path must be reachable by all connected servers and must point to the same physical directory on all of them.
Default Value	
Property	Server Cluster
Attribute	cluster.shared.store.type
Description	PRIVATE_DIRECTORY (default) or SHARED_DIRECTORY The shared store is used to store information that should be synchronized between servers but is not content, for example authentication tokens. If you have a tightly-coupled

	cluster, e.g., behind a load balancer, it is recommended that you configure this as a shared directory.
Default Value	
Property	AMPS Connector Custom Authenticator
Attribute	connector.amps.authenticators
Description	This property is required when a custom authenticator is needed for AMPS connection. A custom authenticator needs be implemented as java .JAR file. The property excepts a JSON object, where key is fully qualified name of the Authenticator Java class, and values are list of constructor parameter names, e.g., "{"com.panopticon.examples.amps.AMPSClientAuthenticator":["User", "Shared Key"]}"
Default Value	
Property	Connector File Path
Attribute	connector.common.filepath.link.disabled
Description	If set to true , the <i>Link to File</i> option will not be available.
Default Value	false
Property	Host Lookup
Attribute	connector.kdb.host.lookup.script
Description	Full path of the shell script file that is accessible on the server. When set, before making a new kdb+ connection, this script is executed to get the host info. This property helps in overriding connection details entered inside the kdb+ connector UI centrally, and may help when different authentications are set at kdb+ like Kerberos/Custom etc. The output of this script is expected to be a JSON object like below. { "host": "localhost", "port": 5001, "username": "", "password": "" } NOTE: Starting with the 21.2 release, the the kdb+ connection pool feature of Panopticon (kdb.connection.pool.xx) can be used together with the host lookup. So any new connection request from the pool, will first execute the script set here, to get the host info before the pool is looked up for available connections. Examples: For Windows connector.kdb.host.lookup.script=E://Data/host.bat For Linux connector.kdb.host.lookup.script= /etc/panopticon/appdata/host.sh
Default Value	
Property	Host Lookup
Attribute	connector.kdb.host.lookup.script.arguments
Description	Delimited set of arguments to be passed to the script when it is executed. '{host}, {port}, {userid}, {password}' is the default value, and

	these parameters are mapped to respective settings in the connector UI i.e., the value entered against these settings in the connector UI are passed as arguments to the script. This property can be extended or updated if you want to pass other datatable parameters as arguments. System parameter like { _user_id} or { _workbook_folder}, if added to the data table, can also be used. If the value of some parameter is null or empty at the time of execution of the script, two single quotes are passed (") against that parameter, this is to make sure that arguments count matches the arguments set at this property.
Default Value	{host},{port},{userid},{password}
Property	Host Lookup
Attribute	connector.kdb.host.lookup.script.arguments.delimiter
Description	Used to split the arguments set at above property.
Default Value	,
Property	Host Lookup
Attribute	connector.kdb.host.lookup.script.timeout
Description	The timeout (in milliseconds) to wait for the host lookup script to run and return the host info.
Default Value	5000
Property	Amazon Kinesis – Data Streams connector
Attribute	connector.kinesis.datastreams.accesskeyid
Description	The Access Key ID from the AWS account.
Default Value	
Property	Amazon Kinesis – Data Streams connector
Attribute	connector.kinesis.datastreams.secretaccesskey
Description	The Secret Access Key ID from the AWS account.
Default Value	
Property	OAuth Token URL
Attribute	connector.oauth.tokenurl
Description	Sets the server-wide token URL.
Default Value	http\://localhost\:5000/oauth/token
Property	Python connector
Attribute	connector.python.host
Description	The default Python Pyro instance host address. NOTES: For connector.python.host, connector.python.password, connector.python.port, and connector.python.serializertype properties: • If set in the Panopticon.properties file, these fields will be hidden in the Python connector and will be applied to the Python transform as well.

	These default Panopticon Real Time connection properties will be applied at runtime.
	These default Panopticon Real Time connection properties will override old Python connection settings.
Default Value	
Property	Python connector
Attribute	connector.python.password
Description	The default HMAC Key.
Default Value	
Property	Python connector
Attribute	connector.python.port
Description	The default Python Pyro host port.
Default Value	
Property	Python connector
Attribute	connector.python.serializertype
Description	The default Python serialization type. Possible values are serpent or pickle .
Default Value	
Property	Rserve connector
Attribute	connector.rserve.host
Description	The default Rserve host address. NOTES:
	<pre>For connector.rserve.host, connector.rserve.password, connector.rserve.port, and connector.rserve.userid properties:</pre>
	• If set in the Panopticon.properties file, these fields will be hidden in the Rserve connector and will be applied to the R transform as well.
	These default Panopticon Real Time connection properties will be applied at runtime.
	These default Panopticon Real Time connection properties will override old Rserve connection settings.
Default Value	
Property	Rserve connector
Attribute	connector.rserve.password
Description	The default password that will be used to connect to the Rserve service.
Default Value	
Property	Rserve connector
Attribute	connector.rserve.port
Description	The default Rserve host port.
Default Value	
Property	Rserve connector

Attribute	connector.rserve.userid
Description	The default user ld that will be used to connect to the Rserve service.
Default Value	
Property	Data Store
Attribute	datastore.connection.schema
Description	Name of the database schema to be used for creating or managing objects inside database.
Default Value	dbo
Property	Data Store
Attribute	datastore.type
Description	Controls which data store connector should be used. Valid values are MonetDB ", MSSQLServer and PostgreSQL .
Default Value	MonetDB
Property	Data Store
Attribute	datastore.connection.jndi
Description	JNDI resource name for the connection e.g., jdbc/MyDB . More details on how to configure JNDI is at <u>JNDI Connection Details</u> section.
Default Value	
Property	Data Store
Attribute	datastore.connection.url
Description	JDBC connection URL for the database e.g., jdbc:monetdb://localhost:49153/PanopticonDataStore This property value is discarded If datastore.connection.jndiproperty is set.
Default Value	
Property	Data Store
Attribute	datastore.connection.driverclassname
Description	Fully qualified Java class name of the JDBC driver used for the connection.
Default Value	org.monetdb.jdbc.MonetDriver
Property	Data Store
Attribute	datastore.connection.username
Description	Username for the connection. Only required when using connection URL.
Default Value	
Property	Data Store
Attribute	datastore.connection.password
Description	Password for the connection. Only required when using connection URL.
Default Value	

Property	REST Documentation
Attribute	documentation.enabled
Description	Enable or disable the OpenAPI Specification documentation for the REST interface.
Default Value	false
Property	Alert
Attribute	email.address
Description	The email address where the alert will be sent from.
Default Value	
Property	Email
Attribute	email.host
Description	The host name used by the email server.
Default Value	
Property	Alert
Attribute	email.password
Description	The email password, if available. NOTE: When using a Gmail account, you must use an app password to authenticate with the Gmail SMTP server. See Sign in with app passwords for more information.
Default Value	
Property	Email
Attribute	email.port
Description	The port number used by the email server.
Default Value	
Property	Email
Attribute	email.security.mode
Description	The security mode used when sending emails. Possible values: NONE , SSL , TLS .
Default Value	NONE
Property	Email
Attribute	email.username
Description	Email account username.
Default Value	
Property	Error Message
Attribute	error.default.message
Description	Defines a generic error message override.
Description	Bollines a generic error message eventue.

Attribute export.filesystem_copy.path If set to a directory, whether existing or not, then: Operations that email CSV, Excel, HTML, Image, PDF, or ZIP files (i.e., scheduled tasks), will also export a copy of the file to the specified path Operations that generate and return PDF, CSV, or ZIP files (e.g., Create PDF Report toloibar button on a dashboard) will also export a copy of the file to the specified path if not set (blank), the server works the same way as before. Default Value Property Image export Attribute export.image.height Description The default height for an exported image. Default Value export.image.width Description The default width for an exported image. Default Value export.image.width Description The default width for an exported image. Default Value 1024 Property File Upload Attribute file.upload.size.max.bytes Description Limit for files size (in bytes) to be uploaded through the web browser (i.e., workbooks, streams applications, streams data sources). Default Value 3000000 Property Copy Image Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value kdb Connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+server (among kdb+servers that use the same username, password, TLS flag, and timeoutly, so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection instance created.	Property	Export File Path
Operations that email CSV, Excel, HTML, Image, PDF, or ZIP files (i.e., scheduled tasks) will also export a copy of the file to the specified path operation and return PDF, CSV, or ZIP files (e.g., Create PDF Report toolbar button on a dashboard) will also export a copy of the file to the specified path if not set (blank), the server works the same way as before. Default Value Property Image export Attribute export.image.height Description The default height for an exported image. Default Value 768 Property Image export Attribute export.image.width Description The default width for an exported image. Default Value 1024 Property File Upload Attribute file.upload.size.max.bytes Description Limit for files size (in bytes) to be uploaded through the web browser (i.e., workbooks, streams applications, streams data sources). Default Value 3000000 Property Copy Image Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 800000 Property kdb* Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+ server (among kdb* servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool.	Attribute	export.filesystem_copy.path
tasks) will also export a copy of the file to the specified path Operations that generate and return PDF, CSV, or ZIP files (e.g., Create PDF Report toolbar button on a dashboard) will also export a copy of the file to the specified path If not set (blank), the server works the same way as before. Default Value Property Image export Attribute export.image.height Description The default height for an exported image. Default Value 768 Property Image export Attribute export.image.width Description The default width for an exported image. Default Value 1024 Property File Upload Attribute file.upload.size.max.bytes Description Limit for files size (in bytes) to be uploaded through the web browser (i.e., workbooks, streams applications, streams data sources). Default Value 3000000 Property Copy Image Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 800000 Property kdb+ Connection Pooling Attribute Attribute Attribute Attribute Connection pool.max.size Description Description Description Copy Image Attribute Attribute Robonometrion.pool.max.size Description Description Robonometrion.pool.max.size Robonometrion.pool.max.size Robonometrion.pool.max.size Robonometrion.pool.max.size Robonometrion.pool.max.size Robonometrion.pool.max.size Robonometrion.pool.max.size Robonometrion.pool.max.size Robonometrion.pool.max.size	Description	If set to a directory, whether existing or not, then:
toolbar button on a dashboard) will also export a copy of the file to the specified path if not set (blank), the server works the same way as before. Proporty Image export Attribute export.image.height Description The default height for an exported image. Default Value 768 Property Image export Attribute export.image.width Description The default width for an exported image. Default Value 1024 Property File Upload Attribute file.upload.size.max.bytes Description Limit for files size (in bytes) to be uploaded through the web browser (i.e., workbooks, streams applications, streams data sources). Default Value 3000000 Property Copy Image Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 800000 Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+server (among kdb+servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same surver. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Property kdb+ Connection Pooling Attribute kdb.connection Pooling		
Default Value export Attribute export.image.height Description The default height for an exported image. Default Value 768 Property Attribute export.image.width Description The default width for an exported image. Default Value export.image.width Description The default width for an exported image. Default Value 1024 Property File Upload Attribute File.upload.size.max.bytes Description Limit for files size (in bytes) to be uploaded through the web browser (i.e., workbooks, streams applications, streams data sources). Default Value 3000000 Property Copy Image Attribute Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 60000 Property Kdb+ Connection Pooling Attribute Add:.connection.pool.max.size Description Description The maximum number of connections that will be kept open for reuse for each kdb+ server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool is that it can reduce latency.		
Property Image export Attribute export.image.height Description The default height for an exported image. Default Value 768 Property Image export Attribute export.image.width Description The default width for an exported image. Default Value 1024 Property File Upload Attribute file.upload.size.max.bytes Description Limit for files size (in bytes) to be uploaded through the web browser (i.e., workbooks, streams applications, streams data sources). Default Value 3000000 Property Copy Image Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 600000 Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+ server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Attribute kdb-connection.pool.ttl		If not set (blank), the server works the same way as before.
Attribute export.image.height Description The default height for an exported image. Property Image export Attribute export.image.width Description The default width for an exported image. Default Value 1024 Property File Upload Attribute file.upload.size.max.bytes Description Limit for files size (in bytes) to be uploaded through the web browser (i.e., workbooks, streams applications, streams data sources). Default Value 3000000 Property Copy Image Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 600000 Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Default Value 10 Property kdb+ Connection Pooling Attribute \text{ kdb+ Connection Pooling}	Default Value	
Description The default height for an exported image. Default Value 768 Property Image export Attribute export.image.width Description The default width for an exported image. Default Value 1024 Property File Upload Attribute file.upload.size.max.bytes Description Limit for files size (in bytes) to be uploaded through the web browser (i.e., workbooks, streams applications, streams data sources). Default Value 3000000 Property Copy Image Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 600000 Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent query each come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Default Value 10 Property kdb+ Connection Pooling Attribute \(\text{Adb-Connection Pooling} \)	Property	Image export
Default Value 768 Property Image export Attribute export.image.width Description The default width for an exported image. Default Value 1024 Property File Upload Attribute file.upload.size.max.bytes Description Limit for files size (in bytes) to be uploaded through the web browser (i.e., workbooks, streams applications, streams data sources). Default Value 3000000 Property Copy Image Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 600000 Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+server (among kdb+servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Property kdb+ Connection Pooling Attribute kdb-connection.pool.ttl	Attribute	export.image.height
Property Image export Attribute export.image.width Description The default width for an exported image. Default Value 1024 Property File Upload Attribute file.upload.size.max.bytes Description Limit for files size (in bytes) to be uploaded through the web browser (i.e., workbooks, streams applications, streams data sources). Default Value 3000000 Property Copy Image Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 60000 Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+ server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Property kdb+ Connection Pooling Attribute kdb+ Connection Pooling	Description	The default height for an exported image.
Attribute export.image.width Description The default width for an exported image. Default Value 1024 Property File Upload Attribute file.upload.size.max.bytes Description Limit for files size (in bytes) to be uploaded through the web browser (i.e., workbooks, streams applications, streams data sources). Default Value 3000000 Property Copy Image Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 60000 Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+ server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Default Value 10 Property kdb+ Connection Pooling Attribute kdb+ Connection Pooling	Default Value	768
Description The default width for an exported image. Default Value 1024 Property File Upload Attribute file.upload.size.max.bytes Description Limit for files size (in bytes) to be uploaded through the web browser (i.e., workbooks, streams applications, streams data sources). Default Value 30000000 Property Copy Image Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 600000 Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Property kdb+ Connection Pooling Attribute kdb-connection.pool.ttl	Property	Image export
Default Value 1024 Property File Upload Attribute file.upload.size.max.bytes Description Limit for files size (in bytes) to be uploaded through the web browser (i.e., workbooks, streams applications, streams data sources). Default Value 30000000 Property Copy Image Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 600000 Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Default Value 10 Property kdb+ Connection Pooling kdb-connection.pool.ttl	Attribute	export.image.width
Attribute file.upload.size.max.bytes Description Limit for files size (in bytes) to be uploaded through the web browser (i.e., workbooks, streams applications, streams data sources). Default Value 3000000 Property Copy Image Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 600000 Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+ server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Default Value 10 Property kdb+ Connection Pooling Attribute kdb-connection.pool.ttl	Description	The default width for an exported image.
Attribute file.upload.size.max.bytes Description Limit for files size (in bytes) to be uploaded through the web browser (i.e., workbooks, streams applications, streams data sources). Default Value 30000000 Property Copy Image Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 600000 Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+ server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Default Value 10 Property kdb+ Connection Pooling Attribute kdb-connection.pool.ttl	Default Value	1024
Description Limit for files size (in bytes) to be uploaded through the web browser (i.e., workbooks, streams applications, streams data sources). Default Value 3000000 Property Copy Image Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 600000 Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Default Value 10 Property kdb+ Connection Pooling Attribute kdb.connection.pool.ttl	Property	File Upload
streams applications, streams data sources). Default Value Property Copy Image Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 600000 Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+server (among kdb+servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Default Value 10 Property kdb+ Connection Pooling Attribute kdb.connection.pool.ttl	Attribute	file.upload.size.max.bytes
Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 600000 Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+ server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Property kdb+ Connection Pooling Attribute kdb.connection.pool.ttl	Description	
Attribute image.client.timeout Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 600000 Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+ server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Property kdb+ Connection Pooling Attribute kdb.connection.pool.ttl	Default Value	30000000
Description Specifies a timeout (in milliseconds) when producing an image or PDF. If it takes longer than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 600000 Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+ server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Property kdb+ Connection Pooling Attribute kdb.connection.pool.ttl	Property	Copy Image
than the timeout, the process will be interrupted, and the image/PDF will not be produced. Default Value 600000 Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+ server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Property kdb+ Connection Pooling Attribute kdb.connection.pool.ttl	Attribute	image.client.timeout
Property kdb+ Connection Pooling Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+ server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Default Value 10 Property kdb+ Connection Pooling Attribute kdb.connection.pool.ttl	Description	
Attribute kdb.connection.pool.max.size Description The maximum number of connections that will be kept open for reuse for each kdb+server (among kdb+servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Default Value 10 Property kdb+Connection Pooling Attribute kdb.connection.pool.ttl	Default Value	600000
Description The maximum number of connections that will be kept open for reuse for each kdb+ server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Property kdb+ Connection Pooling kdb.connection.pool.ttl	Property	kdb+ Connection Pooling
server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency. Setting this property to 0 disables the connection pool. Default Value 10 Property kdb+ Connection Pooling kdb.connection.pool.ttl	Attribute	kdb.connection.pool.max.size
Property kdb+ Connection Pooling Attribute kdb.connection.pool.ttl	Description	server (among kdb+ servers that use the same username, password, TLS flag, and timeout), so that established connections can be reused when subsequent queries come in for the same server. A benefit of the connection pool is that it can reduce latency.
Attribute kdb.connection.pool.ttl	Default Value	10
	Property	kdb+ Connection Pooling
Description Time to live in milliseconds for each connection instance created.	Attribute	kdb.connection.pool.ttl
	Description	Time to live in milliseconds for each connection instance created.

Default Value	30000
Property	Licensing
Attribute	license.hwu.hosted
Description	Boolean stating if you wish to use Managed or Local Altair Units licensing. Set to true if you wish to use managed licensing.
Default Value	false
Property	Licensing
Attribute	license.hwu.hosted.authorization.password
Description	Password to the Altair One account.
Default Value	
Property	Licensing
Attribute	license.hwu.hosted.authorization.token
Description	An authorization token generated through the Altair One admin portal. Used to authorize a machine to the managed Altair Units system.
Default Value	
Property	Licensing
Attribute	license.hwu.hosted.authorization.username
Description	Username to the Altair One account.
Default Value	
Property	Licensing
Attribute	license.hwu.uri
Description	The path where the License Server is running e.g., 6200@191.255.255.0 where the syntax is PORTNUMBER@HOST. If multiple servers are specified, use the ';' semicolon separator sign for Windows and the ':' colon separator sign for Linux. NOTE: If value is not set in the Panopticon.properties, the environment variable ALTAIR_LICENSE_PATH serves as the backup path and will be used.
Example	For Windows: license.hwu.uri=6200@192.168.5.51;6200@192.168.5.52 For Linux: license.hwu.uri=6200@192.168.5.51:6200@192.168.5.52
Default Value	
Property	Licensing
Attribute	license.hwu.use_client_timezone
Description	Determines how the ALJDK should process the timezone details. If set to true , the ALJDK will process the timezone details sent by Panopticon client to the Panopticon server. If set to false , the Panopticon server timezone is used.
Default Value	true

Property	Licensing
Attribute	license.hwu.version
Description	Value must match the license version found in the Altair Units license file.
Default Value	19.0
Property	Licensing
Attribute	license.mode
Description	The license mode. Possible values are FILE or HWU . To use the Altair Units license, set this property to HWU.
Default Value	FILE
Property	Log level
Attribute	logger.level.file
Description	Controls the level that is logged to file.
Default Value	INFO
Property	Server Metrics
Attribute	metrics.authorization.level
Description	Specifies the required authorization level to get server metrics. Available values are ANONYMOUS , VIEWER , DESIGNER , ADMINISTRATOR . NOTE: This property is case sensitive.
Default Value	ADMINISTRATOR
Default Value	ADMINISTRATOR
Property Property	Server Metrics
Property	Server Metrics
Property Attribute	Server Metrics metrics.collection.rate
Property Attribute Description	Server Metrics metrics.collection.rate Specifies the rate at which metrics are collected in milliseconds.
Property Attribute Description Default Value	Server Metrics metrics.collection.rate Specifies the rate at which metrics are collected in milliseconds. 1000
Property Attribute Description Default Value Property	Server Metrics metrics.collection.rate Specifies the rate at which metrics are collected in milliseconds. 1000 Server Metrics
Property Attribute Description Default Value Property Attribute	Server Metrics metrics.collection.rate Specifies the rate at which metrics are collected in milliseconds. 1000 Server Metrics metrics.file.flush.rate Specifies how often metrics should be saved to disk in milliseconds. Only used if the
Property Attribute Description Default Value Property Attribute Description	Server Metrics metrics.collection.rate Specifies the rate at which metrics are collected in milliseconds. 1000 Server Metrics metrics.file.flush.rate Specifies how often metrics should be saved to disk in milliseconds. Only used if the metrics.publisher.type is set to FILE.
Property Attribute Description Default Value Property Attribute Description Default Value	Server Metrics metrics.collection.rate Specifies the rate at which metrics are collected in milliseconds. 1000 Server Metrics metrics.file.flush.rate Specifies how often metrics should be saved to disk in milliseconds. Only used if the metrics.publisher.type is set to FILE. 10000
Property Attribute Description Default Value Property Attribute Description Default Value Property	Server Metrics metrics.collection.rate Specifies the rate at which metrics are collected in milliseconds. 1000 Server Metrics metrics.file.flush.rate Specifies how often metrics should be saved to disk in milliseconds. Only used if the metrics.publisher.type is set to FILE. 10000 Server Metrics
Property Attribute Description Default Value Property Attribute Description Default Value Property Attribute Attribute	Server Metrics metrics.collection.rate Specifies the rate at which metrics are collected in milliseconds. 1000 Server Metrics metrics.file.flush.rate Specifies how often metrics should be saved to disk in milliseconds. Only used if the metrics.publisher.type is set to FILE. 10000 Server Metrics metrics.memory.queue.size Specifies how many metric entries are stored in memory. When the number of metrics goes above the specifies value, the oldest value is removed to make room for the newest
Property Attribute Description Default Value Property Attribute Description Default Value Property Attribute Description	Server Metrics metrics.collection.rate Specifies the rate at which metrics are collected in milliseconds. 1000 Server Metrics metrics.file.flush.rate Specifies how often metrics should be saved to disk in milliseconds. Only used if the metrics.publisher.type is set to FILE. 10000 Server Metrics metrics.memory.queue.size Specifies how many metric entries are stored in memory. When the number of metrics goes above the specifies value, the oldest value is removed to make room for the newest one (FIFO). Only used if the metrics.publisher.type is set to MEMORY.
Property Attribute Description Default Value Property Attribute Description Default Value Property Attribute Description Default Value Property Attribute Description	Server Metrics metrics.collection.rate Specifies the rate at which metrics are collected in milliseconds. 1000 Server Metrics metrics.file.flush.rate Specifies how often metrics should be saved to disk in milliseconds. Only used if the metrics.publisher.type is set to FILE. 10000 Server Metrics metrics.memory.queue.size Specifies how many metric entries are stored in memory. When the number of metrics goes above the specifies value, the oldest value is removed to make room for the newest one (FIFO). Only used if the metrics.publisher.type is set to MEMORY. 100

Description	Specifies the id for which metric publisher configuration to use.
Default Value	
Property	Server Metrics
Attribute	metrics.publisher.type
Description	Specifies the current metric publisher that is used. Available values are NONE , MEMORY , FILE , EMAIL , INFLUX_DB , JDBC , KAFKA , KDB , MQTT , REST , TEXT .
Default Value	MEMORY
Property	Bookmarks repository
Attribute	repository.import.bookmarks.paths
Description	Will import bookmarks from the old format into the repository. Will override any existing bookmarks inside the repository. Must be set to an absolute path. Only bookmarks for workbooks that exists inside the repository will be imported.
Default Value	
Property	Workbook repository
Attribute	repository.migrate.archive.path
Description	Use this property if you have an older (pre 2020) server and wish to start the new server with the same workbook content as the old one, and also to import the workbooks' change history from the old server. Set the property to the absolute path to the old server's <appdata>/Archive/ directory, delete the new server's <appdata>/.repository/ directory, and start the new server. You typically use this property with the repository.migrate.workbooks.path property. See also the section on content migration.</appdata></appdata>
Example	C\:/vizserverdata/Archive
Default Value	
Property	Bookmarks repository
Attribute	repository.migrate.bookmarks.path
Description	Will migrate bookmarks from the old format into the repository if there are no bookmarks inside the repository yet. Set to an absolute path or to the default Bookmarks folder. Only bookmarks for workbooks that exists inside the repository will be migrated. NOTE: If you do not wish to migrate bookmarks or already have bookmarks in the repository, set this property to blank to avoid a warning on startup.
Default Value	Bookmarks
Property	Workbook repository
Attribute	repository.migrate.data.extracts.path
Description	Starting with version 21.0, data extracts are stored inside the repository.
Description	If this property is set to GlobalCaches (default value), or to an absolute path, the server will migrate data extracts into the repository on startup as long as the repository does not contain any previous data extracts. NOTE: If you do not wish to migrate data extracts or already have data extracts in the
Description Default Value	If this property is set to GlobalCaches (default value), or to an absolute path, the server will migrate data extracts into the repository on startup as long as the repository does not contain any previous data extracts.

Property	Data Templates Repository
Attribute	repository.migrate.datatable.templates.path
Description	Will migrate data table templates from the old format into the repository if there are no data table templates inside the repository yet. Set to an absolute path or to the default Datatables folder.
	NOTE: If you do not wish to migrate data table templates or already have data table templates in the repository, set this property to blank to avoid a warning on startup.
Default Value	Datatables
Property	Themes repository
Attribute	repository.migrate.themes.path
Description	Will migrate themes from the old format into the repository if there are no themes inside the repository yet. Set to an absolute path or to the default Themes folder.
	NOTE: If you do not wish to migrate themes or already have themes in the repository, set this property to blank to avoid a warning on startup.
Default Value	Themes
Property	Workbook repository
Attribute	repository.migrate.workbooks.path
Description	Use this property if you have an older (pre 2020) server and wish to start the new server with the same workbook content as the old one. Set the property to the absolute path to the old server's <appdata>/Workbooks/ directory, delete the new server's <appdata>/.repository/ directory, and start the new server.</appdata></appdata>
	See also the section on content migration.
Example	C\:/vizserverdata/Workbooks
Default Value	
Property	Workbook repository
Attribute	repository.pack.enabled
Description	The repository tracks all changes to all workbooks. If you have a very large number of workbooks, or have kept the repository for a very long time, the sheer number of files inside the <code>.repository</code> subdirectory could cause the repository to become slower. Set this property to true to have the repository pack all the files into fewer larger ones for faster access.
Default Value	false
Property	Repository
Attribute	repository.startup.apply.permissions.clean
Description	Use this property with the repository.startup.apply.permissions.path to reset all existing workbook permissions on the server before applying the template. If you set it to true , the server will remove all permissions, then give users full permissions to their private folders, and the "Everyone" group full permissions to public folders.
Default Value	false
Property	Repository
Attribute	repository.startup.apply.permissions.create

Description	Use this property with the repository.startup.apply.permissions.path to create empty workbook folders for any folders that are in the template file but do not yet exist on the server. If you don't set it to true , these folders from the template will be ignored.
Default Value	true
Property	Repository
Attribute	repository.startup.apply.permissions.path
Description	Use this property to make the server apply workbook folder permissions from a template JSON file on startup. Workbook folder permissions in the template will overwrite any existing permissions on the server. This property will not migrate permissions from an older (pre 2020) server, you need to use the PCLI convertpermissions to generate a template file from the old permissions first. See also repository.startup.apply.permissions.clean and repository.startup.apply.permissions.create.
Default Value	
Property	Repository
Attribute	repository.startup.filesystemcheck
Description	If set to true , server runs on startup to verify the repository integrity and reports any of the following issues: • a deleted /HEAD file, • a modified /HEAD, • a modified /refs/heads/master file, • any file deleted inside /objects/ (e.g., /objects/94/443eec118fb8bb2021071896ff7d386a9c9518), • any file modified inside /objects/. NOTE: There may be dangling files in the /objects/ directory or those that are not in use. These files are typically results of failed saves and/or sync conflicts. The check may or may not detect deleted or modified dangling files, but that is not critical.
Default Value	false
Property	Repository Import
Attribute	repository.startup.import.paths
Description	NOTE: Use this property to make the server import content at startup. This is imported on top of the existing content and will always overwrite anything that is already there. This property can be useful for example, if you have multiple servers with different content but you want the latest version of a standard set of workbooks to be deployed on all of them. This property only has effect on a stand-alone or leader server. This property is the list of paths to directories and files, separated by the system specific path separator ";" on Windows and ":" on Linux. Each directory is scanned and imported keeping its local tree structure. For example, workbooks to be imported are placed in a folder and in this property, the absolute path to that folder is specified. ADDITIONAL NOTES: User-specific folders (e.g., "~john/") can be targeted this way, but only if they already
	 User-specific folders (e.g., "~john/") can be targeted this way, but only if they already exist on the server.

	Bundles (exz files) directly listed in the property or found in directories listed are also imported, but always to the root, with their internal structure preserved.
	Files that are not legacy workbooks or bundles are ignored.
	 The same set of workbooks will get imported over and over (startup, user edit, restart) and for bundles (nothing changes in the history the second time), but legacy workbooks change their meta data.
	The import always overwrites local changes (it resets the workbooks in the repository).
	Permissions are not supported, and any folders created will have "SYSTEM" as owner.
Default Value	
Property	Request parameter mapping
Attribute	request.cookie.parameters.mapping.entry.delimiter
Description	The delimiter that separates the configuration entries. This property will only affect incoming parameters.
Default Value	, (Comma)
Property	Request parameter mapping
Attribute	request.cookie.parameters.mapping.optional
Description	The parameters that could be updated with certain cookie values. This property will only affect incoming parameters. The operation will not fail if the cookie values are not present in the request. The parameters will keep their default value instead of the configured cookie value if the cookie is not present. The property should be formatted as follows: Parameter name (Value delimiter) Cookie name.
Default Value	
Property	Request parameter mapping
Attribute	request.cookie.parameters.mapping.required
Description	The parameters that are required to be updated with certain cookie values. This property will only affect incoming parameters. The operation will fail if configured cookie values are not present in the request. The property should be formatted as follows: Parameter name (Value delimiter) Cookie name.
Default Value	
Property	Request parameter mapping
Attribute	request.cookie.parameters.mapping.value.delimiter
Description	The delimiter that separates the parameter name and the cookie name. This property will only affect incoming parameters.
Default Value	: (Colon)
Property	Request parameter mapping
Attribute	request.header.parameters.mapping.entry.delimiter
Description	The delimiter that separates the configuration entries. This property will only affect incoming parameters.
Default Value	, (Comma)
Property	Request parameter mapping

Attribute	request.header.parameters.mapping.optional
Description	The parameters that could be updated with certain header values. This property will only affect incoming parameters. The operation will not fail if the header values are not present in the request. The parameters will keep their default value instead of the configured header value if the header is not present. The property should be formatted as follows: Parameter name (Value delimiter) Header name.
Default Value	
Property	Request parameter mapping
Attribute	request.header.parameters.mapping.required
Description	The parameters that are required to be updated with certain header values. This property will only affect incoming parameters. The operation will fail if a configured header values are not present in the request. The property should be formatted as follows: Parameter name (Value delimiter) Header name.
Default Value	
Property	Request parameter mapping
Attribute	request.header.parameters.mapping.value.delimiter
Description	The delimiter that separates the parameter name and the header name. This property will only affect incoming parameters.
Default Value	: (Colon)
Property	Response parameter mapping
Attribute	response.operation.parameters.mapping.entry.delimiter
Description	The delimiter that separates the configuration entries. This property will only affect outgoing parameters.
Default Value	, (Comma)
Property	Response parameter mapping
Attribute	response.operation.parameters.mapping.optional
Description	The parameters that could be updated with certain Header values. This property will only affect outgoing parameters. The operation will not fail if the Header values are not present in the request. The parameters will keep their default value instead of the configured Header value if the Header is not present. The property should be formatted as follows: Parameter name (Value delimiter) Header name.
Default Value	
Property	Response parameter mapping
Attribute	response.operation.parameters.mapping.required
Description	The parameters that are required to be updated with certain Header values. This property will only affect outgoing parameters. The operation will fail if configured Header values are not present in the request. The property should be formatted as follows: Parameter name (Value delimiter) Header name.
Default Value	
Property	Response parameter mapping
Attribute	response.operation.parameters.mapping.value.delimiter

Default Value :(Colon) Property REST Attribute rest.response.error.stacktrace.included Description Include the error stack trace in REST responses. Default Value false Property Compatibility Attribute server.force_downgrade Description The server normally refuses to start if it detects that the AppData directory has been used by a server with a newer version. This is because downgrading content and other AppData files is not supported and can cause irreversable issues. You can set this property to true to force the server to start anyway, but it is strongly recommended that you do not. Default Value false Property Email Attribute server.host Description The server endpoint address. This will be used to generate links in emails sent by the server, so it should be the server's or load balancer's public URL and needs to be resolvable from the email recipient's machine. For example: Default Value Property PDF and Image generation Attribute server.host.internal Description The local server endpoint address. To generate PDFs and images, the server fires up an external process which then makes HTTP calls to the server itself. This URL needs to be resolvable on the server itself. For example: Default	Description	The delimiter that separates the parameter name and the Header name. This property will only affect incoming parameters.
Attribute rest.response.error.stacktrace.included Description Include the error stack trace in REST responses. Default Value false Property Compatibility Attribute server.force_downgrade Description The server normally refuses to start if it detects that the AppData directory has been used by a server with a newer version. This is because downgrading content and other AppData falle is not supported and can cause irreversable issues. You can set this property to true to force the server to start anyway, but it is strongly recommended that you do not. Default Value Fmail Attribute server.host Description The server endpoint address. This will be used to generate links in emails sent by the server, so it should be the server's or load balancer's public URL and needs to be resolvable from the email recipient's machine. For example: server.host=http://www.company.com/dashboards/ Property PDF and Image generation Attribute server.host.internal Description The local server endpoint address. To generate PDFs and images, the server fires up an external process which then makes HTTP calls to the server itself. This URL needs to be resolvable on the server itself. For example: server.host.internal=http://127.0.0.1:8080/panopticon/ Default Value Property Server Attribute server.id Description Specifies an id for the current server. The value of this property will be part of each metric entry so that it can be tied to a specific server if a server cluster is used. If no value is specified, the MAC address of the localhost network will be attempted to be used to identify the server. If this is not possible, a UUID will be generated. Property SOAP Attribute scape.adaled	Default Value	: (Colon)
Description Include the error stack trace in REST responses. Default Value false Property Compatibility Attribute server normally refuses to start if it detects that the AppData directory has been used by a server with a newer version. This is because downgrading content and other AppData files is not supported and can cause irreversable issues. You can set this property to true to force the server to start anyway, but it is strongly recommended that you do not. Default Value false Property Email Attribute server not address. This will be used to generate links in emails sent by the server, so it should be the server's or load balancer's public URL and needs to be resolvable from the email recipient's machine. For example: server.host=http://www.company.com/dashboards/ Default Value Property PDF and Image generation Attribute server.host.internal Description The local server endpoint address. To generate PDFs and images, the server fires up an external process which then makes HTTP calls to the server itself. This URL needs to be resolvable on the server itself. For example: server.host.internal=http://127.0.0.1:8080/panopticon/ Default Value Property Server Attribute server.id Description Specifies an id for the current server. The value of this property will be part of each metric entry so that it can be tied to a specific server if a server cluster is used. If no value is specified, the MAC address of the localhost network will be attempted to be used to identify the server. If this is not possible, a UUID will be generated. Default Value Property SOAP Attribute scape.	Property	REST
Property Compatibility Attribute server.force_downgrade Description The server normally refuses to start if it detects that the AppData directory has been used by a server with a newer version. This is because downgrading content and other AppData flies is not supported and can cause irreversable issues. You can set this property to true to force the server to start anyway, but it is strongly recommended that you do not. Default Value false Property Email Attribute server.host Description The server endpoint address. This will be used to generate links in emails sent by the server, so it should be the server's or load balancer's public URL and needs to be resolvable from the email recipient's machine. For example: server.host=http://www.company.com/dashboards/ Default Value Property PDF and Image generation Attribute server.host.internal Description The local server endpoint address. To generate PDFs and images, the server fires up an external process which then makes HTTP calls to the server itself. This URL needs to be resolvable on the server itself. For example: server.host.internal=http://127.0.0.1:8080/panopticon/ Default Value Property Server Attribute server.id Description Specifies an id for the current server. The value of this property will be part of each metric entry so that it can be tied to a specific server if a server cluster is used. If no value is specified, the MAC address of the localhost network will be attempted to be used to identify the server. If this is not possible, a UUID will be generated. Default Value Property SOAP Attribute soap.enabled	Attribute	rest.response.error.stacktrace.included
Property Compatibility Attribute server.force_downgrade Description The server normally refuses to start if it detects that the AppData directory has been used by a server with a newer version. This is because downgrading content and other AppData files is not supported and can cause irreversable issues. You can set this property to true to force the server to start anyway, but it is strongly recommended that you do not. Default Value false Property Email Attribute server.host Description The server endpoint address. This will be used to generate links in emails sent by the server, so it should be the server's or load balancer's public URL and needs to be resolvable from the email recipient's machine. For example: server.host=http://www.company.com/dashboards/ Default Value Property PDF and Image generation Attribute server.host.internal Description The local server endpoint address. To generate PDFs and images, the server fires up an external process which then makes HTTP calls to the server itself. This URL needs to be resolvable on the server itself. For example: server.host.internal=http://127.o.o.1:8080/panopticon/ Default Value Property Server Attribute server.id Description Specifies an id for the current server. The value of this property will be part of each metric entry so that it can be lied to a specific server if a server cluster is used. If no value is specified, the MAC address of the localhost network will be attempted to be used to identify the server. If this is not possible, a UUID will be generated. Default Value Property SOAP Attribute soap.enabled	Description	Include the error stack trace in REST responses.
Attribute server.force_downgrade Description The server normally refuses to start if it detects that the AppData directory has been used by a server with a newer version. This is because downgrading content and other AppData files is not supported and can cause irreversable issues. You can set this property to true to force the server to start anyway, but it is strongly recommended that you do not. Default Value false Property Email Attribute server.host Description The server endpoint address. This will be used to generate links in emails sent by the server, so it should be the server's or load balancer's public URL and needs to be resolvable from the email recipient's machine. For example: server.host=http://www.company.com/dashboards/ Default Value Property PDF and Image generation Attribute server.host.internal Description The local server endpoint address. To generate PDFs and images, the server fires up an external process which then makes HTTP calls to the server itself. This URL needs to be resolvable on the server itself. For example: server.host.internal=http://127.0.0.1:8080/panopticon/ Default Value Property Server Attribute server.id Description Specifies an id for the current server. The value of this property will be part of each metric entry so that it can be tied to a specific server if a server cluster is used. If no value is specified, the MAC address of the localhost network will be attempted to be used to identify the server. If this is not possible, a UUID will be generated. Property SOAP Attribute seap.enabled	Default Value	false
Description The server normally refuses to start if it detects that the AppData directory has been used by a server with a newer version. This is because downgrading content and other AppData files is not supported and can cause irreversable issues. You can set this property to true to force the server to start anyway, but it is strongly recommended that you do not. Default Value Froperty Email Attribute Server.host The server endpoint address. This will be used to generate links in emails sent by the server, so it should be the server's or load balancer's public URL and needs to be resolvable from the email recipient's machine. For example: Server.host=http://www.company.com/dashboards/ Default Value Property PDF and Image generation Attribute Server.host.internal Description The local server endpoint address. To generate PDFs and images, the server fires up an external process which then makes HTTP calls to the server itself. This URL needs to be resolvable on the server itself. For example: Server.host.internal=http://127.0.0.1:8080/panopticon/ Default Value Property Server Attribute Server.id Description Specifies an id for the current server. The value of this property will be part of each metric entry so that it can be tied to a specific server if a server cluster is used. If no value is specified, the MAC address of the localhost network will be attempted to be used to identify the server. If this is not possible, a UUID will be generated. Property SOAP Attribute Soap.enabled	Property	Compatibility
used by a server with a newer version. This is because downgrading content and other AppData files is not supported and can cause irreversable issues. You can set this property to true to force the server to start anyway, but it is strongly recommended that you do not. Default Value false Property Email Attribute server.host Description The server endpoint address. This will be used to generate links in emails sent by the server, so it should be the server's or load balancer's public URL and needs to be resolvable from the email recipient's machine. For example: server.host=http://www.company.com/dashboards/ Default Value Property PDF and Image generation Attribute server.host.internal Description The local server endpoint address. To generate PDFs and images, the server fires up an external process which then makes HTTP calls to the server itself. This URL needs to be resolvable on the server itself. For example: server.host.internal=http://127.0.0.1:8080/panopticon/ Default Value Property Server Attribute server.id Description Specifies an id for the current server. The value of this property will be part of each metric entry so that it can be tied to a specific server if a server cluster is used. If no value is specified, the MAC address of the localhost network will be attempted to be used to identify the server. If this is not possible, a UUID will be generated. Property SOAP Attribute soap.enabled	Attribute	server.force_downgrade
Property Email Attribute server.host Description The server endpoint address. This will be used to generate links in emails sent by the server, so it should be the server's or load balancer's public URL and needs to be resolvable from the email recipient's machine. For example: server.host=http://www.company.com/dashboards/ Default Value Property PDF and Image generation Attribute server.host.internal Description The local server endpoint address. To generate PDFs and images, the server fires up an external process which then makes HTTP calls to the server itself. This URL needs to be resolvable on the server itself. For example: server.host.internal=http://127.0.0.1:8080/panopticon/ Default Value Property Server Attribute server.id Description Specifies an id for the current server. The value of this property will be part of each metric entry so that it can be tied to a specific server if a server cluster is used. If no value is specified, the MAC address of the localhost network will be attempted to be used to identify the server. If this is not possible, a UUID will be generated. Property SOAP Attribute soap.enabled	Description	used by a server with a newer version. This is because downgrading content and other AppData files is not supported and can cause irreversable issues. You can set this property to true to force the server to start anyway, but it is strongly recommended that
Attribute server.host Description The server endpoint address. This will be used to generate links in emails sent by the server, so it should be the server's or load balancer's public URL and needs to be resolvable from the email recipient's machine. For example: server.host=http://www.company.com/dashboards/ Default Value Property PDF and Image generation Attribute server.host.internal Description The local server endpoint address. To generate PDFs and images, the server fires up an external process which then makes HTTP calls to the server itself. This URL needs to be resolvable on the server itself. For example: server.host.internal=http://127.0.0.1:8080/panopticon/ Default Value Property Server Attribute server.id Description Specifies an id for the current server. The value of this property will be part of each metric entry so that it can be tied to a specific server if a server cluster is used. If no value is specified, the MAC address of the localhost network will be attempted to be used to identify the server. If this is not possible, a UUID will be generated. Property SOAP Attribute soap.enabled	Default Value	false
Description The server endpoint address. This will be used to generate links in emails sent by the server, so it should be the server's or load balancer's public URL and needs to be resolvable from the email recipient's machine. For example: server.host=http://www.company.com/dashboards/ Default Value Property PDF and Image generation Attribute server.host.internal Description The local server endpoint address. To generate PDFs and images, the server fires up an external process which then makes HTTP calls to the server itself. This URL needs to be resolvable on the server itself. For example: server.host.internal=http://127.0.0.1:8080/panopticon/ Default Value Property Server Attribute server.id Specifies an id for the current server. The value of this property will be part of each metric entry so that it can be tied to a specific server if a server cluster is used. If no value is specified, the MAC address of the localhost network will be attempted to be used to identify the server. If this is not possible, a UUID will be generated. Property SOAP Attribute server.add Soap.enabled	Property	Email
server, so it should be the server's or load balancer's public URL and needs to be resolvable from the email recipient's machine. For example: server.host=http://www.company.com/dashboards/ Property PDF and Image generation Attribute server.host.internal Description The local server endpoint address. To generate PDFs and images, the server fires up an external process which then makes HTTP calls to the server itself. This URL needs to be resolvable on the server itself. For example: server.host.internal=http://127.0.0.1:8080/panopticon/ Default Value Property Server Attribute server.id Description Specifies an id for the current server. The value of this property will be part of each metric entry so that it can be tied to a specific server if a server cluster is used. If no value is specified, the MAC address of the localhost network will be attempted to be used to identify the server. If this is not possible, a UUID will be generated. Property SOAP Attribute seap.enabled	Attribute	server.host
Property PDF and Image generation Attribute server.host.internal Description The local server endpoint address. To generate PDFs and images, the server fires up an external process which then makes HTTP calls to the server itself. This URL needs to be resolvable on the server itself. For example: server.host.internal=http://127.0.0.1:8080/panopticon/ Default Value Property Server Attribute server.id Description Specifies an id for the current server. The value of this property will be part of each metric entry so that it can be tied to a specific server if a server cluster is used. If no value is specified, the MAC address of the localhost network will be attempted to be used to identify the server. If this is not possible, a UUID will be generated. Property SOAP Attribute soap.enabled	Description	server, so it should be the server's or load balancer's public URL and needs to be resolvable from the email recipient's machine. For example:
Property Attribute Server.host.internal The local server endpoint address. To generate PDFs and images, the server fires up an external process which then makes HTTP calls to the server itself. This URL needs to be resolvable on the server itself. For example: server.host.internal=http://127.0.0.1:8080/panopticon/ Default Value Property Server Attribute Server.id Description Specifies an id for the current server. The value of this property will be part of each metric entry so that it can be tied to a specific server if a server cluster is used. If no value is specified, the MAC address of the localhost network will be attempted to be used to identify the server. If this is not possible, a UUID will be generated. Property SOAP Attribute soap.enabled		server.host=http://www.company.com/dashboards/
Attribute server.host.internal Description The local server endpoint address. To generate PDFs and images, the server fires up an external process which then makes HTTP calls to the server itself. This URL needs to be resolvable on the server itself. For example: server.host.internal=http://127.0.0.1:8080/panopticon/ Default Value Property Server Attribute server.id Description Specifies an id for the current server. The value of this property will be part of each metric entry so that it can be tied to a specific server if a server cluster is used. If no value is specified, the MAC address of the localhost network will be attempted to be used to identify the server. If this is not possible, a UUID will be generated. Property SOAP Attribute soap.enabled		
Description The local server endpoint address. To generate PDFs and images, the server fires up an external process which then makes HTTP calls to the server itself. This URL needs to be resolvable on the server itself. For example: server.host.internal=http://127.0.0.1:8080/panopticon/ Default Value Property Server Attribute Specifies an id for the current server. The value of this property will be part of each metric entry so that it can be tied to a specific server if a server cluster is used. If no value is specified, the MAC address of the localhost network will be attempted to be used to identify the server. If this is not possible, a UUID will be generated. Property SOAP Attribute soap.enabled	Property	
external process which then makes HTTP calls to the server itself. This URL needs to be resolvable on the server itself. For example: server.host.internal=http://127.0.0.1:8080/panopticon/ Property Server Attribute server.id Description Specifies an id for the current server. The value of this property will be part of each metric entry so that it can be tied to a specific server if a server cluster is used. If no value is specified, the MAC address of the localhost network will be attempted to be used to identify the server. If this is not possible, a UUID will be generated. Property SOAP Attribute soap.enabled	Attribute	server.host.internal
Property Server Attribute server.id Description Specifies an id for the current server. The value of this property will be part of each metric entry so that it can be tied to a specific server if a server cluster is used. If no value is specified, the MAC address of the localhost network will be attempted to be used to identify the server. If this is not possible, a UUID will be generated. Property SOAP Attribute soap.enabled	Description	external process which then makes HTTP calls to the server itself. This URL needs to be resolvable on the server itself. For example:
Attribute server.id Description Specifies an id for the current server. The value of this property will be part of each metric entry so that it can be tied to a specific server if a server cluster is used. If no value is specified, the MAC address of the localhost network will be attempted to be used to identify the server. If this is not possible, a UUID will be generated. Property SOAP Attribute soap.enabled	Default Value	server.nosc.incernar-nccp.//12/.o.o.1.0000/panopcrcon/
Attribute server.id Description Specifies an id for the current server. The value of this property will be part of each metric entry so that it can be tied to a specific server if a server cluster is used. If no value is specified, the MAC address of the localhost network will be attempted to be used to identify the server. If this is not possible, a UUID will be generated. Default Value Property SOAP Attribute soap.enabled		Sonyor
Description Specifies an id for the current server. The value of this property will be part of each metric entry so that it can be tied to a specific server if a server cluster is used. If no value is specified, the MAC address of the localhost network will be attempted to be used to identify the server. If this is not possible, a UUID will be generated. Default Value Property SOAP Attribute Soap.enabled		
entry so that it can be tied to a specific server if a server cluster is used. If no value is specified, the MAC address of the localhost network will be attempted to be used to identify the server. If this is not possible, a UUID will be generated. Default Value Property SOAP Attribute soap.enabled		
Property SOAP Attribute soap.enabled	Description	entry so that it can be tied to a specific server if a server cluster is used. If no value is specified, the MAC address of the localhost network will be attempted to be used to
Attribute soap.enabled	Default Value	
	Property	SOAP
Description Enable or disable the SOAP interface	Attribute	soap.enabled
	Description	Enable or disable the SOAP interface

Default Value	true
Property	Data table regression testing
Attribute	startup.regression.datatable.exclude.folders
Description	Comma-separated list of folders that will be excluded in the testing. Use this property in combination with the startup.regression.datatable.include.folders property to control which workbooks to include in the testing. For example, you can set startup.regression.datatable.include.folders to "pub\\" and startup.regression.datatable.exclude.folders to "pub\\" and startup.regression.datatable.exclude.folders to "pub\\" and startup.regression.datatable.exclude.folders to "pub\\" and "pub\" and "pub\\" and "
Default Value	
Property	Data table regression testing
Attribute	startup.regression.datatable.include.folders
Description	Comma-separated list of folders to test. The default is blank, which means the root folder and all workbooks will be tested. If you list folders here, then only the data tables in workbooks in these folders will be tested, unless also excluded. Folder paths should include a trailing backslash, and you need to use double backslashes since this is the escape character in Java property files. For example, to only include prod and qa\final, you should set the property to "prod\qa\\final\\" (without quotes).
Default Value	
Property	Data table regression testing
Attribute	startup.regression.datatable.runonce
Description	If set to true , the server will run a data table regression test during the next startup. The property is immediately reset to false , so you need to set it to true again to run another test. NOTE: You can set the property through an environment variable if you want to force the server to run it on every startup.
Default Value	false
Property	Authorization
Attribute	statistics.authorization.level
Description	Allows users to set the authorization level for the statistics and diagnostic REST services. Possible values include: ANONYMOUS , VIEWER , DESIGNER , ADMINISTRATOR . NOTE: This property is case sensitive.
Default Value	ADMINISTRATOR
Property	Statistics
Attribute	statistics.accumulated.enabled
Description	By default, the server accumulates statistics from every run into files in <appdata>/Statistics/, e.g., WorkbookStatistics_Accumulated.json. You can delete these files if you are not interested in this information, or you can set this property to false to disable the accumulation completely.</appdata>

Default Value	true
Property	Subscription
Attribute	subscription.broadcasting.pool.max.size
Description	The maximum number of threads for the broadcasting thread pools of refresh events. The default value is empty, which means that there is no limit. Any value less than 1 also means that there is no limit. When setting a max value for the thread pools, it means that the pool cannot create more than that number of threads. If there are more concurrent events handled by the thread pools than there are threads, they are queued until a thread becomes available. The thread pools are also configured to only increase the pool size if all threads are busy and a new event needs to be processed. If a thread is idle more than 1 minute, it will be removed from the pool and the size of the pool thereby decreases. Any subscription for a static data source are scheduled to refresh each X seconds (based of the refresh period of the datatable) using the TaskScheduled built in to Spring. If multiple subscriptions with the same data query tries to load data at the same time, only one thread will actually load the data. The rest of the subscriptions are queued. When the data is loaded all waiting subscriptions will be given the same data set that are then broadcasted to their respective client.
Default Value	
Property	Subscription
Attribute	subscription.compression.delta.enabled
Description	With delta compression, the server only sends the difference from the last data result on each refresh. For data where only a fraction changes on each refresh, this means much smaller response messages. The trade-offs are that both client and server need to keep the last result to calculate the difference and apply it, and that this operation takes some additional time both on the server and the client. In rare cases, delta compression may worsen performance, e.g., if you have a large data set with very high refresh rate and a large portion of the data changes on each refresh. You can then disable delta processing completely by setting this property to false .
Default Value	true
Property	Subscription
Attribute	subscription.compression.enabled
Description	Enable or disable compression and encoding of subscription broadcast messages.
Default Value	true
Property	Subscription
Attribute	subscription.congestion.control.enabled
Description	When the server loads data for a subscription, it checks that the previous data load for it has completed. If not, it might be a sign that the refresh rate is set too high on the data table. If this happens subscription.maximum.failure times in a row, the server will cancel the subscription. Set this property to false to disable this behavior.
Default Value	true
_	Subscription
Property	Gubbonphon

D	
Description	The maximum number of threads for loading thread pools of refresh events. The default value is empty, which means that there is no limit. Any value less than 1 also means that there is no limit. When setting a max value for the thread pools, it means that the pool cannot create more than that number of threads. If there are more concurrent events handled by the thread pools than there are threads, they are queued until a thread becomes available.
	The thread pools are also configured to only increase the pool size if all threads are busy and a new event needs to be processed. If a thread is idle more than 1 minute, it will be removed from the pool and the size of the pool thereby decreases.
	Any subscription for a static data source is scheduled to refresh each X seconds (based of the refresh period of the data table) using the TaskScheduled built into Spring.
	If multiple subscriptions with the same data query tries to load data at the same time, only one thread will actually load the data. The rest of the subscriptions are queued. When the data is loaded all waiting subscriptions will be given the same data set that are then broadcasted to their respective client.
Default Value	
Property	Subscription
Attribute	subscription.data_log.always_on
Description	When set to true , the data log is always passed from server to client if the user is a Designer or Admin on the server. Previously, the data log would only be passed for workbooks in design mode.
	The data log will be passed also when the data request fails. The " Invalid Configuration " message shown in the visualization will show a " Data Log " button, which will display the relevant logs and error message.
	NOTE: The actual passing of runtime exception is currently implemented in the Kdb+ connector only.
	The benefit of running a server with subscription.data.log.always_on=true is that, the data log is more easily accessed and can be viewed both as success and failure. The data log can also be viewed without having Write permissions on the folder where the workbook is used, which is helpful when connection failures need to be examined in production environments where you have restrictions on workbook editing.
	NOTE: Viewer users are not able to view the Data Log, only Designers and Admins.
Default Value	false
Property	Subscription
Attribute	subscription.limitation.action
Description	Controls the behavior when the subscription.limitation.limit is reached. Allowed values: EXCEPTION, PURGE
Default Value	EXCEPTION
Property	Subscription
Attribute	subscription.limitation.enabled
Description	Enables limitation of subscriptions.
Default Value	false
Property	Subscription
Attribute	subscription.limitation.limit

Description Defines a subscription limit. Default Value 100 Property Subscription Attribute subscription.log.slow.data.loads.seconds Description Logs a subscription that has been loading data for more than X seconds at a WARNING level. NOTES:		
Property Subscription Attribute subscription.log.slow.data.loads.seconds Description Logs a subscription that has been loading data for more than X seconds at a WARNING level. NOTES:	Description	Defines a subscription limit.
Attribute subscription.log.slow.data.loads.seconds Description Logs a subscription that has been loading data for more than X seconds at a WARNING level. NOTES: • Any integer less than 1 (or an empty value) will disable the logging. • If a slow data load has been logged and then returns data, a log message at INFO level will be printed stating that a previously logged slow data load has returned data. Default Value 80 Property Subscription Attribute subscription.maximum.failure Description The amount of time a subscription is allowed to fail in a row before it should be cancelled. The number will be reset to zero if data loading is successful. The maximum failure limit is used so that invalid subscription will not loop brever and fill the logs with error messages. The value -1 will disable the fail mechanism. This means that a subscription can fail encless of times and not be cancelled. Default Value 5 Property Subscription Attribute subscription.purge.condition Description Defines the condition for when subscriptions will be purged. Allowed values: NONE, MEMORY Default Value NONE Property Subscription Attribute subscription.purge.condition.memory.threshold Description Defines a percentual memory threshold for subscription purging, when the subscription.purge.condition = MEMORY. Default Value 80 Property Subscription Attribute subscription.purge.enabled Description Enables subscription purging. Default Value true Property Subscription Attribute subscription.purge.post.restart Default Value True Property Subscription.purge.post.restart Default Value True Property Subscription.purge.post.restart Defont to restart active subscriptions after purge. Only valid when subscription.purge.scope = ALL	Default Value	100
Description Logs a subscription that has been loading data for more than X seconds at a WARNING level. NOTES:	Property	Subscription
level. NOTES: Any integer less than 1 (or an empty value) will disable the logging. If a slow data load has been logged and then returns data, a log message at INFO level will be printed stating that a previously logged slow data load has returned data. Default Value Property Subscription Attribute Subscription in a subscription is allowed to fall in a row before it should be cancelled. The amount of time a subscription is allowed to fall in a row before it should be cancelled. The number will be reset to zero if data loading is successful. The maximum failure limit is used so that invalid subscription will not loop forever and fill the logs with error messages. The value -1 will disable the fall mechanism. This means that a subscription can fail endless of times and not be cancelled. Default Value 5 Property Subscription Attribute Subscription.purge.condition Description Defines the condition for when subscriptions will be purged. Allowed values: NONE, MEMORY Default Value NONE Property Subscription.purge.condition.memory.threshold Description Defines a percentual memory threshold for subscription purging, when the subscription, purge.condition = MEMORY. Default Value 80 Property Subscription Attribute Subscription.purge.enabled Description Enables subscription.purge.enabled Description Enables subscription.purge.enabled Description Default Value Property Subscription.purge.post.restart Description Option to re-start active subscriptions after purge. Only valid when subscription.purge.scope = ALL	Attribute	subscription.log.slow.data.loads.seconds
Attribute subscription maximum.failure Description The amount of time a subscription is allowed to fail in a row before it should be cancelled. The number will be reset to zero if data loading is successful. The maximum failure limit is used so that invalid subscription will not loop forever and fill the logs with error messages. The value -1 will disable the fail mechanism. This means that a subscription can fail endless of times and not be cancelled. Default Value 5 Property Subscription Attribute subscription.purge.condition Description Defines the condition for when subscriptions will be purged. Allowed values: NONE, MEMORY Default Value NONE Property Subscription Attribute subscription.purge.condition.memory.threshold Description Defines a percentual memory threshold for subscription purging, when the subscription.purge.condition = MEMORY. Default Value 80 Property Subscription Attribute subscription.purge.enabled Description Enables subscription purging. Default Value true Property Subscription Attribute subscription.purge.post.restart Description Option to re-start active subscriptions after purge. Only valid when subscription.purge.scope = ALL	Description	 level. NOTES: Any integer less than 1 (or an empty value) will disable the logging. If a slow data load has been logged and then returns data, a log message at INFO
Attribute subscription.maximum.failure Description The amount of time a subscription is allowed to fail in a row before it should be cancelled. The number will be reset to zero if data loading is successful. The maximum failure limit is used so that invalid subscription will not loop forever and fill the logs with error messages. The value -1 will disable the fail mechanism. This means that a subscription can fail endless of times and not be cancelled. Default Value 5 Property Subscription Attribute subscription.purge.condition Description Defines the condition for when subscriptions will be purged. Allowed values: NONE, MEMORY Default Value NONE Property Subscription Attribute subscription.purge.condition.memory.threshold Description Defines a percentual memory threshold for subscription purging, when the subscription.purge.condition = MEMORY. Default Value 80 Property Subscription Attribute subscription.purge.enabled Description Enables subscription purging. Default Value true Property Subscription Attribute subscription.purge.post.restart Description Option to re-start active subscriptions after purge. Only valid when subscription.purge.scope = ALL	Default Value	60
Description The amount of time a subscription is allowed to fail in a row before it should be cancelled. The number will be reset to zero if data loading is successful. The maximum failure limit is used so that invalid subscription will not loop forever and fill the logs with error messages. The value -1 will disable the fail mechanism. This means that a subscription can fail endless of times and not be cancelled. Property Subscription Attribute Subscription.purge.condition Defines the condition for when subscriptions will be purged. Allowed values: NONE, MEMORY Default Value NONE NONE Property Subscription Attribute subscription.purge.condition.memory.threshold Description Defines a percentual memory threshold for subscription purging, when the subscription.purge.condition = MEMORY. Default Value 80 Property Subscription Attribute subscription.purge.enabled Description Enables subscription purging. Default Value true Property Subscription Attribute subscription.purge.post.restart Description Option to re-start active subscriptions after purge. Only valid when subscription.purge.scope = ALL	Property	Subscription
The number will be reset to zero if data loading is successful. The maximum failure limit is used so that invalid subscription will not loop forever and fill the logs with error messages. The value -1 will disable the fail mechanism. This means that a subscription can fail endless of times and not be cancelled. Default Value Subscription Defines the condition for when subscriptions will be purged. Allowed values: NONE, MEMORY Default Value NONE Property Subscription Attribute subscription.purge.condition.memory.threshold Description Defines a percentual memory threshold for subscription purging, when the subscription.purge.condition = MEMORY. Default Value 80 Property Subscription.purge.enabled Description Enables subscription.purge.enabled Description Enables subscription purging. Default Value Property Subscription Enables subscription.purge.post.restart Description Option to re-start active subscriptions after purge. Only valid when subscription.purge.scope = ALIL	Attribute	subscription.maximum.failure
Property Subscription Attribute Subscription.purge.condition Description Defines the condition for when subscriptions will be purged. Allowed values: NONE, MEMORY Default Value NONE Property Subscription Attribute Subscription.purge.condition.memory.threshold Description Defines a percentual memory threshold for subscription purging, when the subscription.purge.condition = MEMORY. Default Value 80 Property Subscription Attribute Subscription.purge.enabled Description Enables subscription purging. Default Value true Property Subscription Attribute Subscription Option to re-start active subscriptions after purge. Only valid when subscription.purge.scope = ALL	Description	The number will be reset to zero if data loading is successful. The maximum failure limit is used so that invalid subscription will not loop forever and fill the logs with error messages. The value -1 will disable the fail mechanism. This means that a subscription can fail
Attribute subscription.purge.condition Description Defines the condition for when subscriptions will be purged. Allowed values: NONE, MEMORY Default Value NONE Property Subscription Attribute subscription.purge.condition.memory.threshold Description Defines a percentual memory threshold for subscription purging, when the subscription.purge.condition = MEMORY. Default Value 80 Property Subscription Attribute subscription.purge.enabled Description Enables subscription purging. Default Value true Property Subscription Attribute subscription.purge.post.restart Description Option to re-start active subscriptions after purge. Only valid when subscription.purge.scope = ALL	Default Value	5
Description Defines the condition for when subscriptions will be purged. Allowed values: NONE, MEMORY Default Value NONE Property Subscription Attribute Description Defines a percentual memory threshold for subscription purging, when the subscription.purge.condition = MEMORY. Default Value 80 Property Subscription Attribute subscription.purge.enabled Description Enables subscription purging. Default Value true Property Subscription Attribute subscription.purge.post.restart Description Option to re-start active subscriptions after purge. Only valid when subscription.purge.scope = ALL	Property	Subscription
Default Value NONE Property Subscription Attribute Subscription.purge.condition.memory.threshold Description Defines a percentual memory threshold for subscription purging, when the subscription.purge.condition = MEMORY. Default Value 80 Property Subscription Attribute Subscription.purge.enabled Description Enables subscription purging. Default Value Property Subscription Attribute Subscription Attribute Option to re-start active subscriptions after purge. Only valid when subscription.purge.scope = ALL	Attribute	subscription.purge.condition
Property Attribute Subscription.purge.condition.memory.threshold Description Defines a percentual memory threshold for subscription purging, when the subscription.purge.condition = MEMORY. Default Value 80 Property Subscription Attribute Subscription.purge.enabled Description Enables subscription purging. Default Value true Property Subscription Attribute Subscription.purge.post.restart Description Option to re-start active subscriptions after purge. Only valid when subscription.purge.scope = ALL	Description	
Attribute subscription.purge.condition.memory.threshold Description Defines a percentual memory threshold for subscription purging, when the subscription.purge.condition = MEMORY. Default Value 80 Property Subscription Attribute subscription.purge.enabled Description Enables subscription purging. Default Value true Property Subscription Attribute subscription.purge.post.restart Description Option to re-start active subscriptions after purge. Only valid when subscription.purge.scope = ALL	Default Value	NONE
Description Defines a percentual memory threshold for subscription purging, when the subscription.purge.condition = MEMORY. Default Value 80 Property Subscription Attribute Description Enables subscription purging. Default Value true Property Subscription Attribute subscription Option to re-start active subscriptions after purge. Only valid when subscription.purge.scope = ALL	Property	Subscription
Subscription.purge.condition = MEMORY. Default Value 80 Property Subscription Attribute subscription.purge.enabled Description Enables subscription purging. Default Value true Property Subscription Attribute subscription.purge.post.restart Description Option to re-start active subscriptions after purge. Only valid when subscription.purge.scope = ALL	Attribute	subscription.purge.condition.memory.threshold
Property Subscription Attribute subscription.purge.enabled Description Enables subscription purging. Default Value true Property Subscription Attribute subscription.purge.post.restart Description Option to re-start active subscriptions after purge. Only valid when subscription.purge.scope = ALL	Description	
Attribute subscription.purge.enabled Description Enables subscription purging. Default Value true Property Subscription Attribute subscription.purge.post.restart Description Option to re-start active subscriptions after purge. Only valid when subscription.purge.scope = ALL	Default Value	80
Description Enables subscription purging. Default Value true Property Subscription Attribute subscription.purge.post.restart Description Option to re-start active subscriptions after purge. Only valid when subscription.purge.scope = ALL	Property	Subscription
Default Value Property Subscription Attribute Subscription.purge.post.restart Description Option to re-start active subscriptions after purge. Only valid when subscription.purge.scope = ALL	Attribute	subscription.purge.enabled
Property Subscription Attribute subscription.purge.post.restart Description Option to re-start active subscriptions after purge. Only valid when subscription.purge.scope = ALL	Description	Enables subscription purging.
Attribute subscription.purge.post.restart Description Option to re-start active subscriptions after purge. Only valid when subscription.purge.scope = ALL	Default Value	true
Description Option to re-start active subscriptions after purge. Only valid when subscription.purge.scope = ALL	Property	Subscription
subscription.purge.scope = ALL	Attribute	subscription.purge.post.restart
Default Value false	Description	
	Default Value	false

Property	Subscription
Attribute	subscription.purge.rate
Description	Defines a fixed rate, in milliseconds. for subscription purging.
Default Value	10000
Property	Subscription
Attribute	subscription.purge.scope
Description	Defines the scope of subscriptions to purge. Allowed values: NON_PERSISTENT_ORPHANS, ALL.
Default Value	NON_PERSISTENT_ORPHANS
Property	Timeout Session
Attribute	timeout.session.enabled
Description	Boolean value stating if timeout functionality should be used or not.
Default Value	false
Property	Timeout Session
Attribute	timeout.session.exception.delimiter
Description	The delimiter to use for the usernames stated in the timeout.session.exception.usernames property.
Default Value	, (comma)
Property	Timeout Session
Attribute	timeout.session.exception.usernames
Description	Usernames that should be excluded from the timeout functionality. Separated by the delimiter stated in the timeout.session.exception.delimiter property.
Default Value	
Property	Timeout Session
Attribute	timeout.session.minutes
Description	Minutes of inactivity before a user session is terminated by logging out the user.
Default Value	480
Property	Timeout Session
Attribute	timeout.session.notification.minutes
Description	Minutes before a timeout that a notification about session timeout is sent to the user.
Default Value	1
Property	WebSocket Connection
Attribute	transport.buffer.size.max.bytes
Description	Maximum size of message buffer for the WebSocket connections.
Default Value	10000000

Property	WebSocket Connection
Attribute	transport.message.size.max.bytes
Description	Maximum size of messages for the WebSocket connections.
Default Value	1000000

10.2023

ABOUT PANOPTICON	
-------------------------	--

For more information on Panopticon and other resources, go to https://www.altair.com/panopticon.