



Altair Panopticon™ v2023.0 WEB AUTHORING GUIDE

TABLE OF CONTENTS

[1] WORKING WITH ALTAIR PANOPTICON REAL TIME WITH A DESIGNER ROLE	1
Introduction	1
Panopticon Data Types	2
Date/Time Key Elements	2
Numeric Field Formats	3
Panopticon Real Time Pages	4
The Welcome Page	
[2] THE WORKBOOKS PAGE	7
Workbooks and Folders Summary View	7
Folders and Workbooks Display View	8
Workbooks Page Primary Layouts	9
Creating a Workbook	14
[3] ADDING AND MANAGING DATA TABLES	16
Working with Add Data Table Wizard	19
Working with Workbook Internal Data Table Editor Layout	27
Adding a New Data Table Using the Workbook Internal Data Table Editor	34
Adding More Data Tables in the Workbook Internal Data Table Editor Layout	40
Rearranging Data Tables	41
Selecting a Data Table	42
Making a Duplicate of a Data Table	43
Moving a Data Table to Data Library	44
Saving a Data Table	45
Deleting a Data Table	46
Adding Data Table Parameters	46
Rearranging Data Table Parameters	48
Manually Entered SQL Queries	48
Special Server Parameters	49
Parameter Encoding and Delimiters	51
Deleting Data Table Parameters	52
Retrieving External Aggregates (Non Additive Data Sets)	53
Calculations with External Aggregates (Non Additive Calculations)	58
Managing Data Sources	59
Common Data Source Settings	64
Selecting and Defining the Data Connector File Source	64
Defining the Message Type in Data Sources	69
Defining the Format in Data Sources	70
Saving or Loading Column Definitions in the Data Sources	72
Setting Show in Timezone and Source Timezone of Data Sources	74



Setting Row Limit of Data Sources	75
Joining Multiple Data Sources in Workbook Data Table Editor	
Modifying the Join Definition	
Union All of Multiple Data Sources	
Grouping and Sorting Columns	
Creating a Custom Sort Order	
Enable Time Series Analysis	
Pivoting and Unpivoting Data	
Pivoting	
Example 1	
·	
Example 2	
Example 3	
Example 4	
Pivoting and Time Series	
Unpivoting	
R Transform	
Best Practices on Working with R Transform in Panopticon	
Example code in R	
Additional Best Practice Recommendations in Using R with Panopticon	
Python Transform	
Best Practices on Working with Python Transform in Panopticon	119
Example code in Python	120
Additional Best Practice Recommendations in Using Python with Panopticon	120
REST Transform	121
Order Book Reconstruction Transform	126
Working with Data Sources	128
Connector Availability	129
Connecting to a Data Source in the Workbook Internal Data Table Editor	130
File/URL Data Sources	131
Connector for Azure	131
Connector for Google Cloud	132
Connector for JSON	134
Supported JSON Structures	134
Connector for MS Excel (Legacy)	136
Upgrading Legacy MS Excel XLSX Data Source to the new MS Excel (xlsx) Connector	
Connector for MS Excel (xlsx)	140
Connector for S3	
Connector for SmartWorks IoT	143
Connector for SmartWorks IoT Write	
Connector for SVG	145
Creating Custom Shapes	
Drawing a Circle with Cubic Bézier Curves	
Connector for Text	
Connector for Web Data	
Connector for XML	
Database Data Sources	
Connector for Apache Cassandra	
Connector for DolphinDB	
Commoder for bolphings	107

	Connector for Elasticsearch 6.x	154
	Connector for Elasticsearch 7.x	155
	Elasticsearch Connectors Dependency Installation	156
	Connector for Google Analytics	156
	Configuring Service Account Authentication for Google Analytics	157
	2. Enabling Analytics API	160
	3. Setting Edit Permissions to the Service Account ID	162
	4. Extracting Profile ID from the URL	162
	Connector for InfluxDB	163
	Connector for JDBC Database	164
	Migration from Database to JDBC Connector	169
	Connector for JDBC Beta	
	Connector for Kx kdb+	174
	On-Demand Queries	177
	Kx kdb+ - Deferred Sync Query	177
	Host Lookup Settings in the Panopticon.properties File	178
	Connector for ksqlDB	179
	Connector for Livy Spark	180
	Connector for MongoDB	181
	Row-Wise Array Expansion	184
	Column-Wise Array Expansion	184
	Bson-Wise Array Expansion	
	Connector for OneTick	185
	Connector for OneTick Cloud	186
	Connector for Panopticon Data Extract	187
	Connector for Python	190
	Connector for Rserve	192
	Connector for Shakti (Beta)	193
	Connector for Splunk	
Streamir	ng Data Sources	194
	Connector for ActiveMQ	
	Connector for Amazon Kinesis – Data Streams	196
	Connector for AMPS	199
	Connector for DolphinDB – Streaming	
	Connector for Google Cloud Pub/Sub	
	Connector for JDBC Database – Streaming	
	Connector for Apache Kafka	207
	Connector for Kafka Publisher	
	Connector for Kx kdb+tick	212
	Connector for ksqlDB – Streaming	215
	Connector for MQTT	
	Connector for OneTick CEP	219
	Connector for Panopticon Streams	
	Connector for RabbitMQ	
	Connector for Redis Streams (Beta)	
	Connector for Solace	
	Connector for Streams Simulator	
	Connector for Streams Simulator – Extract	232

Connector for StreamBase 7.1	235
Connector for StreamBase LiveView	236
Connector for WebSocket	237
Defining Real-Time Settings	239
Defining Real-Time Settings for Apache Kafka and Panopticon Streams Connectors	242
Previewing Streaming Data	245
Highlighting the Latest Data in Real Time Streaming Connectors	246
Parameterization of Connection Settings for Data Sources	
Parameterization of Time Zones in Data Connectors	250
Searching for Columns	254
Making a Duplicate of a Data Source	254
Rearranging Data Sources	256
Deleting Data Sources	256
Adding Calculated Columns	
Adding an Auto Key Column	
Adding a Calculated Column	
Numeric Calculations	
Calculation Aggregation	266
Text Calculations	
Calculation Data Type	
Asymmetric Reporting	
Time Series Calculations	
Time Window Calculations	
Time Period Calculations	
Parameterization in Calculated Columns	
Adding Ranking Columns	
Adding Time Buckets – Categorical Time Analysis	
Adding Identity Bucketing	
Adding Numeric Sign Bucketing	
Adding Numeric Equal Distance Bucketing	
Adding Numeric Manual Bucketing	
Adding Numeric Equal Density Bucketing	
Adding Text Groupings	
Modifying User-Defined Columns	
Creating a Duplicate of a Calculated Column	
Removing User-Defined Columns	
Data Table Columns Settings	
Modification of the Column Names	
Modification of the Numeric or Date/Time Column Format	
Setting the Default Aggregation for Numeric Columns	
Setting the Min and Max Range for Numeric Columns	
Filtering Data Source Columns	
Data Storage	
	022
[4] THE DATA LIBRARY PAGE	323
Data Library Display View	225
Data Library Display View	
Adding a New Data Table in the Data library	323

Working with Data Table Editor	328
Importing To Data Store	
Removing a Data Table from Data Store	336
Working with Joined Data Table Editor	337
Joining Multiple Data Tables in the Joined Data Table Editor	
Union All of Multiple Data Tables	
Joined Data Table Error Message	
Creating Data Extracts	
Data Library Toolbar and Context Menu	
Copying Data Tables	
Moving Data Tables	
Clearing and Importing Data Table to Data Store	
Exporting Bundle for a Data Table or Folder	
Importing a Folder Bundle	
Creating Data Library Folders	
Ordaning Data Library Folders	
[5] BUILDING A WORKBOOK	362
Using the Open Workbook in Design Mode	364
Creating a Dashboard	366
Dashboard Editor Product Tour	367
Reset the Workbook Editor Tour	369
Setting the Dashboard Properties	370
Setting the Workbook Properties	372
Rearranging Dashboards	376
Making a Duplicate of a Dashboard	377
Renaming Dashboards	378
Deleting Dashboards	380
Adding Dashboard Parameters	
Deleting Dashboard Parameters	
Dashboard Design	
The Select Part Pane	
Using the Dashboard Templates	
Dashboard Canvas Grid Lines	
Maximizing Visualizations or Parts	
Expanding Visualizations or Parts	
Splitting Visualizations or Parts to Create a New One	
Resizing Visualizations or Parts	
Moving Visualizations or Parts	
Dashboard Part Toolbar	
Cutting or Copying Selected Dashboard Part	
Pasting Selected Dashboard Part	
Deleting Selected Dashboard Part	
Undo or Redo	
Aligning or Distributing Dashboard Parts	
Panopticon Visualizations	
Adding Visualizations to the Dashboards	
-	
Visualization General Settings	410

General	417
Visualization Title Rows	418
Double Click Mode	422
Automatic Parameterization	422
Help Text	425
Modifying the Data Table that is Associated to the Visualization	426
Sync	428
Synchronization of the Shared Variables in the Visualizations of a Dashboard	428
Morphing Visualizations	434
Breakdown	438
Adding Columns to the Breakdown	439
Adding Parameterized Columns to the Breakdown	445
Modifying the Columns of the Breakdown	449
Sorting the Visualization for Each Level of the Breakdown	450
Sorting the Visualization Based on the Breakdown Column Values	452
Adding Breakdowns	452
Selecting Other Breakdowns	455
Deleting Breakdowns	455
Level of Details	455
Manual	456
One Level	459
Two Levels	461
Three Levels	462
Four Levels	463
Five Levels	464
Cross Tabbing	464
Axes	470
Cross Tab Axes	470
Visualizations Axes	471
Table Visualization Axis	474
Visualization Static Filter	475
Modifying Visualization Static Filter	479
Deleting Visualization Static Filter	481
Rank Filtering	482
Rank Filtering for the Table Visualization	491
Select Variables	498
Snapshot Visualizations	498
Time Series Visualizations	499
Combination Visualizations	499
Variable Constant State	500
Associating Columns to the Variables	501
Deleting Variables from a Visualization	504
Variables Configuration	505
Size Variable Configuration	505
	507
X & Y Variables Configuration	
X & Y Variables ConfigurationZ Variable Configuration	
	508

Change Variable Configuration	509
Opacity Variable Configuration	510
BoxPlot Variable Configuration	516
Shape Variable Configuration	519
Reference Variable Configuration	525
Spread Variable Configuration	525
OHLC Variable Configuration	529
Reference Lines Variable Configuration	531
Color Variable Configuration	536
Color Variable Configuration for Text Columns Using the Palette Color Source	537
Color Variable Configuration for Text Columns Using the #RGB Color Source	540
Color Variable Configuration for Numeric Columns	545
General Colors and Shared Single Configuration	551
Icons Variable Configuration	556
Records Variable Configuration	562
Details Variable Configuration	569
Details Variable Configuration for Visualizations with Records or Visuals Variable	581
Time Axis Variable Configuration	589
Text Axis Variable Configuration for the Text Combination Graph	592
Style Variable Configuration for Visualizations	594
Supported Parameterized Variable Titles	596
Table Visualization	598
Records Variable Configuration for the Table Visualization	601
Grouping Colums in the Table Visualization	621
Aggregation Methods	626
Abs	628
Abs Sum	632
Combinations	634
Count	636
Count Distinct	637
Count Non Zero	645
Cumulative Sum	646
Cumulative Sum By Max	647
Do Not Aggregate	649
Harmonic Mean	649
Intercept	650
Level	651
Max	659
Mean	660
Min	662
Neg	663
Percentile	664
Percent of Parent	666
Count Distinct Percent of Parent and Count Distinct Percent of Total	667
Percent of Total	669
Percent of Total Change	669
Percent of Parent Reference	670
Percent of Total Reference	670

	Pos	671
	Product	673
	Ratio of Sums	674
	Sibling Rank	676
	Slope	678
	Stdev	679
	Stdevp	681
	Sum	682
	Unique	683
	Text Unique and Text Concat Distinct	684
	Weighted Harmonic Mean	687
	Weighted Mean	687
	Weighted Sample Standard Deviation and Weighted Sample Variance	688
	Weighted Population Standard Deviation and Weighted Population Variance	689
	Weighted Sum	689
Snapsh	ot Visualization Settings	690
	Bar Graph Settings	690
	Box Plot Settings	692
	Bullet Graph Settings	694
	Categorical Line Graph Settings	700
	Circle Pack Settings	702
	Donut Chart Settings	702
	Donut Gauge Settings	703
	Dot Plot Settings	703
	Funnel Chart Settings	706
	Heat Matrix Settings	707
	Map Plot Settings	
	Network Graph Settings	
	Numeric Line Graph Settings	
	Numeric Needle Graph Settings	
	Numeric Stacked Needles Graph Settings	
	Pareto Chart Settings	
	Pie Chart Settings	
	Record Graph Settings	
	Scatter Plot Settings	
	3D Scatter Plot Settings	
	Shapes Settings	
	Surface Plot Settings	
	3D Surface Plot Settings	
	Table Visualization Settings	
	Ticker Tile Settings	
	Treemap Settings	
-	Waterfall Chart Settings	
Timese	ries Visualization Settings	
	Candle Stick Graph Settings	
	Horizon Graph Settings	
	Line Graph Settings	
	Needle Graph Settings	744

	Stacked Needle Graph Settings	747
	Grouped Needle Graph Settings	749
	OHLC Graph Settings	751
	Order Book Graph Settings	752
	Price Band Graph Settings	754
	Spread Graph Settings	757
	Stack Graph Settings	759
	Timeseries Scatter Plot Settings	760
	Timeseries Surface Plot Settings	763
Combin	nation Visualizations Settings	764
	Guidelines in Using the Numeric Combination Graph	765
	Creating Density Plots in the Numeric Combination Graph	769
	Adding a Numeric Combination Graph	773
	Text Combination Settings	793
	Popup Titles in Text Combination Graph and Numeric Combination Graph	815
	Time Combination Settings	816
Legend	ls	831
	Adding a Color Legend	831
	Adding an Icon Legend	838
	Adding a Shape Legend	841
	Adding a Series Legend	845
Filters .		854
	Adding a Filter Box	854
	Filter Settings	865
	Deleting Column Filters	871
	Filter Mode Types	872
	Free Text	873
	Multiple Selection	876
	Multiple Selection Drop Down List	879
	Single Selection Drop Down List	882
	Single Selection	883
	Include/Exclude List	884
	Include List	886
	Numeric Range	887
	Date Time Range	887
	Modifying the Filter Box Layout	
	Adding a Time Filter Box	
Global	Filtering	893
	Deleting Global Filters	897
	Viewing Active Filters	898
Actions	-	899
	Interactive Parameters	901
	Time Parameters	903
	Zoom Bound Parameters	904
	Constant Parameters	
	Action Scope	
	Adding Navigation Actions	
	Adding URL Actions	

	Adding Script Actions	923
	Adding Data Update Actions	932
	Filtering Workbook Actions Based on the Dashboard Scope or Source Data Table	942
	Adding an Action Form	946
	Adding a Numeric Action Slider	958
	Adding a Numeric Range Action Slider	
	Adding an Action Button	967
	Defining Action Parameter Properties	975
	Adding an Action Date Picker	977
	Adding an Action Date Range Picker	988
	Selecting Relative Dates in Action Date Picker and Action Date Range Picker Controls	1002
	Adding an Action Dropdown	1004
	Adding an Action Text Box	1009
General	Parts	1014
	Adding a Text Label	1014
	Panel	1019
	Adding an Image Box	1023
	Adding an Iframe Part	1025
	Adding a JavaScript Part	1026
	Adding a Tabbed Panel	1029
Managir	ng Themes in a Workbook	1032
Ü	Modifying a Workbook Theme	
Color Pa	alettes in a Workbook	1044
	Creating a New Single Color Palette In a Workbook	
	Creating a New Sign Color Palette In a Workbook	1046
	Creating a New Text Color Palette In a Workbook	
	Creating a Sequential or Diverging Numeric Color Palette in a Workbook	
	Modifying Color Palettes in a Workbook	1051
	Creating a Duplicate of a Color Palette	1052
	Deleting Color Palettes in a Workbook	1053
Shape F	Palettes in a Workbook	1053
	Creating a New Shape Palette in a Workbook	1054
	Modifying Shape Palettes in a Workbook	1056
	Creating a Duplicate of a Shape Palette	1058
	Deleting Shape Palettes in a Workbook	1058
Workboo	ok Toolbar	
	Copying Dashboard Image	1061
	Ad Hoc PDF Generation	1061
	Bookmarking	1063
	Viewing and Fixing Workbook Issues	1067
Alerting.		1071
	Setting Up Alerts on the Web Client	1072
	Sorting Alerts	
	Searching for Alerts	
	Enabling Alerts on the Alerts Page	
	Displaying Active Alerts	
	Activating or Deactivating All Alerts	
	Viewing Triggered Alerts	1083

I	Importing Alerts	1084
I	Exporting Alerts	1085
ı	Modifying Alert Settings	1085
I	Deleting Alerts	1086
i	Enabling Alerts	1088
	Sample Email Alerts	1090
	Sample Web Client Alerts	1091
(Sample Webhook Alerts	1094
Using the	Open Workbook in View Mode	1097
(Context Menu	1099
	Visualization Filtering	1102
	Drilling into Visualizations	1102
	Data Export	
	Rubber Band Zoom and Selection	
	Zooming In and Out with Mouse Wheel	
	Panning Around Within the Zoomed Area	
	Setting Numeric Axis Range	
	Variable Visibility	
	Pinning Details Pop-up	
	Display the Execution Meta Data	
	Adjust Column Width in the Table Visualization	
	Hide or Display Columns in the Table Visualization	
	Displaying a Hierarchy Column in the Table Visualization	
	Additional Table Operations	
,	Adjust Width of the Text Axis Leaf in Table Visualizations	
	Move Columns in the Table Visualization	
	Visual Table Sorting	
	Setting Snapshot Time in a Time Series Visualization	
	Visualization Header Controls	
·	Exporting to Excel (TSV-format) of Visualizations	
	Toggling Between a Visualization and a Table	
	Maximize	
ı	Drilling Into, Sorting, Removing, Adding, and Swapping Columns in a Breakdown and Cross T	
•	Drilling into Hierarchy Displays	
	Removing Breakdown or Cross Tab Columns	
	Adding Breakdown or Cross Tab Columns	
	Moving Breakdown Columns	
	Toggling Between Rows and Columns of a Cross Tab	
	rogging between flows and columns of a cross rab	1172
[6] AXIS	GRAPHS	1143
	raph	
Y-Axis Gr	raph	1144
Creating	an Axis Graph	1145
,	Add a Column to the Main Axis	1145
,	Add Visual Members	1145
1	Multiple Visual Members	1145

Group By Setting for the Visual Member	1145
Value Axis Assignment	1146
Visual Member Groups	1146
Tooltip Settings	1146
Cross Tabbing	1146
Samples of Axis Graphs	1146
[7] GLOBAL PARAMETERS	1152
[7] GEODAL FARAMETERO	1132
Adding Global Parameters	1154
Modifying Global Parameters	1156
Deleting Global Parameters	1159
Refresh Global Parameters	1159
Searching for Global Parameters	1159
[8] ACCESSING WORKBOOKS AND CONTEXT MENU OPTIONS	1162
Accessing Workbooks	1162
Searching for Workbooks	1164
Workbooks Toolbar and Context Menu	1168
Sorting Workbooks	1169
Copying Workbooks	1170
Moving Workbooks	1172
Deleting Workbooks or Folders	1173
Merging or Importing Workbooks	1174
Workbook and Folder Context Menu	1176
Renaming Workbooks or Folders	1177
Creating Folders	1178
Adding Groups and Users with Allowed Authorization	1180
Adding Groups and Users with Denied Access	1182
Creating Subfolders	1185
Updating Folder or Subfolder Properties	1187
Uploading Workbooks	
Viewing Workbook History and Republishing	1192
Moving a Workbook	
Copying a Workbook	
Deleting a Workbook or Folder	
Downloading a Workbook	
Exporting a Workbook or Folder Bundle	
Importing Workbook Bundle	
Panopticon Workbook Examples	
Visualization Guide	
Example Use Cases and Sample Dashboards	
Capabilities and How to Guides	
Capabilitios and Fion to Guidos	1204
[9] WEBHOOKS	1208

Folders and Webhooks Display View	1209
Searching for Webhooks	1210
Creating Webhooks	1211
Webhooks Toolbar and Context Menu	1213
Sorting Webhooks	1214
Renaming a Webhook	1215
Moving Webhooks	1216
Copying Webhooks	1216
Deleting Webhooks	1217
Triggering Webhooks	1218
[10] MANAGING WORKBOOK THEMES	1219
Folders and Themes Display View	1219
Searching for Themes	1221
Creating a New Theme	1222
Define the Default Style Settings of a Theme	1223
Define the Custom Style Settings of a Theme	1233
Define the Color Palettes Settings of a Theme	1234
Define the General Color Settings of a Theme	1236
Define the Editor Style Settings of a Theme	1240
Define the Shape Palettes of a Theme	1240
Define the Dashboard Templates of a Theme	
Themes Toolbar and Context Menu	1243
Sorting Themes	1244
Renaming a Theme	1245
Moving Themes	1245
Copying Themes	1246
Downloading Themes	1247
Uploading Themes	1247
Deleting Themes	1249
Color Palettes	1251
Importing a Color Palette	
Exporting a Color Palette	1254
Creating a New Single Color Palette	1254
Creating a New Sign Color Palette	1256
Creating a New Text Color Palette	1257
Creating a Sequential or Diverging Numeric Color Palette	1259
Modifying Color Palettes	1262
Creating a Duplicate of a Color Palette	1263
Deleting Color Palettes	1264
Shape Palettes	
Creating a New Shape Palette	
Uploading a Shape Palette	
Downloading a Shape Palette	
Modifying Shape Palettes	
Creating a Duplicate of a Shape Palette	
Rearranging Shape Palettes	

Deleting Shape Palettes	1271
[11] PANOPTICON RESOURCES	1272
[APPENDIX]	1274
Supported Roles in Panopticon Real Time	1274
System Requirements	1275

[1] WORKING WITH ALTAIR PANOPTICON REAL TIME WITH A DESIGNER ROLE

Altair Panopticon™ supports web authoring wherein, a user with a Designer role can assemble, maintain, and publish monitoring and analysis workbooks in the Web client.

INTRODUCTION

In F	Panopticon Real Time, visual data discovery is performed through workbooks. A workbook is a collection of:
	<u>Dashboards</u> (Visual Layouts)
	Data tables (Data Query and Schema Definitions)
	Actions (Contextual Interaction Definitions)
	Overall styling
Das	shboards may consist of several parts including: visualizations, legends, filters, action controls, labels, and images.
	a tables output both data schemas and data conduits, and define the queries and source data repository initions, to retrieve data. They do not store data but are simply the conduit to which data flows through.
retr bas	e core of the product is the processing of data, which can range from Real Time Streaming datasets, that are ieved asynchronously, to static and historical datasets and are retrieved synchronously on a defined periodic sis. It is assumed that data is never at rest, and consequently, data refresh is an automatic operation across all asets.
Dat	a sources can be connected to directly, with data retrieved on the fly as it is required.
Dat	a can be accessed in several methods, depending on the need and source repositories capabilities:
	Retrieve all data into memory.
	For example, retrieving an MS Excel spreadsheet.
	Retrieve subsets into memory, which may be summarized, or parameterized.
	For example, retrieving a summary view, and then retrieving a detailed dataset, based on the selection in the summary view. This method provides very tightly controlled data retrieval times but requires the paths through data to be pre-specified, with pre-defined data queries (including stored procedures).
	Retrieve only required results into memory, by querying on demand, pushing aggregation and filtering tasks to underlying big data repositories, or queryable data stores.
und	s is commonly known as a ROLAP implementation, where the product is dynamically writing data queries to the derlying data repository and retrieving aggregated and filtered datasets. Given the on-demand nature of this thod, it is more suitable to exploratory data analysis but requires dynamic query generation.

In the following sections the product will be demonstrated, starting with the various layouts, the definition of data retrieval and then the building of dashboards. Other topics include working with webhooks, setting up alerts, and

configuring workbook themes.

Panopticon Data Types

Panopticon Real Time has three data types:

Data Type	Description
Text	Stored as String.
<u>Time</u>	Stored as java.util.Date + long (64-bit int) picoseconds.
Number	Stored as Double (64-bit float), assuring value precision in at least 15 decimal digits. For integer values loaded from a data source, full precision covers the span from -253 to 253 (-9,007,199,254,740,992 to 9,007,199,254,740,992).

Date/Time Key Elements

The key elements of the Date/Time format include:

Component	Format
Year	уууу
Month	MM
Month as an abbreviation	MMM
Day	dd
Hour (24-hour clock)	нн
Minute	mm
Second	ss
Hour (12-hour clock; a.m./p.m.)	tt
Millisecond	SSS
Microsecond	SSSSSS
Nanosecond	SSSSSSSS
Space/separator (required if time is specified)	'Т'
Zulu (Greenwich Mean Time)	'Z'
Time zone (ISO 8601 time zone)	X
UNIX Epoch time	POSIX
Milliseconds since UNIX Epoch time	POSIXMILLIS
Seconds since midnight	Seconds
Milliseconds since midnight	Millis
Microseconds since midnight	Micros
Nanoseconds since midnight	Nanos

NOTE

 To parse and format times with higher than millisecond precision, the format string needs to end with a period followed by sequence of uppercase S. There can be no additional characters following them.

For example: yyyy-MM-dd HH:mm:ss.SSSSSS

• The "Seconds", "Millis", "Micros", and "Nanos" formats are used for parsing of the data in the data connectors and not for the display of the Date/Time columns.

Numeric Field Formats

The numeric field formats set in the *Data Table Settings* pane are used in the *Format* field for numbers that will be displayed in the dashboards, either in tables, filters, or in visualization pop-up details.

Useful formats include:

Format	Description
0.0 %	Produces a percentage with a single decimal place. The percentage will be 100 times the original value.
0.0 '%'	Displays a number and adds a percentage suffix. In this case the number will not be multiplied.
#,##0	Produces a number without any decimal places plus the thousand separator
#,##0.00	Produces a number with two decimal places plus the thousand separator.
#,##0.0000	Produces a number with four decimal places plus the thousand separator.
#,##0.##	Produces a number with two decimal places if a decimal exists. Otherwise no decimal will be displayed.
#,##0;(#,##0)	Produces a number without any decimal places, and with a thousand separator, where negative numbers are displayed in parenthesis
n	Produces numbers with two decimal places (for example, #,##0.00).
Р	Produces percentages with two decimal places (for example, 0.00 %).
#,##0; #,##0	Similar to #,##0, except that there will be no distinction between negative and positive numbers. This number format can be used to display Ranking on a Line Graph producing a Bump Chart.
0%	Produces a percentage without any decimal place. The percentage will be 100 times the original value.
0.00%	Produces a percentage with two decimal places. The percentage will be 100 times the original value.
0.00%;(0.00%)	Produces a percentage with two decimal places where negative numbers are displayed in parenthesis.
\$#,##0	Produces a number without any decimal places, and with a thousand separator with a USD prefix.

NOTE	You can also specify a customized format.
------	---

PANOPTICON REAL TIME PAGES

A designer role has access to six pages, i.e., Welcome, Workbooks, Data Library, Webhooks, Alerts, Parameters, and Themes.


Altair Panopticon[™] Workbooks Data Library Webhooks Alerts Parameters Themes D

Page and Descriptions

Page	Description		
<u>Welcome</u>	The first screen that displays when you log on to Panopticon Real Time.		
Workbooks	Allows you to: View, create, upload, rename, move, copy, download, merge, remove workbooks, and publish/republish them into folders to which the user has permissions to Import and export workbooks bundle Search for workbooks		
Data Library	Allows you to: Create a data table Create a joined data table Search for data tables (data store, live, joined, extracts) Rename, move, copy, export bundles, remove, view the details of a data table Clear and/or import data to data store		
Webhooks	Allows you to create, rename, move, copy, remove, and trigger webhooks.		
Alerts	Allows you to: View alert definitions and events Import and export alerts Deactivate or activate all alerts Show all active alerts Search for alerts Clear all alert events		
<u>Parameters</u>	Allows you to: Create global parameters Refresh parameters Search for parameters		
Themes	 Allows you to: Create a new theme including default styles, custom styles, color palettes, general colors, editor, shape palettes, dashboard templates Copy, download, or reset a theme to default Search for theme 		

The Welcome Page


The *Welcome* page is the first screen that displays when you log on to Panopticon Real Time. This page can also be accessed by clicking the **Altair Panopticon** logo on the header.



From this page you can:

- Open recently viewed workbooks (if available)
- Create a new workbook
- Open the Web Authoring Quick Start Guide
- View online documentation and help

Canceling the Login page displays this Welcome page.




Instead of *Create a Workbook*, the *Explore* section is available where you can explore the workbooks available in your organization.

[2] THE WORKBOOKS PAGE

WORKBOOKS AND FOLDERS SUMMARY VIEW

Clicking the **Workbooks** tab displays the *Workbooks* page with the workbooks and folders summary. This is a sample view with a personal folder (i.e., **My Workspace**) and four workbooks.



Workbooks and Folders Summary Layout Sections and Descriptions


Section	Description
1	Folders List of folders where workbooks can be saved or published.
2	Folder Context Menu Allows <u>creating</u> , <u>renaming</u> , <u>removing</u> , <u>exporting</u> or <u>importing</u> bundles, and assigning <u>permissions</u> of folders. Also, <u>creating</u> and <u>uploading</u> workbooks.
3	Search Workbook Entering text will filter the returned workbooks.


Section	Description
4	Toolbar Allows sorting, copying, moving, merging, and removing of workbooks. Also, to display the workbooks list either on List View or Grid View.
5	Create Workbook Allows creating a new workbook.
6	Quick Access List List of recently opened workbooks.
7	Folders List Available folders on List View.
8	Workbooks List Available workbooks on <i>List View</i> .
9	Workbook Context Menu Allows renaming, viewing history and republishing, moving, copying, downloading, exporting bundles, and removing workbooks.


FOLDERS AND WORKBOOKS DISPLAY VIEW

Workbooks can be displayed either on a List or Grid View.

On the *Toolbar*, click **List View** , the workbooks are displayed in a standard listing.







On either display view style, clicking on a workbook title or thumbnail displays the workbook on the Open Workbook in View Mode.


WORKBOOKS PAGE PRIMARY LAYOUTS

There are four primary layouts to define and manage workbooks:

Workbooks and Folders Summary


This layout allows you to:

- Manage workbook folders
- <u>Create, view, upload, sort, rename, copy, move, merge, delete, download, export bundle, view history and republish workbooks</u>
- Search for workbooks



Workbook Internal Data Table Editor

Allows the process of collecting, cleaning, transforming, and consolidating data into one data table, primarily for use in analysis.




You can also use the Add Data Table Wizard to add and manage data tables.

Open Workbook in Design Mode

Allows you to build dashboards by adding <u>visualizations</u>, <u>filters</u>, <u>action controls</u>, <u>legends</u>, <u>labels</u>, and <u>images</u> based on the data tables that were added.

Here is an example workbook with the components in design mode:




Once a workbook is open, it will display all dashboards as separate tabs, and list all data tables it utilizes in the *Data Table* pane to the left of the screen. Selecting a visual will automatically select the linked data table, or alternatively the data table can be manually selected through the drop-down list box.

For more information on how to use the *Open Workbook in Design Mode* view, refer to <u>Using the Open Workbook in Design Mode</u>.

Open Workbook in View Mode

This layout shows the workbook on the Web client that allows users to analyze fully interactive dashboards.





For more information on how to use the *Open Workbook in View Mode* view, refer to <u>Using the Open Workbook in View Mode</u>.

NOTE

The **Back** button allows going back to the root folder. It is only available on the toolbar section of the <u>Open Workbook in Design Mode</u> and <u>Open Workbook in View Mode</u> if startURL is available in the workbook.json file located in <appdata>/JavaScriptConfiguration/.

```
{
  "allowOrigin" : "",
  "baseUrl" : "..",
  "forceClientSelectionHandling" : true,
  "startUrl" : "../",
  "subscriptionCompression" : true,
  "webGlEnabled" : true,
  "dataLoadTransport" : "WEBSOCKET",
  "pdfMultiplePagesEnabled" : true,
  "automaticReconnectOnServerDisconnect" : true,
  "localization" : {
    "defaultLocale" : "en-US"
  }
}
```

However, for the **Back** button to use the browser history to navigate back despite startUrl being set in the file, add useBrowserHistoryToNavigateBack and set to true.

```
{
  "allowOrigin" : "",
  "baseUrl" : "..",
  "forceClientSelectionHandling" : true,
  "startUrl" : "../",

  "useBrowserHistoryToNavigateBack" : true,
  "subscriptionCompression" : true,
  "webGlEnabled" : true,
  "dataLoadTransport" : "WEBSOCKET",
  "pdfMultiplePagesEnabled" : true,
  "automaticReconnectOnServerDisconnect" : true,
  "localization" : {
     "defaultLocale" : "en-US"
}
```


After updating the workbook. json file, restart the Panopticon application.

CREATING A WORKBOOK

A user with a Designer role can create new workbooks and publish them into folders to which the user has permission.

Steps:

- 1. Create a workbook by doing one of the following:
 - Click
 New Workbook
 on the Welcome or Workbooks page.
 - Right-click on a folder or sub-folder then select New Workbook in the context menu on the Workbooks page.




The New Workbook dialog displays.



2. Enter the name of the workbook then click




The new workbook with a dashboard page (named **Dashboard1**) is displayed on the *Open Workbook in Design Mode*.



The dashboard name by default is editable. You can enter a descriptive dashboard name.

To proceed in creating a workbook, data tables must be added first. On the *Data Table* pane, there are three options to add or edit data tables.



See Adding and Managing Data Tables for more information.


[3] ADDING AND MANAGING DATA TABLES

You must select the data table you want to use in a Panopticon workbook. The data table definition can be unique to a single workbook. You can also save the data table definition locally for other users or publish the data table template.

Adding and managing data tables can be done via one of four ways:

Add Data Table Wizard in a Workbook

On the Data Table pane, click Add Data Table . The Add Data Table Wizard displays.



This wizard allows you to fetch data from data sources and data library.


See Working with Add Data Table Wizard for more information.

■ Edit Data Table Wizard in a Workbook

On the *Data Table* pane, select a data table in the drop-down list and then click either of these **Edit Data Table** icons:


for data table saved to the workbook

The Edit Data Table Wizard displays.



• for data table saved to the data library

The Data Table Editor displays.



For more information on working with this view, see Working with Data Table Editor.

NOTE

The Edit Data Table icon is disabled if:

- The selected data table is too complex to allow editing in the wizard. In this instance, use the <u>Workbook Internal Data Table Editor</u> layout instead.
- A data table has not yet been added.
- Workbook Internal Data Table Editor in a Workbook


On the Data Table pane, click Workbook Data table Editor. The Workbook Internal Data Table Editor displays.



See Working with Workbook Internal Data Table Editor for more information.

Data Library Page

Click the Data Library tab. The Data Library page displays.



See The Data Library Page to create data tables that will be used in building workbooks.

WORKING WITH ADD DATA TABLE WIZARD


The number of steps in the *Add Data Table Wizard* will be based on whether you selected a data table from the Data Library or a connector to configure.

Selecting a Data Table in the Add Data Table Wizard

If there are available data tables that were selected in the *Data Library* page, the **Data Library** tab will be selected. This option has two steps:


1. Select Data Table.

Select a data table in the list.



2. Preview Data.

Displays the preview of the data table you selected.




Do one of the following:

Property	Description
1	Search Columns Allows searching of columns in the Data Preview.
2	Data Preview Executes the queries to return and display data. NOTE: The maximum number of rows displayed in the Data Preview is 100.
3	Open in Data Library Editor Displays the Data Table Editor layout where you can further configure the data table.
4	Group and Sort Columns Allows grouping and sorting columns.


Click to save the changes and close the wizard.

Your data will be displayed in the columns of the Data Table pane.



Data tables added from the <u>Data Library</u> using the *Add Data Table* wizard can be refreshed and deleted from the *Data Table* pane.

Click the drop-down list and hover on a data table.



You can do one of the following:

- Click to reload linked data table to reflect the updates done in the Data Library.
- Click to delete the linked data table.


Selecting a Connector in the Add Data Table Wizard

This option consists of three steps:

1. Select Connector.

Click any of these data source group tabs:


File/URL



Then select one of the following data sources:

• <u>Azure</u>	Google Cloud	• JSON
MS Excel (legacy)	MS Excel (xlsx)	• <u>\$3</u>
<u>SmartWorks IoT</u>	SmartWorks IoT Write	• <u>SVG</u>
• <u>Text</u>	Web Data	• <u>XML</u>


Database



Then select one of the following data sources:

• <u>Cassandra</u>	• <u>DolphinDB</u>	Elasticsearch 6.x
Elasticsearch 7.x	Google Analytics	• <u>InfluxDB</u>
• JDBC	JDBC Beta	• Kx kdb+
• KsqlDB	• <u>LivySpark</u>	• MongoDB
OneTick	OneTick Cloud	Panopticon Data Extract
• <u>Python</u>	• Rserve	Shakti Beta
• <u>Splunk</u>		

Streaming




Then select one of the following data sources:

ActiveMQ	Amazon Kinesis – Data Streams	• AMPS
DolphinDB - Streaming	Google Cloud Pub/Sub	JDBC Database - Streaming
• <u>Kafka</u>	Kafka Publisher	Kdb+ Tick
KsqlDB – Streaming	• MQTT	OneTick CEP
Panopticon Streams	RabbitMQ	Redis Streams
• <u>Solace</u>	Streams Simulator	Streams Simulator - Extract
StreamBase 7.1	StreamBase LiveView	WebSocket


2. Configure.

Define the connection settings of the selected data source (e.g., MS Excel (legacy)).



When the necessary properties have been defined, the **Next** button is enabled.

to move to the next step.




Panopticon Web Authoring Guide

Click

3. Preview Data.

Displays the preview of the data table you are creating.




Do one of the following:

Property	Description					
1	Search Columns Allows you to search for columns in the Data Preview.					
2	Data Preview Executes the queries to return and display data. NOTE: The maximum number of rows displayed in the Data Preview is 100.					
3	 Save to Data Library or Workbook Allows you to save the data table in the <u>data library</u> or in the workbook. Selecting Workbook displays Open in Data Table Editor. Save to Data Library Workbook Open In Data Table Editor					
	Clicking Open in Data Table Editor displays the <u>Workbook Internal Data Table</u> <u>Editor</u> layout where you can further configure the data table.					
4	Group and Sort Columns Allows grouping and sorting columns.					

Click to save the changes and close the wizard.

Your data will be displayed in the columns of the *Data Table* pane. For this example, the data table is saved in the workbook.



WORKING WITH WORKBOOK INTERNAL DATA TABLE EDITOR LAYOUT


This data table editor accessed in a workbook allows you to quickly connect to any data source and combine data from multiple sources so you can visualize all your data in a single visualization.

Connecting to data environments is easy with pre-built connectors to a wide variety of sources right out of the box.

However, to get the most of these data and produce effective visualizations, they may need to be:

- Integrated with other data sources or files to produce a data with more sense.
- □ Transformed for normalization and aggregation.

The Workbook Internal Data Table Editor layout is displayed as below, where in this example, there are joined data sources:




Workbook Internal Data Table Editor Sections and Definitions

Section	Description				
1	Back Exit the Workbook Data Table Editor view and go to the Open Workbook in Design Mode view.				
2	Data Table List of data tables. Can be <u>rearranged</u> .				
3	Toolbar After the data is successfully retrieved, three options on the Workbook Data Table Editor layout allows: Making a duplicate of the data table Moving data table to data library Deleting the data table				
4	Search Columns Allows searching of columns on the Data Sources Preview.				
5	Data Preview Executes the queries to return and display preview of the data table you are creating.				

Section	Description
	NOTE: The maximum number of rows displayed in the Data Preview is 100.
6	Add Data Table or Select Data Template Add data table or select a data table template.
7	Data Table Parameters Add or manage data table parameters.
8	Data Table Settings Definition of the name of the selected data table, description, and the auto refresh period (in seconds). Also allows the retrieval of external aggregates and set custom message to be displayed upon unsuccessful data connection.
9	Group and Sort Columns When the Column Order is set to Sorted, the columns are grouped by type (Text, Date/Time, then Numeric) and sorted alphabetically.
10	Data Sources One or more data sources that can be connected to directly, with data retrieved on the fly as it is required. Can be <u>rearranged</u> .
11	Join/Union All Definition Allows definition of a join or union all of multiple data sources.
12	Duplicate Data Source Allows creating a duplicate data source
13	Add Data Source Allows adding data sources from the available data connectors.
14	Connector Settings Displays the connector settings of the data source and allows for <u>limiting the amount of data to be returned.</u>
15	Preview Selected Data Source Preview the selected data source on the Data Preview panel.
16	Refresh Preview Refresh the data sources preview.
17	Save Data Table Save the data table definition and go to the Open Workbook in Design Mode view.
18	Row Limits Settings Allows setting of the <u>row limit</u> of data sources.
19	Collapse Data Preview Collapse the Data Preview pane. Click to expand the Data Preview pane.


NOTE Most of these sections are also a Library page.	available in the <u>Data Table Editor</u> in the Data
--	---

Clicking Calculated Columns a displays the New Column list box.




Option	Description		
Add Auto Key	Allows creation of an <u>auto key</u> for the data schema on the <i>Data Sources Preview</i> .		
Add New Calculated Column	Allows creation of a <u>calculated column</u> from the existing columns in the data table.		
Add New Ranking Column	Allows creation of a new numeric column based on the <u>ranking</u> of columns in your data.		
Add New Time Bucket Column	Allows creation of time buckets (categorical time analysis).		
Add New Numeric Bucket Column	Allows creation of <u>Identity</u> , <u>Sign</u> , <u>Manual</u> , <u>Equal Density</u> , and <u>Equal Distance</u> columns.		
Add New Text Grouping	Allows creation of a grouping based on source text column.		


Clicking **Debug** b displays the *Debug* pane.



Section	Description			
1	Data Table Id Id of the data table. Can be used for parsing of server logs.			
2 Data table is used on dashboard(s) List of dashboards where the data table is used. If a data table is not used, it can be				
3	Data Log Details of the execution meta data which includes the data source name, response time, and duration (ms).			
4	Parameters Parameters in the data table.			
5	Logs Logs of the last query. IMPORTANT: In Panopticon version 2023.0, query logging is only available for the Kx kdb+ connector.			




Clicking **Transform Settings** displays the *Transform Settings* pane.



Section	Description		
Transform Settings	Allows you to perform the following:		
	<u>Pivoting</u> or <u>unpivoting</u> retrieved data.		
	• Transforming data to enable <u>time series analysis</u> including interpolation.		
	 Running an R or Python script for data transformation. 		
	 Lists of orders to be <u>reconstructed into an Order Book</u> and conflated for output display. 		

Clicking Columns displays the Columns Settings pane.



Section	Description		
Columns Settings	Allows you to perform the following:		
	View the column <u>data type</u>		
	Rename the column names		
	Select the <u>numeric</u> or Date/Time <u>format</u>		
	Select the <u>numeric default aggregation</u>		
	Define the Min and Max range of numeric columns		
	Define <u>custom sort order</u>		


Adding a New Data Table Using the Workbook Internal Data Table Editor

In the Workbook Data Table Editor, follow the steps below to add data tables.

Steps:

☑ Workbook Data Table Editor 1. On the Data Table pane, click


The Workbook Internal Data Table Editor view displays. ← Back Data Tables Data Table Settings



2. On the Data Tables pane, click and select New Data Table:




A new data table instance is created.




In the *Connector List* pane, some connectors require additional third-party software installation to be enabled. This typically requires adding JAR files to the <code>Lib</code> folder of the Tomcat installation and restarting Tomcat. For the supported Elasticsearch connectors, refer to the <u>Elasticsearch Connectors Dependency Installation</u> section. For the other connectors, refer to *Panopticon Real Time Installation and Reference Guide* for more information.

3. On the *Data Table* Settings pane, enter the *Title* of the data table and click . The new name is applied to the data table under the *Data Tables* pane and on the *Data Sources* panel.



4. Enter the Description of the data table.

This is also displayed under the data table instance which can be helpful when selecting among the data tables in the list.



5. You can opt to enter the Auto Refresh period.

This property defines how often the data source is checked for new data, when accessing the source directly. Panopticon will issue new queries at the interval shown in the *Auto Refresh* (s) box and automatically deliver updates to the workbook. The default is **900 seconds** (**15 minutes**). The minimum refresh period depends on the performance of your data repository and the amount of time required executing your data queries.

If a streaming source is selected, the refresh period is ignored.

NOTE

- Setting the Auto Refresh field to any value less than or equal to zero will
 disable the auto refresh for the data table.
- The Auto Refresh property is a string and can be parameterized.
- 6. You can also opt to enter a custom *Error Message* that will be displayed when an error occurs while fetching data.



- 7. To add a data source, click a data source group tab.
 - File/URL

Then select one of these data sources:

•	<u>Azure</u>	•	Google Cloud	•	<u>JSON</u>
•	MS Excel (legacy)	•	MS Excel (xlsx)	•	<u>S3</u>
•	SmartWorks IoT	•	SmartWorks IoT Write	•	SVG
•	<u>Text</u>	•	Web Data	•	<u>XML</u>

Database

Then select one of these data sources:

• <u>Cassandra</u>	• <u>DolphinDB</u>	Elasticsearch 6.x
Elasticsearch 7.x	Google Analytics	• <u>InfluxDB</u>
• JDBC	JDBC Beta	• Kx kdb+
• KsqlDB	• <u>LivySpark</u>	• MongoDB
OneTick	OneTick Cloud	Panopticon Data Extract
• <u>Python</u>	• Rserve	Shakti Beta
• <u>Splunk</u>		

Streaming


Then select one of these data sources:

ActiveMQ	<u>Amazon Kinesis – Data</u> <u>Streams</u>	• AMPS
DolphinDB - Streaming	Google Cloud Pub/Sub	JDBC Database - Streaming
• <u>Kafka</u>	Kafka Publisher	• Kdb+ Tick
KsqlDB – Streaming	• MQTT	OneTick CEP
Panopticon Streams	RabbitMQ	Redis Streams
• Solace	Streams Simulator	Streams Simulator - Extract
StreamBase 7.1	StreamBase LiveView	WebSocket


- 8. Tap the **Preview Selected Data Source** slider to turn it on and display the preview of the selected data source.
- 9. Then, you can either click:
 - o Refresh Preview for static connectors

 ► Start Preview
 - for streaming connectors

The retrieved query/table/sheet/schema is displayed in the *Data Sources* panel. The system displays the preview data at the bottom of the screen.



Click to collapse the *Data Preview* pane.




- Click to expand the Data Preview pane.
- 10. After adding data sources, you can also:
 - Manage data source properties
 - Define transform settings

- Retrieve external aggregates
- Add data table parameters
- Sort columns
- Define a join or union all of the data sources
- Add user defined columns such as:
 - Auto key
 - Calculated column
 - Ranking column
 - Time bucketing column
 - Numeric bucketing (<u>Identity</u>, <u>Sign</u>, <u>Manual</u>, <u>Equal Density</u>, and <u>Equal Distance</u>)
 - Text grouping column




11. Click the Save

When saved, the notification displays:



12. Click . You are returned to the <u>Open Workbook in Design Mode</u>, with the new data table added in the <u>Data Table</u> pane drop-down list.



IMPORTANT

The succeeding sections in this chapter mostly apply to the *Workbook Internal Data Table Editor* layout.


Adding More Data Tables in the Workbook Internal Data Table Editor Layout

You can add several data tables that you can use to build the different visualizations and parts in the dashboards of a workbook.

Steps:

1. On the Data Table pane, click Workbook Datatable Editor


The Workbook Internal Data Table Editor view displays.



2. On the Data Tables pane, click and select **New Data Table**.



A new data table is added in the list and the *Workbook Internal Data Table Editor* view changes to display the enabled *Data Table Settings* and *Data Sources* panel.



3. Repeat steps 3 to 11 of the Adding a New Data Table section.

Rearranging Data Tables


The order of the data tables can be rearranged.


Steps:

1. Click a data table you want to move.

The **Hand Hover** Ticon displays along with the blue marker before or after a data table where you can drop the item.

2. Drag and drop the data table to the desired position.






3. Click the **Save** button.

When saved, the notification displays.


Selecting a Data Table

Click a data table in the Data Tables list to display it in the Data Table Settings and Data Sources Settings panes.




Making a Duplicate of a Data Table

Click the **Duplicate** button of a data table in the *Data Tables* list.



The data table is duplicated.




Moving a Data Table to Data Library


A data table that was created in the Workbook Internal Data Table Editor can be moved to the Data Library.

Steps:

1. Click the **Move to Data Library** icon of a data table in the *Data Tables* list.




The Move to Data Library dialog displays.



- 2. You can opt to enter a new *Name* of the published data table template.
- 3. Select the folder or subfolder where the data table template will be published.



The moved notification message displays.



NOTE

- The data table is removed from the Data Tables pane in the Workbook Internal Data Table Editor.
- The original data table is removed from the workbook and replaced with a linked data table, pointing to the data library.

Saving a Data Table

Save the settings in the Workbook Internal Data Table Editor view by clicking . A notification message displays.




To close the Workbook Internal Data Table Editor view without saving the changes made, click



Deleting a Data Table

Click the **Delete** button of a data table in the *Data Tables* list. A notification message displays when the data table is in use on the dashboard.




ADDING DATA TABLE PARAMETERS

Parameters filter the data set returned to the visualization. Parameters are especially valuable when programming <u>Actions</u> in a workbook. You can use the parameters function to pull and enter specific data into SQL queries, web searches or other actions that you may wish to program as part of a workbook.

Steps:


- 1. On the *Data Table Settings* pane, click + Parameter A new parameter displays (i.e., **New Parameter 1**).
- 2. Click New Parameter < number>.

The section expands to allow definition of the parameter name and default value.



- 3. Enter the parameter *Name* then click \checkmark .
- 4. Select the *Type*: **Text**, **Numeric**, or **Time**.
- 5. Enter the Default Value.

You can enter several default values, separated by a comma.



NOTE

For the Time type, the following formats for the default value are accepted:

- "yyyy-MM-dd"
- "yyyy-MM-ddTHH:mm:ss"
- "yyyy-MM-ddTHH:mm:ss.SSS"
- 6. Repeat steps 1 to 5 to add more parameters.
- 7. Click the **Save** button.

The Data Sources Preview at the bottom of the screen updates based on the default parameter values.

NOTE

When adding <u>visualizations</u> or parts on the <u>dashboard</u>, the associated <u>data</u> <u>table</u> is checked for defined parameters that will be applied to the dashboard.

Rearranging Data Table Parameters


The order of the data table parameters in the Data Table Editor layout can be rearranged.


Steps:

1. Click on a parameter you want to move.

The **Hand Hover** Y icon displays along with the blue marker before or after a data table parameter where you can drop the item.

2. Drag and drop the parameter to the desired position.






3. Click the **Save** button. When saved, the notification displays.

Manually Entered SQL Queries

Panopticon Real Time will dynamically update the SQL query to use the parameters you have set up by putting the parameter name within curly brackets: **{parameter}**. Adding a dollar symbol prefix to the parameter is still supported for backward compatibility.

In this example, the software will replace the {Symbol} item in the SQL query with the Default Value.

In our example below, the *Default Value* is set to **MSFT**, the stock ticker symbol for Microsoft.



Based on this parameter setup, Panopticon Real Time will dynamically update this SQL Query:

```
SELECT * FROM Static WHERE Ticker = {Symbol}
```

and replace it with this:

SELECT * FROM Static WHERE Ticker = MSFT

NOTE

Depending on your setting on the data table regarding quotes around parameters, you should – or should not – put the default value of the parameter within quotes.

As there may be more than one value being returned by the parameter a more appropriate WHERE clause syntax would be:

```
SELECT * FROM Static WHERE Ticker IN ({Symbol})
```

The selection is labeled Enclose parameters in quotes and can be selected or unselected.

When this option is selected, the software will automatically put parameter values within quotes, and the default value should be specified *with* quotes, since the SQL query should *not include* quotes:

Default value: 'MSFT'

```
SELECT * FROM Static WHERE Ticker = {Symbol}
```

When this option is unselected, the software will *not* put parameter values within quotes. Therefore, as required for correct SQL syntax, you should include quotes in your SQL query. Consequently, your default parameter value must be specified *without quotes:*

Default value: MSFT

```
SELECT * FROM Static WHERE Ticker = '{Symbol}'
```

This option is unchecked typically when dynamically parameterizing column selection.

Special Server Parameters

Panopticon supports the following built-in parameters with special usage. The parameters are evaluated strictly server-side. This means that they can be referenced in data source settings, for example in a query statement or a text connector text input, to include them in columns in a data table. However, the parameters cannot be referenced

in for example visualization titles or dashboard text boxes, since they are not assigned a value in the web client. Any value passed to the server from the client will be ignored and overridden with the server's value. The special server parameters are all case-sensitive and include:

Parameter Name	Description	Value	Old Name
_current_time	Returns the Date/Time of the current time with millisecond precision.	2021-02-24T05:18:47Z	CurrentTime
_current_time_utc	Same as _current_time but in UTC, therefore not dependent on the server's time zone.	2021-02-23T21:18:47	
_dashboard_name	Returns the name of the dashboard.	SysParamsDashboard	
_datatable_name	Returns the name of the data table.	42d8cd06-a99f-4a54- 8f1b-378585cf	
_datatable_title	Returns the title of the data table.	SysParamsTable	
_last_workday	Returns the last business Date/Time with millisecond precision (excludes Saturdays and Sundays).	2021-02-23T05:18:47Z	LastWorkDay
_quarter_start	Returns the date of the most recent start/first day of the quarter period (i.e., 1st January, 1st April, 1st July, 1st October) with the time set to midnight.	2021-01-01T08:00:00Z	QuarterStart
_user_id	The username stripped of domain information and converted into lower case. (If it contains a back slash, only the part after the first back slash is returned.) The _user_id parameter can then be used as the basis for a data query filter clause, limiting the returned results to be specific to the user's profile.	stefan_odelfalk	userid
_user_name	Returns the username exactly as it appears in the Identity.	DWCH\Stefan_Odelfalk	username
_timezone	Returns the name of the system clock timezone.	Europe/Stockholm	
_timezone_offset	Returns the difference, in hours, of (current time) minus (current time UTC).	+01:00	
_week_start	Returns the current Date/Time with millisecond precision of the most recent Monday.	2021-02-23T05:18:47Z	WeekStart
_workbook_folder	Returns the workbook folder.	examples\	
_workbook_name	Returns the workname name.	SysParamsWorkbook	

NOTE

The parameter names **userid** and **username** was historically reserved by the system but have now been replaced by **_user_id** and **_user_name**. The old names still function as aliases for these system parameters so that old workbooks do not break.

Other special usage parameters relate to time series analysis and the use of the time filter box which including the following: TimeWindowStart TimeWindowEnd Snapshot When the time filter box handles are moved to filter on a time window, these special parameters will automatically receive the updated date-times, in ISO UTC format. For example: 02/Jan/2008 00:00:00 14/Nov/2008 00:00:00 06/Mar/2009 00:00:00 Produces:

TimeWindowStart = 2008-01-02T00:00:00Z

TimeWindowEnd = 2009-03-06T00:00:00Z

Snapshot = 2008-11-14T00:00:00Z

For example:

26/Mar/2008 16:17:13 22/Dec/2008 00:00:00 09/Jan/2009 17:50:47

Produces:

TimeWindowStart = 2008-03-26T16:17:13Z TimeWindowEnd = 2009-01-09T17:50:47ZSnapshot = 2008-12-22T00:00:00Z

These parameters can then be used as appropriate to restrict the amount of time series data returned in the resultant

Typically, when Time parameters are used, they are written for visual display, or for input into a data query.

The curly bracket syntax is used to determine the display format.

For example:

{TimeWindowStart} produces: 2008-03-26T16:17:13Z

{TimeWindowStart:yyyy-MM-dd} produces: 2008-03-26 {TimeWindowStart:dd/MMM/yy} produces: 26/Mar/08 {TimeWindowStart:HH:mm:ss} 16:17:13 produces:

Parameter Encoding and Delimiters

Parameters should be placed in a query enclosed by curly brackets. For example:

{symbol}

Three types of parameters are available:

□ Text (the default)

	Date/Time (through the Time Special Parameters)
	Numeric (through selecting a numeric field, or using a Numeric Action Slider)
Ead	ch can be encoded appropriately.
For	text parameters, the full syntax is as follows:
{ []	<pre>parametername]:[delimiter]}</pre>
For	example:
{ s	<pre>ymbol:, }</pre>
	e colon separates the parameter name from the delimiter string. If there is only a single value, then the delimiter is utilized.
For	numeric and Date/Time parameters the full syntax is as follows:
{ []	<pre>parametername]:[display format]}</pre>
For	evample.

For example:

```
{TimeWindowStart:yyyy-MM-dd HH:mm:ss}
{volume:#,##0}
{minresult:#,##0.00}
```

Parameter encoding can be used within:

- data connectors to define a query, subscription, and connection settings
- □ R Transform to define an R script
- Python Transform to define a Python script
- □ the resulting dashboard for visualization titles
- □ Text label controls
- □ Visualizations to define variable titles

Refer to the sections below for more information.

NOTE


The original \$ format of prepending a parameter value with the dollar symbol is still supported for backwards compatibility reasons, but it is more limited in what it can achieve and should be avoided.

Deleting Data Table Parameters

Defined data table parameters can be deleted.

Steps:

1. Hover on a parameter that you want to delete.



2. Click . The parameter is deleted.

RETRIEVING EXTERNAL AGGREGATES (NON ADDITIVE DATA SETS)

In general, Panopticon Real Time processes data that itself can aggregate through standard aggregation methods, including Sum, Min, Max, Mean, and so on. However, there may be occasions when aggregate values cannot be calculated internally but must be retrieved separately.

When working with financial risk data, especially Value at Risk (VaR) the data will be by definition non-additive and cannot be calculated internally within Panopticon Real Time. Therefore, we allow aggregates to be retrieved in addition to the base data set. Configuration of the External aggregate can be supplied explicitly by the user or implicitly from the data plug-in.

An example workbook demonstrating this principle for both static snapshots and Time Series named **How to Non Additive** is included with the product.

An example data format is included below, which first lists the lowest level data, followed by the aggregates. The Column titled *Desk* defines whether the row is aggregate or a leaf value.


Global	Region	Country	Office	Desk	Exposure	10 VaR	1 VaR
Global	North America	USA	Boston	Boston Equity	502.5591	96.93133	34.38913
Global	North America	Canada	Toronto	Toronto Commodities	449.1171	83.44991	26.30474
Global	North America	USA	Chicago	Chicago Commodities	652.1543	76.20758	2.714785
Global	North America	USA	New York	New York FX	517.6406	71.2854	37.26238

Global	Region	Country	Office	Desk	Exposure	10 VaR	1 VaR
Global	North America	USA	Boston	Boston Equity	502.5591	96.93133	34.38913
Global	North America	Canada	Toronto	Toronto Commodities	449.1171	83.44991	26.30474
Global	North America	USA	Los Angeles	Los Angeles Mutual Funds	182.0767	67.68958	11.1428
Global	North America	USA	New York	New York Mutual Funds	812.583	64.44671	40.76365
Global	North America	USA	Los Angeles	Los Angeles Equity	471.5469	39.9832	39.31864
Global	North America	USA	New York	New York Commodities	369.0428	39.51506	46.6825
Global	North America	USA	Chicago	Chicago Fixed Income	459.5511	33.45534	17.68969
Global	North America	USA	New York	New York Fixed Income	701.7921	31.34119	43.45796
Global	North America	USA	New York	New York Equity	810.3085	30.91666	20.31064
Global	North America	USA	Chicago	Chicago FX	77.76167	23.44857	41.05015
Global	North America	USA	Los Angeles	Los Angeles FX	285.2182	22.41497	18.51936
Global	North America	Canada	Toronto	Toronto Equity	909.3673	16.85309	30.22478
Global	North America	USA	Boston	Boston Fixed Income	305.9504	12.37541	3.2304
Global	North America	Canada	Vancouver	Vancouver Commodities	260.9837	10.91653	13.70787
Global	North America	Canada	Toronto		1358.484	75.7861	51.20194
Global	North America	Canada	Vancouver		260.9837	8.24374	8.960773
Global	North America	USA	Boston		1065.943	130.6419	27.43908
Global	North America	USA	Chicago		1601.07	145.2946	67.41181
Global	North America	USA	Los Angeles		938.8418	82.48388	41.31485
Global	North America	USA	New York		3211.367	122.2747	161.8823
Global	North America	Canada			1619.468	99.31398	54.7861
Global	North America	USA			6817.222	518.8613	289.0221

Global	Region	Country	Office	Desk	Exposure	10 VaR	1 VaR
Global	North America	USA	Boston	Boston Equity	502.5591	96.93133	34.38913
Global	North America	Canada	Toronto	Toronto Commodities	449.1171	83.44991	26.30474
Global	North America				8436.69	566.3662	392.1354
Global					20990.08	1626.839	1104.829

To retrieve external aggregates:


- 1. Retrieve your data set including both base data, plus aggregate data.
- 2. On the *Data Table Settings* pane, tap the **Includes Aggregate Data** slider to turn it on and then select the text column that defines the leaf.



3. Enter the Value to determine aggregate rows. The default being blank.



4. Click the **Save** button.



If the leaf or lowest level of data is identified by selecting a specific categorical column, multiple non-additive hierarchies can be supported. In these cases, the aggregates must be supplied, where every column to the left of the selected column, is defined as a potential aggregate.

For example, the following dataset includes the hierarchy:

Global → Region → Country → Office → Asset Class -- > Desk

It includes the base data for each desk, plus aggregates for:

Global → Region → Country → Office → Asset Class

 $\mathsf{Global} \to \mathsf{Region} \to \mathsf{Country} \to \mathsf{Office}$

Global → Region → Country

Global → Region

Global

Additionally, aggregates have been supplied for the different hierarchy:

 $\mathsf{Global} \to \mathsf{Asset} \ \mathsf{Class} \to \mathsf{Region} \to \mathsf{Country} \to \mathsf{Office} \to \mathsf{Desk}$

 $\mathsf{Global} \to \mathsf{Asset}\,\mathsf{Class} \to \mathsf{Region} \to \mathsf{Country} \to \mathsf{Office}$

 $\mathsf{Global} \boldsymbol{\rightarrow} \mathsf{Asset} \, \mathsf{Class} \boldsymbol{\rightarrow} \, \mathsf{Region} \boldsymbol{\rightarrow} \, \mathsf{Country}$

Global → Asset Class → Region

Global → Asset Class

Global	Region	Country	Office	AssetClass	Desk	10 VaR	1 VaR
Global	North America	USA	Boston	Equity	Boston Equity	96.93133048	34.38913175
Global	North America	USA	New York	FX	New York FX	71.28540032	37.26238164
Global	North America	USA	New York	Fixed Income	New York Fixed Income	31.34118784	43.45795678
Global	North America	USA	New York	Equity	New York Equity	30.91665946	20.31063719
Global	North America	Canada	Toronto	Equity	Toronto Equity	16.85309075	30.22477718
Global	North America	USA	Boston	Fixed Income	Boston Fixed Income	12.37540616	3.230399924
Global	North America	USA	Boston	Equity	TOTAL	96.93133048	34.38913175
Global	North America	USA	New York	FX	TOTAL	71.28540032	37.26238164
Global	North America	USA	New York	Fixed Income	TOTAL	31.34118784	43.45795678
Global	North America	USA	New York	Equity	TOTAL	30.91665946	20.31063719
Global	North America	Canada	Toronto	Equity	TOTAL	16.85309075	30.22477718
Global	North America	USA	Boston	Fixed Income	TOTAL	12.37540616	3.230399924
Global	North America	Canada	Toronto	TOTAL	TOTAL	75.78610302	51.2019375
Global	North America	USA	Boston	TOTAL	TOTAL	130.6419004	27.43907688
Global	North America	USA	New York	TOTAL	TOTAL	122.2746767	161.882264
Global	North America	Canada	TOTAL	TOTAL	TOTAL	99.31398318	54.78609529

Global	Region	Country	Office	AssetClass	Desk	10 VaR	1 VaR
Global	North America	USA	Boston	Equity	Boston Equity	96.93133048	34.38913175
Global	North America	USA	New York	FX	New York FX	71.28540032	37.26238164
Global	North America	USA	TOTAL	TOTAL	TOTAL	518.8613204	289.0221365
Global	North America	TOTAL	TOTAL	TOTAL	TOTAL	566.366159	392.1354295
Global	TOTAL	TOTAL	TOTAL	TOTAL	TOTAL	1626.839172	1104.828695
Global	TOTAL	TOTAL	TOTAL	Equity	TOTAL	606.4144769	329.4784359
Global	TOTAL	TOTAL	TOTAL	Fixed Income	TOTAL	451.081016	178.6103631
Global	North America	TOTAL	TOTAL	Equity	TOTAL	192.2519763	122.2667907
Global	North America	TOTAL	TOTAL	Fixed Income	TOTAL	65.59614378	54.72134119
Global	North America	TOTAL	TOTAL	FX	TOTAL	99.57659408	82.30710941
Global	North America	USA	TOTAL	Equity	TOTAL	188.3931344	102.2566554
Global	North America	Canada	TOTAL	Equity	TOTAL	15.16778167	27.20229946
Global	North America	USA	TOTAL	FX	TOTAL	105.4340408	87.14870408

Calculations with External Aggregates (Non Additive Calculations)

Calculations are built from the underlying data fields within the dataset. For additive datasets, aggregates of calculated fields are either based on:


- □ A defined aggregation method, using the leaf calculation, and aggregating this up the hierarchy.
- The Calculate aggregation method, using the sum of each term in the formula, up the hierarchy.

In the case of external aggregates, and applying the Calculation aggregation method, calculations will use the external aggregate values for each term within the formula, when calculating up the hierarchy.

MANAGING DATA SOURCES


A data table can consist of one or more data sources and can be connected to directly, with data retrieved on the fly as it is required.

Click on a data source on the *Data Sources* pane. The currently selected data source is highlighted (grey background) and the settings are displayed.




Connector Settings

Sample 1



Sample 1 (Text Data – Manual Text) displays the text values and the properties of the generated columns based on the set properties (i.e., Skip First n Rows, Data Type Discovery, Text Qualifier, and Column Delimiter)

Sample 2




This lists options specific to the data source. In the case above for Sample 2 (MS Excel (legacy)), it lists the file path to the Excel workbook, and the sheet to be used.

In the Connector Settings pane, the amount of data to be returned can also be specified.

For more information on the data source specific settings, refer to <u>Data Connectors</u> for more information.

Transform Settings

Clicking the **Transforms Settings** button displays the transform settings of the currently selected data source.




The *Transform Settings* allow for:

- <u>Pivoting</u> retrieved data
- <u>Unpivoting</u> retrieved data
- Transforming data to enable time series analysis including interpolation
- Running an R or Python script for data transformation
- Running a <u>REST Transform</u>
- Lists of orders to be reconstructed into an Order book and conflated for output display

Columns Settings

Clicking the Columns button displays the retrieved columns from the data source.



The Column Settings allows you to:

- modify the column data type
- rename column names
- select the <u>numeric</u> or <u>Date/Time</u> format
- select the numeric default aggregation
- define <u>custom sort order</u>

COMMON DATA SOURCE SETTINGS

Most of the data sources share the following
--


- Data Connector File Source
- Load Type for a File Source
- Message Type selection and definition
- □ Saving and loading of column definitions
- Time zone definition
- Row Limits definition

Selecting and Defining the Data Connector File Source

Several connectors including <u>JSON</u>, <u>SVG</u>, <u>Text</u>, <u>XML</u>, and <u>Streams Simulator</u>, allow selection from a File, Web URL, or Text source.



For the MS Excel (legacy) connector, you can select from a File or Web URL source.



Steps:

Select the connector file source:

□ File


You can either:

Upload a data source snapshot by clicking Upload File browse to the file source.





After selecting the file, it is displayed with the timestamp of the snapshot.



The data source is placed in the repository and locked, synchronized, and bundled with the workbook version


To change the data source, click then **Browse** to browse to a new version of the file, which is uploaded into the repository, and create a new version of the workbook that reads it.

• Link to a data source file by clicking **Link to File** and entering a *File Path*.


The supported file types for the connector are displayed as guide (e.g., for the Text connector they are .CSV, .TXT, and .TSV).


Load Type	Upload File	Link To File	
Text File Path			(File Type: .csv,.txt,.tsv)

Ensure that in a cluster, you need to use a shared path, or put it on every node and use a path that resolves on every node. You can update its contents whenever you want.




Text
 Then enter the text block to be parsed.






□ Web URL


The dialog changes to allow specification of the following:



Property	Description
Authentication Type	 Basic Basic authentication. OAuth



- Token URL The URL to retrieve the access token from.
- Token Request Body The request body used for access token requests.
- Add Access Token To The Access token retrieved from the Token URL can be added to headers, URL or request body, depending on how the endpoint needs the token.



- Request Headers A header is automatically added to the REST API request.
- Request URL The URL needs to be manually parameterised with a {access_token} parameter, before calling the REST API, the parameter is replaced with the actual token.
- Request Body The Request Body needs to be manually parameterised with a {access_token} parameter, before calling the REST API, the parameter is replaced with the actual token.

NOTES:

- The given request body is posted to the Token URL as application/x-www-form-urlencoded, so the request body must be formatted like field1=value1&field2=value2, e.g., client_id=xxxx&client_secret=xxxx&grant_type=client_credentials.
- Not available in the Streams Simulator connector.
- If you have a pre-generated API token for the service you connect to and want to
 use the Bearer Authentication (Token Authentication), select the Authentication
 Type Basic, and manually type into the Headers field:

Authorization="Bearer xxxxyz_some_secret_token"

Leave the *User Id* and *Password* fields blank.


The API token in the *Headers* field can be a Panopticon parameter reference, and the API token can be saved as a global server parameter.

Path The absolute path including the HTTP where the file is located.

Proxy Server URI The HTTP Proxy setting that will allow the connector to reach the endpoint.

Headers are separated by a comma


	 Each Header is entered as Name = Value, where Name and Value can be enclosed in double quotes to allow inclusion of any character except for double quotes Name and Value can also be left unquoted, in which case they may not include 				
	comma or equals characters				
Content Encoding	Select the <i>Content Encoding</i> with the HTTP Header: None, GZip, Deflate, or GZip and Deflate				
User Id	The user ld that will be used to connect to the connector's service.				
Password	The password to connect to the connector's service.				
	Check the Show Characters box to display the entered characters.				
HTTP Method	Select the appropriate HTTP method for the request from the following options: GET OST PUT DELETE GET - retrieve data POST - add new data PUT - replace existing data DELETE - remove existing data				
Timeout	The length of time to wait for the server response (10 to 300). Default is 10 .				
Request Body	The Request Body for the HTTP POST.				
Content Type	The required Content Type. Default is application/x-www-form-urlencoded.				
Record Path	The record path that will be queried by the connector's path (e.g., myroot.items.item).				




Defining the Message Type in Data Sources

Message types specify the format of the data within the message.


Steps:





2. Define or set the columns that represent the sections of the message.

Property	Description
Name	The column name of the source schema.
Fix Tag/JsonPath/Text Column Index/XPath	The Fix Tag/JsonPath/Text Column Index/XPath of the source schema.
Туре	The data type of the column. Can be a Text, Numeric, or Time
Date Format	The format when the data type is Time .
Enabled	Determines whether the message field should be processed.




Defining the Format in Data Sources

You can select the format to use in the connector for Azure, Google Cloud, and S3 data sources.


Steps:

1. Select the Data Type:




JSON

If **JSON** is selected, enter the *Record Path* which allows the identification of multiple records within the JSON document (e.g., **myroot.items.item**).



Text If Text is selected, confirm the Decimal Separator, Text Qualifier, Column Delimiter, and if the first row of the message includes column headings. Text Data Type **Decimal Separator** Period {.} Text Qualifier <none> Column Delimiter Comma {,} First Row Headings Column Index controls the position of a column, Must be >= 0. **Generate Columns** Save Load Name Column Index Type **Date Format** 🗸 Enabled 🕂 🗕 **XML** If XML is selected, enter the Record Path which allows the identification of multiple records within the XML document (e.g., //myroot/items/item) . Xml Data Type (eg. //myroot/items/item) Record XPath Period {.} **Decimal Separator** Prepend 'default:' for the elements falling under default namespace. Generate Columns Save Load Name Enabled + -**XPath** Type **Date Format** Excel For **Excel** file type, select the required sheet and adjust the headers on first row, if needed. Excel Data Type



2. Define or set the columns that represent the sections of the file.

3. Property	Description
Name	The column name of the source schema.
JsonPath/Column Index/XPath	The JsonPath/Column Index/XPath of the source schema.
Туре	The data type of the column. Can be a Text, Numeric , or Time
Date Format	The <u>format</u> when the data type is Time .
Enabled	Determines whether the message field should be processed.


NOTE	To parse and format times with higher than millisecond precision, the format string needs to end with a period followed by sequence of uppercase S. There can be no additional characters following them. For example: yyyy-MM-dd HH:mm:ss.SSSSS				
o delete a column, check its or all the column entries, check the topmost , then click .					

Saving or Loading Column Definitions in the Data Sources


Save or load column definitions in the data sources.

Steps:

- 1. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the **Save** button is enabled.
- 2. Click Save to save a copy of a column definitions file (.exs).
- Instead of generating columns done in step 1, click to load column definitions (.exs) file.
 The Load Column Definitions dialog displays.




- 3.1. To load column definitions, you can either:
 - drag it from your desktop and drop in the dialog, or
 - click Choose Column Definitions File to Load and select one in the Open dialog that displays.
 The name of the column definitions is displayed on the loaded column definitions area.



3.2. Click Ok


A notification displays when the file is loaded.



This populates the list of columns from the .exs file.


Setting Show in Timezone and Source Timezone of Data Sources

Date/Time values of output data and Date/Time inputs in the data source, where supported, is by default unchanged. For example, in the JSON data source:



Steps:


1. To present the outputs in another time zone, select the desired time zone from the *Show in Timezone* drop-down list box.



In this case, the Date/Time values in the data source is assumed to be in **UTC**. Therefore, for the output data, values are converted from **UTC** to the selected time zone. And inputs (if any) are converted back to **UTC**.

Use the Search box to search for the preferred time zone.

2. This enables the *Source Timezone* drop-down list. Select a new one if the Date/Time values in the data source are not in **UTC**.



In this case, the Date/Time values for the output data are converted from the selected *Source Timezone* to the selected *Show in Timezone*, and inputs (if any) are converted to the selected *Source Timezone*.

3. Click the **Save** button.

Setting Row Limit of Data Sources


When working with large data sets, you can set the row limit for the amount of reads or loads from the data source.

Steps:


1. Click on a data source on the *Data Sources* panel. The currently selected data source is highlighted (grey background).

The corresponding Data Source Settings pane is displayed.


For an MS Excel (legacy) data source, this will display:



2. Click **Row Limits** to expand and display the properties you can set.



3. Click the Data Set Row Limit drop-down and select the value. The range of value is from 100 to No Limit.



NOTE Data Set Row Limit can be parameterized.

4. In the When Data Set Exceeds Limit drop-down, you can select either:



Prevent Data Loading

For example, there are 1000 rows of data, if you set the row limit to 100, no data will be loaded:

To load data, ensure that the row limit is greater than the data set.

Truncate Data Set

This is an efficient method of deleting data (i.e., rows in a table) beyond the data row set limit. For example, if there are 1000 rows of data, if you set the row limit to 100, only 100 rows of data will be loaded. The remaining or the rest of the records/rows in the data set will be truncated.

5. Click the Save



button.

JOINING MULTIPLE DATA SOURCES IN WORKBOOK DATA TABLE EDITOR

There are occasions where the desired data is not achieved or available using a single query and table. This is often the case with time series where you want to join a static data set to a time series database.

To join multiple tables, add the source tables in the *Workbook Data Table Editor* view and join them using a common field or a join key. Furthermore, you can also perform a transform of a table for time series analysis, if required.

NOTE

- Joining two data sources can be done using more than one left and right key columns is now supported.
- It is no longer needed to modify the data types to text to join data sources.

In this section, we will discuss how to join the following sample tables using two common fields.

Sample Table 1

Item	isodatetime	ask_price	ask_volume	bid_price	bid_volume
Price	2008/01/17 13:00:00	17.75	2	17.65	1
Rate	2008/01/17 13:00:01	17.70	2	17.64	1
Price	2008/01/17 13:00:00	17.74	1	17.61	1

Sample fields

Sample Table 2

TradeID	RatePrice	ISODateTime	trade_price	trade_volume	Side	AggressivePassiveDark
1	Price	2008/01/17 13:00:00	17.79	200	Buy	Aggressive
2	Rate	2008/01/17 13:00:02	17.65	100	Sell	Dark
3	Price	2008/01/17 13:00:04	17.72	100	Buy	Dark
4	Price	2008/01/17 13:00:06	17.71	200	Sell	Passive

Sample fields


Steps:

1. On the Data Sources Settings pane, add a new data source by clicking the Add Data Source




button.

The list File/URL data sources is displayed on the Connectors pane.




2. Select a data sources tab then select a data source.

When there are two or more data sources on the *Data Sources* pane, the **Join** icon is displayed.



3. To join the data sources, click the **Join** icon.

The icon changes to and the *Join Settings* pane displays.



4. Select the join Type:



Left Outer Join

Keeps all rows from the left table. When there are no matching values from the right table, empty values will be returned.



Right Outer Join

Keeps all rows from the right table. When there are no matching values from the left table, empty values will be returned.



Full Outer Join

Returns all rows from both tables, whether they have a matching row or not.



Inner Join


Selects only rows from both tables for which the join keys match.




Cross Join

Returns the Cartesian product of rows from tables in the join.

5. Click + Join Key




- Select the unique ID from the Left Column data source from the drop-down list that will be used to match the unique ID from the Right Column data source (e.g., Item).
- 7. Select the unique ID from the Right data source from the drop-down list (e.g., RatePrice).




8. Click Refresh Preview then click to expand the Data Preview pane.

The selected join type is displayed in the *Join* definition box and the data table of the joined data sources is loaded on the *Data Sources Preview* area.


• For the Left Outer Join, the joined table now displays seven rows based on the Item join key of the left table.




• For the *Right Outer Join*, the joined table now displays seven rows based on the **RatePrice** join key of the right table.



• For the *Full Outer Join*, the joined table now displays all rows that are matching or not matching based on the **Item/RatePrice** join keys of both tables.




 For the Inner Join, the joined table now displays seven rows based on the Item/RatePrice join keys of both tables.




• For the *Cross Join*, the joined table now displays twelve rows based on the combination of each row from the first table with each row from the second table.

Note that Join Keys definition is not available.



9. Now, let us add new left and right join keys. Click on the *Join Settings* pane.

A new *Left Column* and *Right Column* entry displays.




- 10. Select the left and right join keys (e.g., **isodatetime** and **ISODateTime**)
- 11. Again, select the join Type.
- 12. Click Refresh Preview

The selected join type is displayed in the *Join* definition box and the data table of the joined data sources is loaded on the *Data Sources Preview* area.


• For the Left Outer Join, the joined table now displays three rows based on the Item and **isodatetime** join keys of the left table.

All of the rows from the left table are kept. Note that for the rows with no matching values from the right table, empty values are returned.




For the Right Other Join, the joined table now displays four rows based on the RatePrice and ISODateTime
join keys of the right table.


All of the rows from the right table are kept. Note that for the rows with no matching values from the left table, empty values are returned.



For the Full Outer Join, the joined table now displays six rows from both tables. The first row is based on the Item/RatePrice and isodatetime/ISODateTime join keys of both tables while the next five rows are those that did not match the join keys.




 For the Inner Join, the joined table now displays one row based on the Item/RatePrice and isodatetime/ISODateTime join keys of both tables.



• For the *Cross Join*, the joined table now displays twelve rows based on the combination of each row from the first table with each row from the second table.

Note that Join Keys definition is not available.



- 13. To delete left and right join keys in the *Join Settings* pane, click
- 14. Click Save to save the join. Once saved, a notification message displays.




NOTE

If there is an error in the join definition, the Join icon or Left/Right Column drop-down is marked with a red border. Consequently, the preview is not displayed.

For example, if the join keys have different data types, an error message is displayed:


"A panopticon.developer.tables.standalone.TextColumn column from the left table in the join is not compatible with a panopticon.developer.tables.standalone.NumericColumn column in the right."




Modifying the Join Definition

Steps:

1. Click the **Join** button.



The Join Settings pane displays with the join definition.



- Modify the join type or select another unique ID from the right or left data source or add new left and right join keys.
- 3. Click Refresh Preview

The selected join type or union all is displayed in the *Join* or *Union All* definition box and the data table of the joined or combined data sources is loaded on the *Data Sources Preview* area.

UNION ALL OF MULTIPLE DATA SOURCES

There are occasions where the source data is held across multiple disparate repositories so that the rows of the data set are distributed. In this case, instead of doing a Join, perform a Union All.


Common use cases for union all include:

- □ Performance data to its benchmark.
- Historical data from a database to current streaming data from a message bus.


Union All is done based on column position and requires data type match between data sources.

Steps:

To join the data sources, click the **Join** buttor




The Join Settings pane displays.



2. Select Union All then click Refresh Preview

The result of the union all is displayed in the Data Source Preview.




3. Click . Once saved, a notification displays.




GROUPING AND SORTING COLUMNS


Below is an example of an MS Excel data source with text, numeric, and Date/Time data types.



By default, when displayed on the preview area of the *Data Table Editor* view, the columns are sorted alphabetically and grouped by data type.



To display the columns based on how they are displayed on the data source, click Original.




CREATING A CUSTOM SORT ORDER

For this sample data:

Month	Weekday	Date	MonthNo	WeekdayNo
January	Monday	01/01/2021	1.00	1.00
February	Tuesday		2.00	2.00
March	Wednesday		3. 00	3.00
April	Thursday		4. 00	4.00
May	Friday		5. 00	5.00
June	Saturday		6. 00	6.00
July	Sunday		7. 00	7.00
August	Monday		8. 00	1.00
September	Tuesday		9. 00	2.00
October	Wednesday		10. 00	3.00
November	Thursday		11. 00	4.00
December	Friday		12. 00	5.00

When used in a visualization or filters, will be displayed as:



On the *Columns* pane in the *Data Table Editor* layout, you can create the custom sort order of the dimensions or text columns of the selected data source. Consequently, this allows the dimensions to be displayed in a <u>visualization</u> and <u>filter</u> in the correct or desired order.


Steps:

1. Click the Columns button.

The Columns pane is displayed.

2. Enter the order of the values (separated by a comma) of the dimensions or text columns under the *Custom Sort Order* section.





4. Click . Once saved, a notification displays.



Using the data with custom sort order, the visualization and filters will now be displayed as:




ENABLE TIME SERIES ANALYSIS

Panopticon supports a number of data visualizations that are useful for monitoring and analyzing time series data, including the Line Graph, Needle Graph, Stack Graph, Horizon Graph, and OHLC/Candle Stick visualizations.

All non-time series visualizations will display a selected time slice (the **Snapshot**) of a time series dataset, unless displaying time window calculations.

Your source data must be transformed in order to use time series visualization. The transform converts the dataset into a cube, where the Z axis of the cube represents time, providing a set of time slices to play through and calculate across.



When there is a time slice, but not a value determined by the selected dimensions, the value will be set to null, and in the case of a line graph, a gap in the line will be drawn.

The time slices of the output time series can be identical to the input dataset, or as typically the case with sensor data will be standardized by barring (conflating) into an appropriate granularity for display.


A source table to be used for time series must have the following properties:

A unique key or set of keys forming a compound key for each data series. For example, you can use the Stock Symbol as the unique ID in a set of Stock Market data.


- □ A Date/Time stamp of data type Date Time
- □ A series of numeric or text fields providing values for each unique ID for each available Date/Time stamp.

Steps:


- 1. Click on a data source on the *Data Sources* pane. The currently selected data source is highlighted (grey background). The corresponding *Data Source Settings* pane displays.
- 2. Click the **Transform Settings** button. The *Transform Settings* pane displays.



3. Tap the **Transform to enable Time Series analysis** slider to turn it on.



The checkboxes for one time series per data row, or close and time series with time slices that don't align, ensure that duplicate values are highlighted, and the time cube volume is minimized.



4. Click **Fetch Schema** to update columns available for time series transform.

Check columns which define comparable items over time

Ticker

Select the key or compound key columns from the source list of dimensions to define comparable items over time.

Check columns which define comparable items over time



These define each series and correspond to the rows of the generated time cube.

6. Select the column to define the time axis values (Date/Time stamp).

Default value is Date.

To define the time axis values, Use Date ▼

7. Set the Date/Time range of the column set in step 5 in the From and To text boxes.

This filters the time series visualization data causing less data to go over the network to the Web client.

NOTE

The range is not calculated from the start and end values but rather from the Max (the start or the first time slice of the dataset) to Min (the end or the last time slice of the dataset) range. For example, the start and end values can be from **2000-01-01** to **2020-01-01** but the conflation still works as it takes the Date/Time range of the supplied time series.

8. Choose whether you want to **Conflate** the dataset by setting the **Barring** period to **Auto**, or a defined value, between **Year** and **Nanosecond**.



Setting the barring period conflates the dataset to a defined granularity, returning a set number of data points, by default being between **50** and **1000** for **Auto**.



As data is potentially being aggregated across time, an <u>Aggregate</u> must be selected. The default conflation aggregate is <u>Mean</u>. Other options include: <u>Sum, Min, Max, First, Last</u> and <u>Count</u>.



Barring can be useful to standardize sparse time series, which is especially common with sensor data, outputting values at defined time intervals, and potentially minimizing the number of rendered data points.

The available barring periods besides **Auto** are:

Year, Half Year, Quarter Year, Month, Day, Two Hours, Hour, Half Hour, Quarter Hour, Ten Minutes, Five Minutes, Minute, Half Minute, Quarter Minute, Ten Seconds, Second, Half Second, Quarter Second, Tenth Second, Fifty Milliseconds, Ten Milliseconds, Five Milliseconds, Milliseconds, Fifty Microseconds, Ten


Microseconds, Five Microseconds, Microsecond, Fifty Nanoseconds, Ten Nanoseconds, Five Nanoseconds, Nanosecond.

However, when the barring period is set to None, you can enable Add Auto Identifier Column: Sequence ID.




This means that when multiple values are processed at the same time along with selected dimensions, the seqid will be added to each unique occurrence per time slice and defined dimensions, incrementing starting from 1.

9. Choose whether you want to interpolate for missing values.



The interpolation can replace missing numeric values with **Zero**, the **Previous Value**, or an **interpolation between known values (Interpolated)**.

- 10. Click Refresh Preview
- 11. Click then to save the data table and exit the Data Table Editor layout. On the Open Workbook in Design Mode, a time series data table is visually identified by the time series curve to the left of any numeric time series fields.



PIVOTING AND UNPIVOTING DATA

Data comes in two major formats: **long**, where the columns can't be reduced and has many rows vs **wide**, where the columns can't be reduced, and fewer rows are needed.

wide					long					
	m	m	f	f		2010	de	m	Α	
	de	en	de	en		2010	de	m	В	
2010	5	5	1	12	Pivot	2010	de	f	Α	
2010	43	6	5	2		2010	de	f	В	
2011	3	0	34	3		2010	en	m	А	
2011	2	4	65	3	Unpivot	2010	en	m	В	
						2010	en	f	А	:
						2010	en	f	В	
						2011	de	m	А	
						2011	de	m	В	
						2011	de	f	А	3
						2011	de	f	В	6
						2011	en	m	А	
						2011	en	m	В	
						2011	en	f	Α	

Data can be transformed from long to wide or back again. However, the term pivot and unpivot are sometimes used for either transformation. In Panopticon, we define **pivot** as a movement from long data to wide data and **unpivot** as a movement from wide data to long data.

2011

The use of either pivoting or unpivoting data is based on the ease of calculation or to more easily join the data together.



Panopticon's pivoting has special requirements due to the real-time aspect of the product.

Pivoting

Pivoting in Panopticon is **always with respect to time**. Panopticon finds the first date or Date/Time column from left to right in the dataset and uses that. As an example, in the table below, if you want the Date 2 column to be the one used, transform the data so it will be the first date column in the dataset.

Date	Letter	Value	Date 2
10/1/2015	Α	1	1/1/2017
10/1/2015	Α	2	1/29/2017
10/29/2015	Α	3	2/26/2017
11/26/2015	В	4	3/26/2017
11/26/2015	В	5	4/23/2017
12/24/2015	В	6	5/21/2017
1/21/2016	С	7	6/18/2017
2/18/2016	D	8	7/16/2017
3/17/2016	E	9	8/13/2017
4/14/2016	F	10	9/10/2017
5/12/2016	F	11	10/8/2017
6/9/2016	G	12	11/5/2017

Pivoting in Panopticon is about taking the row values in category and turning them into columns by some operation like:

Count
Last
Min
Max
None
Sum (default

Mean or median are not used since it is about real time response in Panopticon, and these functions are expensive to calculate. For static data, if you need to pre-calculate those types of transformations, you can use a table visual to determine the value. However, for real-time data and real-time response, the functions Count, Last, Min, Max, and Sum are exactly what you need.

Multiple pivot columns can be defined.

Either different:

Measure ColumnsValue ColumnsAggregates


When this occurs, the resulting pivoted column names will be prepended as appropriate to ensure that each column is uniquely identified.



In cases where some columns cannot be aggregated after pivoting, it is recommended to select the None aggregate. For more information, refer to $\underline{\mathsf{Example}\ 4}.$

Example 1

A common format for database sourced data is key value pairs. As an example, below; price changes are listed as key value pairs for a set of symbols.



When retrieved, the data table preview displays the same key value pair layout.



Steps:

1. To pivot the data, click the **Transform Settings** button on the *Data Sources Setting* pane.

The Transform Settings pane displays.

2. Tap the Pivot slider to turn it on.

The **Transform Settings** button and **Pivot** tab change to respectively.

- 3. Click + Pivot
- 4. Select the Measure Column. This is the column that will be pivoted.
- 5. Select the Value Column.
- 6. For the Measure Values, you can either:
 - enter the possible values of the selected *Measure Column*, or
 - click Populate Measure Values button to populate the text box.




These values will become the output columns of the pivot data transform.

- 7. Select the Aggregate method for the value column.
- 8. Click Refresh Preview

For example:

Measure Column = Item
Value Column = Value
Measure Values = Close(local), Mcap(Local)
Aggregate= Sum


All columns that are not the Measure or Value columns will be removed from the output data structure.



The preview is updated to show the pivoted layout, which in the case below now shows each change as a separate data column. These pivoted results are additionally available as input into calculated columns.



Example 2



For the sample above, the *Measure* column is the one you want to pivot. In this case, you will need to pivot to create a unique **Sum** per date and measure.

The column named *Category* will be used as the Measure (pivot) column, and value column (*Value*) is the one you will aggregate.

Click the **Populate Measure Values** button to populate the *Measure Values* box that you can aggregate (i.e., **A**, **B**, **C**, **D**, **E**, **F**, **G**). The default **Sum a**ggregation is applied.




Clicking Refresh Preview transforms the data and is displayed on the Data Sources Preview.


The expected pivot is achieved as there is only one row per unique date, and the *Letter* and values columns are summed up.



The original dataset had 12 rows, now it is reduced to 10 because the original dataset had the following rows:




And they have been pivoted by **Sum** to the values in the first and third rows.




Example 3


In the example above, you populated the *Measure Values* box with **A**, **B**, **C**, **D**, **E**, **F**, **G**. If you skip a value such as **A**, the transformed data will display as:



In the original dataset, the three rows with the A value had the dates 10/1/2015 12:00:00 AM and 10/29/2015 12:00:00 AM:




Not including the **A** value in the pivot still displayed the dates but did not include the **A** data since in Panopticon, pivoting is always with respect to time.



Example 4

When applying a pivot transform, you can select Sum, Min, Max, Count, or Last aggregation method.


However, when there are two or more non-unique combinations of values in the columns that are not specified as *Measure* or *Value* columns, they may not be aggregated.




For the sample above, the *Measure* column is the one you want to pivot. In this case, you will pivot to create a unique **Sum** per *v* and measure.

The column named id will be used as the Measure (pivot) column, and value column (v) is the one you will aggregate.


Click the **Populate Measure values** button to populate the *Measure Values* box that you can aggregate (i.e., **A**, **B**, **C**). The default **Sum** aggregation is applied.




Clicking Refresh Preview transforms the data and is displayed on the Data Sources Preview.




Note that the *n* column is not aggregated after pivoting. To fix this, set the *Aggregate* to **None**.




After clicking Refresh Preview, the expected pivot is achieved and there is no aggregate applied to all of the columns.



Pivoting and Time Series




<u>Enabling the time series analysis</u> when you perform a transform solves the problem of having to specify all of the values. It also allows you to choose which Date/Time column should be used to specify the time series.



Unpivoting

A common alternative format for time series data sets is as follows:



Where the first column represents the Date/Time, and subsequent columns represent the same variable such as Price for a given item. In the MS Excel screen shot above, the price history for a series of stocks is displayed.

By default, this format cannot be used within Panopticon, as it expects each item to occur on a different row, with each variable (such as Price) occupying a single column.

The format is in fact a pivoted version of the format that Panopticon requires.

In general, when unpivoting, individual columns are being converted into additional rows with only two columns, by default named **Measure** and **Value**.

Steps:


1. To unpivot the data, click the **Transform Settings** button on the *Data Sources Setting* pane.

The *Transform Settings* pane displays.

Unpivot


2. Click

The Transform Settings pane changes to display the Unpivot Settings.



3. Tap the Unpivot slider.

The **Transform Settings** button and **Unpivot** tab change to respectively and all of the columns are moved to the *Unpivot* box.




You may opt to move fields from the Columns to Unpivot box, or vice versa, using the following buttons:

- move all fields from the Columns to Unpivot box

- move all fields from the *Unpivot* to *Columns* box
- click after selecting one or more fields from the Columns box to move to the Unpivot box
- click after selecting one or more fields from the *Unpivot* box to move to the *Columns* box

You can also filter the list of columns by entering a text in the Search Columns search box.



4. Give appropriate names to the Measure and Value columns.

For example:

```
Measure Column = Return Type
Value Column = Return Value
```

- 5. Define the display formats for numeric fields. The default setting is: #,##0.00
- 6. Refer to Enable Time Series Analysis for more information in enabling this feature.

Enabling the time series analysis when you perform an unpivot solves the problem of having to specify all of the values. It also allows you to choose which Time column should be used to specify the time series.

7. Click 3 Refresh Preview

R TRANSFORM

An R script can be executed as a data transformation step in the data pipeline. Specifically:

- Data is retrieved from an underlying source.
- ☐ The returned data table is translated into an R data frame.
- ☐ The R data frame and supplied R Script are passed to an external R process running Rserve.
- ☐ The external Rserve process returns a resulting R data frame.
- □ The returned data frame is translated into a Panopticon table for visualization rendering.

For this to occur, both R and Rserve must be installed, and initialized.

NOTE


 When used with streaming data sources (e.g., message bus), the Real Time Limit of a streaming data source should be set to a value longer than the time taken to perform the R data transform.

For example, if the transform operation takes 2 seconds, the Real Time Limit should be set to **2500** milliseconds.

 When used for non-streaming data sources (e.g., Database), the data table Auto Refresh period should be set to a value longer than the time taken to perform the R data transform.

For example, if the transform operation takes 2 seconds, the data table *Auto Refresh* period should be set to **3** seconds.

When the **R** button is selected, the *Transform Settings* pane changes to show:



Steps:

1. Tap the Enable R Transform slider to turn it on.

The **Transform Settings** button and **R** tab change to Transform settings and Transform settings, respectively. The default *Address* (i.e., **localhost**) and *Port* (i.e., **6311**) fields are displayed.

2. Specify the Username and Password if authentication is enabled on the Rserve process.

NOTE	The Address, Port, Username, and Password fields will be hidden if their corresponding properties are set in the Panopticon.properties file.		
	Field	Corresponding Property in Panopticon.properies	
	Address	connector.rserve.host	
	Port	connector.rserve.port	
	Username	connector.rserve.userid	
	Password	connector.rserve.password	

- 3. The Frame Name that Panopticon will produce, and then be utilized by the R scripts should be specified. Default is df.
- 4. Specify whether to Enclose Parameters in Quotes.
- 5. Enter the *R Script*. This R script should reference the input frame name and return a data frame. Just like an underlying SQL query, the R Script itself can be parameterized.

This step will work for small and simple use cases. However, when you have several transforms, or when each transform is applied to several data tables, it is highly recommended to follow the instructions in the Best Practices on Working with R Transform in Panopticon section.

6. On the *Input Schema/Sample Data* section, the column names of the input data source are displayed. In cases where there are no rows from the input data source and the R script is not handling zero rows, you can add sample data to ensure transform is applied.

To add or manage the sample data, you can use the following icons:

Icon	Description
+	Add sample data for the input column names.
-	Check a box of a sample data row and click to delete or check the topmost box and click to delete all of the sample data rows.

7. Click Test Script

If successful, the output schema is displayed.

Otherwise, a notification is displayed with the cause of the error. Update the script.

8. Select the *Date-time class* that will be applied to the transform:

- Date is the simplest data type to use for calendar dates. It is stored as integers and is represented as the number of days since 1970-01-01, with negative values for earlier dates.
- chron that can be used for chronological objects which can handle dates and times.
- POSIXct is built-in POSIXt date-time data type with ct that stands for calendar time. It stores the number of seconds since the origin.
- 9. The *Timeout* is set to **10** seconds by default to ensure that slow running R scripts do not impact other areas of the product. You can opt to enter a new value.
- 10. Click Refresh Preview to see the output columns from the R transform.
- 11. Refer to Enable Time Series Analysis for more information in enabling this feature.

Best Practices on Working with R Transform in Panopticon

When applying a transform with R in Panopticon for small and simple cases, you have the option of typing or pasting the code directly into the *Transforms* window. However, when you have several different transforms, or when each transform is applied in several data tables, it is highly recommended to follow the steps outlined below on how to apply functional programming and the D.R.Y. principle (Don't Repeat Yourself) to the R transforms in Panopticon.

Steps:

- 1. Save your code in R-files for R. This option gives you the freedom to work on the code in RStudio.
- 2. Instead of using an imperative coding approach, define one or several functions in the file, which when invoked, runs your code, takes a data frame as an input argument, and then returns the resulting data frame.
- 3. In the *Transforms* window of Panopticon, reference this external code file at the very top:

```
source("path/to/your/folder/your R file.R")
```

You can then invoke (call) any function that you have defined in your code file with a function call in the transform code window. Ideally, the function will return the transformed data frame.

4. The path to the external code file needs to be valid both from the point of view of Panopticon Designer on your local workstation, and from the point of view of Panopticon Real Time you publish to. This can be assured by introducing a global parameter in the Real Time under the **Parameters** tab.

For example, you can name the parameter **R_code_path** and define its value as the full path to the folder that contains your code files. Next, on Panopticon Real Time, define a global parameter with the same name, but with a value that is the path to the server-side folder containing your code files. Copy the code files to the server-side folder then edit the path specified in your sourcing call in the transform so that it contains the parameter. For example:

```
source(file.path("{R code path}", "your R file.R"))
```

This will achieve a path reference to your code file which is valid in both the Designer and Server. It is also useful when promoting or migrating a Panopticon workbook from one server environment to another.

NOTE

- If there is a need to apply different transforms to different data sets, you can solve this by defining several different functions in your code file.
- For very similar functions, avoid repeating the same code in a file by factoring out the common parts and placing them in a separate function, which can be invoked by the other functions.
- For a transform that needs to have different outputs based on certain conditions or variables, this can be controlled by adding another input parameter to the function. Depending on the argument given to that parameter, you can make the function do things differently by evaluating a condition. In addition, this argument can – if you want to – be supplied via a Panopticon parameter and thereby be put under a dashboard enduser control.

Example code in R

File: my_transform_code.R

```
# minimal example function
add_one = function(df, colname) {
    df[colname] = df[colname]+1
    return(df)
}
```

Panopticon R transform window code:

```
source(file.path("{my_R_code_path}","my_transform_code.R"))
# data set is loaded in dataframe named 'my_data_frame'
add_one(df = my_data_frame, colname = "my_column_name")
# the function returns a data frame
# which is picked up by Panopticon
```

Additional Best Practice Recommendations in Using R with Panopticon

With an <u>R transform</u> or the <u>Rserve</u> connector in Panopticon, it is fairly quick and easy to enter some short code snippet and use the result. However, as a project grows, and if a solution is moved into production and becomes business critical, you need more structure in your use of R and Rserve with Panopticon:

- Code should be made into functions, even if used only in one place and even if the code content is very brief. Thereby, the operations performed by each function will be contained and you avoid the risk of naming conflicts and contamination in the global environment.
- Ensure you handle exceptions in the code you write. For example, when applying an R transform to data, you can do an initial check in your code to see if the dataset is either zero-row or has any rows. In which case, you want to terminate and just return the empty dataset. You should also use tryCatch clauses, whereby in the event of an error or a warning, you could, for example, insert the error/warning message into the designated column in your dataset and then return it to Panopticon. If there is no error, the same column could contain a plain "OK" or similar as an indicator of a no-errors result.
- Functions should ideally be turned into a package. The benefit of that is mainly about the possibility of adding unit testing and automating dependency package imports.

	Your package should have unit tests that are run when building the package.			
	Your package should import any other packages that you have a dependency on.			
	Developing, Testing and Debugging the package should happen in a proper IDE, where proper debugging tools and full error messages can be monitored easily. For testing and debugging, some boiler-plate code snippets and parameter input data can be prepared, to mimic the input which could come from Panopticon parameters when the code is used via Panopticon.			
	In Panopticon, the code field of the transform or connector should contain an absolute mininum of code; perhap as little as a single function call, where the function takes the necessary arguments coming from Panopticon parameters.			
	With R and Rserve, it should be configured to load (import) your packages on startup, which will avoid the overhead of repeated loading of the packages upon each call.			
P	YTHON TRANSFORM			
ΑF	Python script can be executed as a data transformation step in the data pipeline. Specifically:			
	Data is retrieved from an underlying source.			
	The returned data table is translated into a Python object; specifically, a list of dictionaries.			
	The Python object, and supplied Python Script are passed to an external Python process running Pyro. (Python Remote Objects) e.g., https://pypi.python.org/pypi/Pyro4/			
	The external Pyro process returns a list of dictionaries.			
	The returned list of dictionaries is translated into a Panopticon table for visualization rendering.			
	 When used with streaming data sources (e.g., message bus), the Real Time Limit of a streaming data source should be set to a value longer than the time taken to perform the Python data transform. For example, if the transform operation takes 2 seconds, the Real Time Limit should be set to 2500 milliseconds. When used for non-streaming data sources (e.g., Database), the data table <i>Auto Refresh</i> period should be set to a value longer than the time taken to perform the Python data transform. For example, if the transform operation takes 2 seconds, the data table <i>Auto Refresh</i> period should be set to 3 seconds. 			
Ste	eps:			
1.	Tap the Enable Python Transform slider.			
	The Transform Settings button and Python tab change to respectively.			
2.	Specify the <i>Host</i> and <i>Port</i> of the Pyro process, along with the <i>HMAC key</i> (Password).			
3.				

4. Select the Serialization Type: Serpent or Pickle


Serpent – simple serialization library based on ast.literal_eval

Pickle – faster serialization but less secure

Modify the configuration.py file located in ..\Anaconda3\Lib\site-packages\Pyro4 to specify the serialization to be used.

For example, if **Pickle** is selected, self.SERIALIZER value should be changed to **pickle** and self.SERIALIZERS ACCEPTED value should be changed to include **pickle**:

```
def reset(self, useenvironment=True):
        Set default config items.
       If useenvironment is False, won't read environment variables settings (useful
if you can't trust your env).
       self.HOST = "localhost" # don't expose us to the outside world by default
        self.NS HOST = self.HOST
       self.NS PORT = 9090 # tcp
       self.NS BCPORT = 9091 # udp
       self.NS BCHOST = None
       self.NATHOST = None
       self.NATPORT = 0
       self.COMPRESSION = False
       self.SERVERTYPE = "thread"
       self.COMMTIMEOUT = 0.0
       self.POLLTIMEOUT = 2.0 # seconds
       self.SOCK REUSE = True # so reuseaddr on server sockets?
       self.SOCK NODELAY = False # tcp nodelay on socket?
        self.THREADING2 = False # use threading2 if available?
        self.ONEWAY THREADED = True # oneway calls run in their own thread
        self.DETAILED TRACEBACK = False
       self.THREADPOOL SIZE = 16
       self.AUTOPROXY = True
        self.MAX MESSAGE SIZE = 0 # 0 = unlimited
        self.BROADCAST ADDRS = "<br/>broadcast>, 0.0.0.0" # comma separated list of
broadcast addresses
        self.FLAME ENABLED = False
        self.PREFER IP VERSION = 4 # 4, 6 or 0 (let OS choose according to RFC 3484)
       self.SERIALIZER = "pickle"
        self.SERIALIZERS ACCEPTED = "pickle, marshal, json" # these are the 'safe'
serializers
        self.LOGWIRE = False # log wire-level messages
        self.PICKLE PROTOCOL VERSION = pickle.HIGHEST PROTOCOL
       self.METADATA = True # get metadata from server on proxy connect
        self.REQUIRE EXPOSE = False # require @expose to make members remotely
accessible (if False, everything is accessible)
       self.USE MSG WAITALL = hasattr(socket, "MSG WAITALL") and platform.system()
                # not reliable on windows even though it is defined
       self.JSON MODULE = "json"
       self.MAX RETRIES = 0
```



- 5. Tap the Use Apache Arrow slider to enable fast serialization of data frames in the Python transform.
- 6. Specify whether to Enclose Parameters in Quotes.
- 7. On the *Input Schema/Sample Data* section, click source are displayed.




In cases where there are no rows from the input data source and the Python script is not handling zero rows, you can add sample data to ensure transform is applied.

To add or manage the sample data, you can use the following icons:

Icon	Description			
+	Add sample data for the input column names.			
-	Check a box of a sample data row and click to delete or check the topmost box and click to delete all of the sample data rows.			

8. Enter the *Python Script*. This returns the output list of dictionaries. Just like an underlying SQL query, the Python script itself can be parameterized.



Click
 Test Script

 If successful, the output schema is displayed.

Otherwise, a notification is displayed with the cause of the error. Update the script.

- 10. The *Timeout* is set to **10** seconds by default to ensure that slow running Python scripts do not impact other areas of the product. You can opt to enter a new value.
- 11. Click Refresh Preview to see the output columns from the Python transform.
- 12. Refer to Enable Time Series Analysis for more information in enabling this feature.

Best Practices on Working with Python Transform in Panopticon

When applying a transform with Python in Panopticon for small and simple cases, you have the option of typing or pasting the code directly into the *Transforms* window. However, when you have several different transforms, or when each transform is applied in several data tables, it is highly recommended to follow the steps outlined below on how to apply functional programming and the D.R.Y. principle (Don't Repeat Yourself) to the Python transforms in Panopticon.

Steps:

- 1. Save your code in py-files for Python. This option gives you the freedom to work on the code using the IDE of your choice (i.e., PyCharm, Spyder, Atom etc.).
- 2. Instead of using an imperative coding approach, define one or several functions in the file, which when invoked, runs your code, takes a data frame as an input argument, and then returns the resulting data frame.
- 3. In the *Transforms* window of the Panopticon Designer, reference this external code file at the very top:

```
from sys import path
path.append("path/to/your/folder/")
import YourPythonFile
```

You can then invoke (call) any function that you have defined in your code file with a function call in the transform code window. Ideally, the function will return the transformed data frame.

4. The path to the external code file needs to be valid both from the point of view of Panopticon Designer on your local workstation, and from the point of view of Panopticon Real Time you publish to. This can be assured by introducing a global parameter in Panopticon Real Time under the **Parameters** tab.

For example, you can name the parameter **Python_code_path** and define its value as the full path to the folder that contains your code files. Next, on Panopticon Real Time, define a global parameter with the same name, but with a value that is the path to the server-side folder containing your code files. Copy the code files to the server-side folder then edit the path specified in your sourcing call in the transform so that it contains the parameter. For example:

```
from sys import path
path.append("{Python_code_path}")
import YourPythonFile
```

This will achieve a path reference to your code file which is valid in both the Designer and Server. It is also useful when promoting or migrating a Panopticon workbook from one server environment to another.

NOTE

- If there is a need to apply different transforms to different data sets, you can solve this by defining several different functions in your code file.
- For very similar functions, avoid repeating the same code in a file by factoring out the common parts and placing them in a separate function, which can be invoked by the other functions.
- For a transform that needs to have different outputs based on certain conditions or variables, this can be controlled by adding another input parameter to the function. Depending on the argument given to that parameter, you can make the function do things differently by evaluating a condition. In addition, this argument can – if you want to – be supplied via a Panopticon parameter and thereby be put under a dashboard enduser control.

Example code in Python

File: myTransformCode.py

```
# minimal example function
def AddOne(df, colname):
    df[colname] = df[colname]+1
    return(df)
```

Panopticon Python transform window code:

```
import pandas as pd
from sys import path
path.append("{my__Python_code_path}")
import myTransformCode as tc
# data set is loaded in a list of dictionaries named 'table'
myDataFrame = pd.DataFrame(table)
tc.AddOne(df = myDataFrame, colname = "value")
return(myDataFrame)
```

Additional Best Practice Recommendations in Using Python with Panopticon

With a <u>Python transform</u> or the <u>Python connector</u> in Panopticon, it is fairly quick and easy to enter some short code snippet and use the result. However, as a project grows, and if a solution is moved into production and becomes business critical, you need more structure in your use of Python with Panopticon:

- Code should be made into functions, even if used only in one place and even if the code content is very brief. Thereby, the operations performed by each function will be contained and you avoid the risk of naming conflicts and contamination in the global environment.
- □ Ensure you handle exceptions in the code you write. For example, when applying a Python transform to data, you can do an initial check in your code to see if the dataset is either a zero-row or has any rows. In which case, you want to terminate and just return the empty dataset. You should also use try-except clauses, whereby in the event of an error, you could, for example, insert the error message into the designated column in your dataset and then return it to Panopticon. If there is no error, the same column could contain a plain "OK" or similar as an indicator of a no-errors result.
- Functions should ideally be turned into a package. The benefit of that is mainly about the possibility of adding unit testing and automating dependency package imports.

Your package should have unit tests that are run when building the package.
Your package should import any other packages that you have a dependency on.
Developing, Testing, and Debugging the package should happen in a proper IDE, where proper debugging tools and full error messages can be monitored easily. For testing and debugging, some boiler-plate code snippets and parameter input data can be prepared, to mimic the input which could come from Panopticon parameters when the code is used via Panopticon.
In Panopticon, the code field of the transform or connector should contain an absolute minimum of code; perhaps as little as a single function call, where the function takes the necessary arguments coming from Panopticon parameters.

REST TRANSFORM


A REST Transform can be used when you have access to a REST API that accepts a POST or PUT request, containing data in a JSON-formatted request body. The API is expected to apply a specific transform or calculation on the data and returns the resulting data set. Typically, any REST API used this way is created and made available by your own organization, since the owner of the REST API will be able to monitor any data handed to it. Using a REST Transform is an alternative to using a Python Transform or R Transform. There are various cloud services that facilitate the task of exposing your code as a REST API.

Steps:

1.	Click the Transform Settings button on the <i>Data Sources Setting</i> pane.
	The <i>Transform</i> Settings pane displays.

2. Click _____

The Transform Settings pane changes to display the REST Transform Settings.




Tap the Enable REST Transform slider.

The **Transform Settings** button and **REST** tab change to respectively.


4. On the Request Settings section, define or select the following required properties:

Property
Authentication Type




Enter the *URL* of the REST API. Then enter the *User Id* and the *Password* that will be used to the connect to the REST API.

OAuth



Then enter the following settings:

- o **Token URL** The URL to retrieve the access token from.
- o **Token Request Body** The request body used for access token requests.
- Add Access Token To The Access token retrieved from the Token URL can be added to headers, URL or request body, depending on how the REST endpoint needs the token.



- Request Header A header is automatically added to the REST API request.
- Request URL The URL needs to be manually parameterised with a {access_token} parameter, before calling the REST API, the parameter is replaced with the actual token.

	 Request Body - The Request Body needs to be manually parameterised with a {access_token} parameter, before calling the REST API, the parameter is replaced with the actual token. URL - The URL of the REST API.
Timeout	The length of time to wait for the server response (10 to 300). Default is 10 .
HTTP Method	Select the appropriate HTTP method for the request from the following options: POST •
	POST
	PUT
	 POST – add new data PUT – replace existing data
Content Type	The only supported content type is application/json. This value cannot be changed.

5. Enter the Request Body.

The request body is required to always be JSON formatted. The request body JSON should be structured to conform with what the target REST API is expecting. To the extent that the REST API you are using supports it, you can include any values or Panopticon parameter references in the request body. There are three special parameters to use for referencing the dataset you send as part of your request:

Parameter	Description
{table}	Returns a JSON or Python dictionary along with the KEY and the values. For example, when used, the data in the response is: [{'ProductIds': 1.0, 'rel': 'a'}, {'ProductIds': 2.0, 'rel': 'b'}, {'ProductIds': 3.0, 'rel': 'c'}, {'ProductIds': 4.0, 'rel': 'd'}, {'ProductIds': 5.0, 'rel': 'e'}]
{table-columns}	Just the column names of the dataset.
{table-data}	Returns rows of pure data in the following form: [[1.0, 'a'], [2.0, 'b'], [3.0, 'c'], [4.0, 'd'], [5.0, 'e']] This example is a list of lists in Python.

In the example below, a JSON object has been constructed, consisting of three name-value pairs. The first two are referencing a couple of parameters that have also been defined on the data table in Panopticon, and the third one is referencing the {table} parameter. Where {table} is referenced, Panopticon will insert a JSON array of dictionaries (JSON objects of one name-value pair per column, and one such object per row in the dataset).

```
"requestId":{reqId},
"requestTime":"{_current_time_utc}",
"data":{table-data}
}
```

- 6. Select the Response Type:
 - JSON

	If JSON is selected, en JSON document (e.g.,		ch allows the identification of multiple records within the
	Response Type	Json	
	Record Path		(eg. myroot.items.item)
•	Text		
	If Text is selected, confincludes column heading		Column Delimiter, and if the first row of the message
	Response Type	Text	
	Text Qualifier	<none></none>	▼
	Column Delimiter	Comma {,}	▼
	First Row Headings	<u>~</u>	
	The Column Index con	trols the position of a col	umn, ensure the value is >= 0.
	XML	·	
	(e.g., //myroot/items/it		ch allows the selection of records within the XML document
	Record Xpath		
		e elements falling under	default namespace.
Click colu	Generate Columns	to the fetch the schen	na based on the connection details. Consequently, the list one first 'n' rows of the input data source is populated and the
You	can also opt to load or	save a copy of the colum	nn definition.
Click	to add columns an	d specify their properties	:
Pr	operty	Description	
Na	ame	The column name of t	he source schema.
	onPath/Text Column dex/XPath	The JsonPath/Text Co	lumn Index/XPath of the source schema.
Ту	ре	The data type of the c	olumn. Can be a Text, Numeric, or Time
Da	ate Format	The format when the	data type is Time .
Er	nabled	Determines whether the	ne message field should be processed.

To delete a column, check its \Box or all the column entries, check the topmost \Box , then click \blacksquare .

- 9. Click Refresh Preview to see the output columns from the REST transform.
- 10. Refer to Enable Time Series Analysis for more information in enabling this feature.

ORDER BOOK RECONSTRUCTION TRANSFORM

The *Transform* settings allow for orders to be reconstructed into an order book and standardized by conflating into an appropriate granularity for the output display.

The returned data table will be ready for the time series transform.

Steps:

1. To reconstruct a list of orders, click the **Transform Settings** button on the *Data Sources Setting* pane. The *Transform* Settings pane displays.

Orderbook Reconstruction

2. Click -

The Transform Settings pane changes to display the Order Book Reconstruction Settings.

3. Tap the Order Book Reconstruction slider.

The **Transform Settings** button and **Orderbook Reconstruction** tab change to Orderbook Reconstruction and Orderbook Reconstruction, respectively.

NOTE


- The Field Values section will have default values from the dataset.
- To reconstruct the Order Book from these orders, the data must include the following columns or fields:
 - o Order ID (Unique Per Order)
 - Order State / Event Type (New > Replace > Trade / Cancel)
 - o Update Time
 - Side (Buy or Sell)
 - o Price
 - o Balance / Remaining Quantity

Certain Order Types may also be excluded from the book reconstruction (e.g., Market Orders).

- 4. Match a column, from the generated schema of the source file, for the following Fields:
 - Id = [OrderID]
 - Type = [Order Type]
 - Price = [Limit Price (USD)]
 - Time = [Update Time]

- Order State = [Event Type]
- Side = [Side]
- Balance = [Remaining Quantity (BTC)]
- Price Group = [Symbol]

For example:



In this example, *Price Group* is mapped to **Symbol**. It can also be mapped to **Participant** if available in the data source.

- 5. Under the Field Value section, the default values for this dataset are mapped accordingly:
 - New = [New]
 - Canceled = [Cancelled]
 - Trade = [Trade]
 - Excluded = [Excluded]
 - Buy Side = [Buy Side]
 - Sell Side = [Sell Side]
- 6. Set the <u>Date/Time</u> range of the *Output* by entering values in the *From* and *To* text boxes. These values can also be parameterized.
- 7. Set the maximum number of levels of the output. Default is 25.

- 8. Set the target number of output time slices. Default is 100.
- 9. Click Refresh Preview to see the output columns from the Orderbook Reconstruction transform.
- 10. Refer to Enable Time Series Analysis for more information in enabling this feature.

NOTE

Enabling the time series analysis when you perform Order Book Reconstruction Transform solves the problem of having to specify all of the values. It also allows you to choose which Time column should be used to specify the time series.

WORKING WITH DATA SOURCES

Panopticon Real Time can connect to a number of disparate source repositories, including files, databases, and message buses. Although the process of retrieving a data table is similar, connectors may have different user interfaces.

Data connectivity to third-party products is based on general available versions. Typically, new versions are supported within one calendar year of release, although the timing of including the new version in support is dependent on customer demand. New versions of popular data sources within our customer base are generally supported quickly after general availability.

D-4- :-		: Da	!	Daal	T:		احصاسمي	:	41	-1-4-	4
Data is	retrieved	into Pai	iopticon	Real	i ime ai	na con	vertea	Into	three	aata	types:

- Number (Double)
- □ Text (Unicode)
- Timestamp (Nanosecond accuracy)

Date type conversion is specific to each data connector, and ODBC/JDBC driver for Database sources. However typical data type mappings are as follows:

- □ Boolean → Text
- □ Integer → Number
- □ Date → Timestamp
- □ Date/Time → Timestamp
- □ Time → Timestamp
- □ GUID → Text

Sources must support Unicode to be able to retrieve Unicode-based text.

NOTE

For streaming connectors, there are two settings that need to be considered:

Real Time Limit

This is the period how often Panopticon Real Time in-memory table is updated.

Auto Refresh


This is the period how often a client (i.e., Web/WPF) receives data from Panopticon Real Time.

Connecting to data sources may require entering your login credentials. To avoid saving this information in your workbooks, it is recommended to parameterize these connection settings. Refer to Parameterization of Connection Settings for Data Sources for more information.

Connector Availability

Connectors are available in *Add Data Table Wizard*, *Workbook Internal Data Table Editor*, *Data Table Editor*, and *Joined Data Table Editor*. Although the interfaces may be different, the fields or properties to configure for a connector is similar.

Below is the list of File/URL data sources in the Workbook Internal Data Table Editor layout.



Click on the other data source group tabs to select <u>database</u> and <u>streaming</u> data sources.


The Search box allows you to immediately find a particular data source that you want to use. Click a data source group tab then enter the name of the data source in the Search box.

Connecting to a Data Source in the Workbook Internal Data Table Editor

Steps:

1. Select a data source group tab in the *Connectors* pane then select a data source.

The Connector Settings pane displays (e.g., MS Excel (legacy).



- 2. You can opt to modify the *Name* of the data source then click .
- 3. Define the data source properties or options in the connector.

FILE/URL		
• <u>Azure</u>	Google Cloud	• <u>JSON</u>
MS Excel (legacy)	MS Excel (xlsx)	• <u>S3</u>
<u>SmartWorks IoT</u>	SmartWorks IoT Write	• <u>SVG</u>
• <u>Text</u>	Web Data	• <u>XML</u>
DATABASE		
• <u>Cassandra</u>	• <u>DolphinDB</u>	Elasticsearch 6.x
Elasticsearch 7.x	Google Analytics	• <u>InfluxDB</u>
• <u>JDBC</u>	JDBC Beta	• Kx kdb+
KsqlDB	• <u>LivySpark</u>	• MongoDB
• <u>OneTick</u>	OneTick Cloud	Panopticon Data Extract
• Python	• Rserve	Shakti Beta
• <u>Splunk</u>		
STREAMING		

ActiveMQ	<u>Amazon Kinesis – Data</u> <u>Streams</u>	• AMPS
DolphinDB - Streaming	Google Cloud Pub/Sub	JDBC Database - Streaming
• <u>Kafka</u>	Kafka Publisher	Kdb+ Tick
KsqlDB – Streaming	• MQTT	OneTick CEP
Panopticon Streams	RabbitMQ	Redis Streams
• Solace	Streams Simulator	Streams Simulator - Extract
StreamBase 7.1	StreamBase LiveView	WebSocket

- 4. Set the row limit of the data set, if required.
- 5. Tap the Preview Selected Data Source slider to turn it on.
- 6. Select one of the following:
 - Refresh Preview
 for static connectors, or
 - for streaming connectors.

FILE/URL DATA SOURCES

Connector for Azure

Azure connector allows:

- □ For retrieval of the file from an Azure blob storage
- □ JSON/XML/Text/Excel files to be read from the Azure blob storage

Steps:

1. Enter the following information:

Property	Description
Container	Azure container where the file resides.
Account Name	Azure storage account name.
Account Key	Azure storage account key. To test the connection, click Test Connection
	If Connection Failed displays, ensure the Container, Account Name, and Account Key values are correct. You can also hover on this message to view the connection error.
File Path	Azure blob file path.

2. Select the <u>Data Type</u>.

3. Select either the period (.) or comma (,) as the Decimal Separator.

NOTE Prepend 'default:' for the elements falling under default namespace.

- 4. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the **Save** button is enabled.
- 5. You can also opt to load or save a copy of the column definition.
- 6. Click to add columns to the Azure connection that represent sections of the message. Then enter or select:

Property	Description
Name	The column name of the source schema.
JsonPath/Column Index/XPath	The JsonPath/Column Index/XPath of the source schema.
Туре	The data type of the column. Can be a Text, Numeric, or Time
Date Format	The <u>format</u> when the data type is Time .
Enabled	Determines whether the message field should be processed.

NOTE

To parse and format times with higher than millisecond precision, the format string needs to end with a period followed by sequence of upper case S. There can be no additional characters following them.

For example: yyyy-MM-dd HH:mm:ss.SSSSSS

To delete a column, check its or all the column entries, check the topmost , then click .

Connector for Google Cloud

Google Cloud connector allows for retrieval of the file from Google Cloud storage. This connector allows JSON/XML/Text/Excel files to be read from the Google Cloud storage.

Steps:

1. Enter the following information:

Property	Description			
Bucket	Google Cloud bucket where the file resides.			
Access Key	Access key to your Google Cloud service account.			
Secret Key	Secret key to your Google Cloud service account. To test the connection, click Test Connection Connection Failed displays, ensure the Bucket, Access Key, and Secret Key values are correct. You can also hover on this message to view the connection error.			
File Path	Cloud storage resource path.			

- 2. Select the Data Type.
- 3. Select either the period (.) or comma (,) as the Decimal Separator.

NOTE Prepend 'default:' for the elements falling under default namespace.

- 4. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the **Save** button is enabled.
- 5. You can also opt to <u>load or save</u> a copy of the column definition.
- 6. Click to add columns to the Google Cloud connection that represent sections of the message. Then enter or select:

Property	Description
Name	The column name of the source schema.
JsonPath/Column Index/XPath	The JsonPath/Column Index/XPath of the source schema.
Туре	The data type of the column. Can be a Text, Numeric , or Time
Date Format	The format when the data type is Time .
Enabled	Determines whether the message field should be processed.

	NOTE	To parse and format times with higher than millisecond precision, the format string needs to end with a period followed by sequence of upper case S. There can be no additional characters following them.
		For example: yyyy-MM-dd HH:mm:ss.SSSSSS
То	delete a col	umn, check its or all the column entries, check the topmost , then click .

Panopticon Web Authoring Guide

Connector for JSON

The JSON connector allows the retrieval and processing of JSON files, either from a disk, a Text, or from a defined URL.

The supported JSON structures are discussed here.

Steps:

- 1. Select the JSON File Source.
- Enter the Record Path which allows the identification of multiple records within the JSON document (e.g., myroot.items.item). This property can be parameterized.
- 3. Select either the dot (.) or comma (,) as the Decimal Separator.
- 4. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the **Save** button is enabled.
- 5. You can also opt to load or save a copy of the column definition.
- 6. Click to add columns and specify their properties:

Property	Description	
Name	The column name of the source schema.	
Json Path	The Json Path of the source schema.	
Туре	The data type of the column. Can be a Text, Numeric, or Time	
Date Format	The <u>format</u> when the data type is Time .	
Enabled	Determines whether the message field should be processed.	

ſ	\neg		Γ	1 .	_
To delete a column, check its	_	or all the column entries, check the topmost	_	, then click	Ξ.

7. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged.

You can opt to define the Show in Timezone and Source Timezone settings.

Supported JSON Structures

Panopticon supports JSON structures that represent one or several records where each record will become a row in a data table. It can be an array of JSON strings, or a set of named JSON string elements. Each record must be on the same record path, e.g., **mydata.people**. Each name in each record must follow hierarchically directly after the record path, e.g., **mydata.people.name**. Each record must be a JSON string of name-value pairs. Each name can have the following as value:

	sing		

- a JSON string of other name-value pairs
- a JSON array of values

Each name that has as value a single value or an array of values will become a column in the data table. In case a name has as value an array of multiple values, then each value in the array will result in a column in the data table.

In case the JSON data has a structure where a name does not contain a single value, but instead an array of several values, you can optionally omit this name from the data table when making the column settings in the Panopticon data connector, by manual deletion. This is typically a preferred option when the array contains a large number of

values, or when the different records have a large variety in the values, since this will result in a large number of columns, where many of the rows will have a blank value.

Here are examples of supported JSON structures:

Example 1: An array of JSON strings with name-value pairs, each name with a single value:

Example 2: An array of JSON strings with name-value pairs, some names having a single value and some names having a nested JSON string as value:

```
{
      "mydata": {
            "people": [{
                         "Name": "Peter",
                         "Age": "20",
                         "Address": {
                                "Street": "Park Avenue",
                                "Number": "1"
                         }
                   },
                         "Name": "Paul",
                         "Age": "21",
                         "Address": {
                                "Street": "Mainstreet",
                                "Number": "17"
                   },
                         "Name": "Mary",
                         "Age": "22",
                         "Address": {
                                "Street": "Cedar Road",
                                "Number": "5"
                         }
                   }
            ]
      }
}
```

Example 3: Named elements instead of an array, where the element name will be parsed into a column called **KeyColumn** in the data table:

```
{
      "Peter": {
            "Age": "20",
            "Address": {
                   "Street": "Park Avenue",
                   "Number": "1"
            }
      "Paul": {
            "Age": "21",
            "Address": {
                   "Street": "Mainstreet",
                   "Number": "17"
      } ,
      "Mary": {
            "Age": "22",
            "Address": {
                   "Street": "Cedar Road",
                   "Number": "5"
            }
      }
}
```

Example 4: An array of JSON strings with name-value pairs, where some names have as value an array of multiple values. A column will be created in the data table for each unique value in the arrays:

```
{
      "mydata": {
            "people": [{
                         "Name": "Peter",
                         "Age": "20",
                         "Address": ["Mainstreet", "Whoville"]
                  },
                   {
                         "Name": "Paul",
                         "Age": "21",
                         "Address": ["Backstreet", "Barnburg"]
                   },
                         "Name": "Mary",
                         "Age": "22",
                         "Address": ["Runroad", "Suburbia"]
                  }
            ]
      }
```

Connector for MS Excel (Legacy)

This is the most commonly used data connector when prototyping and is used for retrieving data from MS Excel workbooks or spreadsheets, where for each selected sheet, the first row contains the field/column names, and subsequent rows contain the data.

NOTE

In production use, it is not advised to use a single Excel file as multiple Panopticon data sources. This is because, when using the same Excel file with the data on several sheets, conflicts may occur in reading the file.

Steps:

- 1. Select the MS Excel File Source.
- 2. Select the number of rows that will be skipped in the Excel file from the Skip First n Rows drop-down list.
- 3. If the MS Excel file is password-protected, enter the File Password.


Check the **Show Characters** box to display the entered password characters.



Otherwise, proceed to step 6.

- 4. Click . This updates the *Sheet* drop-down list box and the **Upgrade to MS Excel (xlsx)**Upgrade to MS Excel (xlsx) button is enabled if the selected file is XLSX.
- 5. You can either:
 - · select the required sheet then proceed to step 8, or
 - click Upgrade to MS Excel (xlsx) to upgrade XLSX data source to MS Excel (xlsx).

Once upgraded, the first available sheet will be automatically selected, and the columns will be populated.



See MS Excel (xlsx) Connector for more information.

Upgrading Legacy MS Excel XLSX Data Source to the new MS Excel (xlsx) Connector

The upgrade is only available for MS Excel data sources that are not:


- □ Using a Range since MS Excel (xlsx) only supports selection of a sheet.
- Using password protection.

Steps:


1. On the Workbooks and Folders Summary page, click a legacy workbook with an MS Excel XLSX connector data source.

The workbook is displayed on the Open Workbook in Edit View layout.

- 2. Do one of the following:
 - Click Edit Data Table to open the Edit Data Table Wizard, or




Click Workbook Data Table Editor to open the Workbook Internal Data Table Editor view.




3. click Upgrade to MS Excel (xlsx)

The settings are now displayed on the MS Excel (xlsx) connector panel.

On the Edit Data Table Wizard:



On the Data Table Editor view:



See Connector for MS Excel (xlsx) to make the necessary changes.


Connector for MS Excel (xlsx)

The MS Excel (xlsx) connector allows for retrieval and processing of MS Excel workbook data stored using the XLSX file format. The MS Excel (xlsx) connector processes data on a row-by-row basis, allowing for better performance and less memory consumption compared to the MS Excel (legacy) connector.

Steps:

1. Select the MS Excel (xlsx) file source. Do one of the following:

To change the data source, click then **Browse**



Browse

Link to a XLSX data source file by clicking **Link to File** and entering a *File Path*.


is uploaded into the repository, and also create a new version of the workbook that reads it.

to browse to a new version of the file, which



Ensure that in a cluster, you need to use a shared path, or put it on every node and use a path that resolves on every node. You can update its contents whenever you want.

When a file is selected, the MS Excel (xlsx) connector will automatically select the first available sheet, set the first row as headers, and populate available columns.



By default, all the generated columns are enabled. You can uncheck the **Select All** box, then check the boxes of the columns that will be enabled.

- 2. Adjust Sheet selection, if required. Selecting a new sheet will re-populate the Columns list.
- Adjust the Headers On First Row if needed. By default, the connector will pick up headers from the first row if all cells on the first row contain text data.

You can opt to select one of the following:

- Leave headers on first row as Auto if you want the connector to automatically pick up column names from sheet.
- Select Yes to force picking first row as headers.
- Select No to force not picking first row as headers. This will auto generate all column names.

Columns

Name	Туре		Date Format	Enabled
Column1	Text	~	~	✓
Column2	Text	~	*	~
Column3	Text	~	*	✓
Column4	Text	~	~	✓
Column5	Text	~	_	✓
Column6	Text	~	_	~

4. Adjust column *Type* or *Date Format* to adjust data interpretation.

Connector for S3

The S3 connector allows for retrieval of the file from an S3 storage location. This connector allows JSON/XML/Text/Excel files to be read from the S3 storage. This connector will work with any S3 compliant storage providers.

Steps:

1. Enter the following information:

Property	Description
URL	URL where the S3 bucket can be accessed. Default is https://s3.amazonaws.com .
Bucket	S3 bucket where the file resides.
Access Key	Access key to your S3 service account.
Secret Key	Secret key to your S3 service account. To test the connection, click Test Connection
	If Connection Failed displays, ensure the <i>Bucket</i> , <i>Access Key</i> , and <i>Secret Key</i> values are correct. You can also hover on this message to view the connection error.
File Path	Path of the on the S3 bucket.

- 2. Select the <u>Data Type</u>.
- 3. Select either the period (.) or comma (,) as the Decimal Separator.



- 4. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the **Save** button is enabled.
- 5. You can also opt to <u>load or save</u> a copy of the column definition.

6. Click to add columns to the S3 connection that represent sections of the message. Then enter or select:

Property	Description	
Name	The column name of the source schema.	
JsonPath/Column Index/XPath	The JsonPath/Column Index/XPath of the source schema.	
Туре	The data type of the column. Can be a Text, Numeric, or Time	
Date Format	The format when the data type is Time .	
Enabled	Determines whether the message field should be processed.	

NOTE	To parse and format times with higher than millisecond precision, the format string needs to end with a period followed by sequence of upper case S. There can be no additional characters following them.
	For example: yyyy-MM-dd HH:mm:ss.SSSSSS
To delete a co	or all the column entries, check the topmost , then click .

Connector for SmartWorks IoT

The SmartWorks IoT connector allows reading data from SmartWorks IoT, mostly from AnythingDB OpenAPI endpoints. This dedicated connector is recommended over the standard JSON connector since it can automatically iterate over all the available data from service using **next_cursor** information in the response. The UI also allows minimal settings required to connect to the SmartWorks IoT OpenAPI endpoints.

NOTE

The Token URL is not visible in the connector. You can set the server-wide token URL in the "connector.oauth.tokenurl" property in the Panopticon.properties file.

Steps:

1. Enter the Client ID, Client Secret, Grant Type, and Scope to connect to the SmartWorks IoT.

The Panopticon server builds up the request body formatted as **application/x-www-form-urlencoded** from these four fields.

2. Enter the full *URL* including any filter query, limit, etc.

For example:

https://api.swx.altairone.com/spaces/altair/collections/ElectronicBoards/things-status?limit=50&property%3Atemp=gt%3A20&property%3Adim=80

- 3. Enter the Record Path. Default is data.
- 4. Select either the dot (.) or comma (,) as the Decimal Separator.
- 5. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the **Save** button is enabled.
- 6. You can also opt to load or save a copy of the column definition.

7. Click . A new column entry is displayed. Enter or select the following properties:

Property	Description	
Name	The column name of the source schema.	
JsonPath	The JsonPath of the source schema.	
Туре	The data type of the column. Can be a Text , Numeric , or Time	
Date Format	The <u>format</u> when the data type is Time .	
Enabled	Determines whether the message should be processed.	

To delete a column, check its	or all the column entries, check the topmost	. then click	_
TO delete a column, check its	of all the column entires, check the topinost	, trierr click	

- 8. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged.
 - You can opt to define the **Show in Timezone** and **Source Timezone** settings.
- 9. Set the <u>row limit of the data set</u>. Consequently, the maximum number of records fetched from service is controlled as this setting is used while auto iterating data from service using the **next_cursor** information in the response.

Connector for SmartWorks IoT Write

The SmartWorks IoT Write connector allows calling PUT/POST/DELETE requests to SmartWorks IoT services for write back scenarios. A typical use case is to add or update records in AnythingDB from Panopticon. Since this connector is not for reading data, a successful service call will only return a data table with one column called **Result** with **Success** as value.



The Token URL is not visible in the connector. You can set the server-wide token URL in the "connector.oauth.tokenurl" property in the Panopticon.properties file.

Steps:

1. Enter the Client ID, Client Secret, Grant Type, and Scope to connect to the SmartWorks IoT Write.


The Panopticon server builds up the request body formatted as **application/x-www-form-urlencoded** from these four fields.

2. Enter the URL that accepts PUT/POST/DELETE request.

For example:

 $\verb|https://api.swx.altairone.com/spaces/altair/collections/ElectronicBoards/things/01edb9j75vymj8p7qppm19h8nx|$

3. Specify the appropriate *HTTP Method* for the request from the following options:



- POST Add new data.
- PUT Replace existing data.
- DELETE Remove existing data.

- 4. Enter the Request Body for the HTTP POST/PUT.
- 5. Click Refresh Preview to call the service.

NOTE

Use PUT requests carefully to avoid duplicate entries since each data call to this connector will trigger a service call.

Connector for SVG

The SVG connector can provide for:

- Maps for Choropleth map visualizations (http://en.wikipedia.org/wiki/Choropleth map).
- □ Store plans for visualization of crowd flows, client interaction volumes, and so on.
- Schematic drawings of process industry facilities for hardware performance monitoring.

The SVG XML is translated, and the rendering is done by Panopticon Real Time. For this reason, Panopticon Real Time does not support the full scope of the SVG standard definition.

The only element supported is PATH: http://www.w3.org/TR/SVG/paths.html

This connector allows you to select the SVG *File Source*.

Creating Custom Shapes

SVG-files with path expressions describing custom shapes are easy to create for simple shapes.

NOTE

The x-y coordinate system in the Panopticon <u>Shapes</u> visualization has positive x-values going right and positive y-values going DOWN, not up. An empty shape visualization has origo (0,0) at the top-left corner.

In the d-attribute of the path element, the following commands/instructions are supported by the <u>Shapes visualization</u> in Panopticon:

M,m: http://www.w3.org/TR/SVG/paths.html#PathDataMovetoCommands

Z,z: http://www.w3.org/TR/SVG/paths.html#PathDataClosePathCommand

L,1: http://www.w3.org/TR/SVG/paths.html#PathDataLinetoCommands

H,h: http://www.w3.org/TR/SVG/paths.html#PathDataLinetoCommands

V, v: http://www.w3.org/TR/SVG/paths.html#PathDataLinetoCommands

C,c: http://www.w3.org/TR/SVG/paths.html#PathDataCubicBezierCommands


S,s: http://www.w3.org/TR/SVG/paths.html#PathDataCubicBezierCommands

NOTE

Upper case commands set the absolute points, while the lower case commands set the relative points.

The following code, saved in a text file with the file extension .svg, can be read with the SVG connector in Panopticon and will produce 2 columns: **NodeKey1**, which contains the id-values for the g-tags, and **ShapeData**, which contains the d-value of the path-tags. The ShapeData column can then be applied to the <u>Shapes variable</u> of the <u>Shapes variable</u> of the <u>Shapes variable</u> part.

```
<svg>
<g id="Square Example">
<path d="M 1,1 h 9 v 9 h -9 v -9 z" />
</g>
<g id="Triangle Example">
<path d="M 11,10 h 10 l -5,-10 l -5,10 z" />
</g>
<g id="Circle Example">
<path d="M 0.5,17 c0.5,6.667 9.5,6.667 10,0 -0.5,-6.667 -9.5,-6.667 -10,0 z"
/>
</g>
<g id="Hexagon Example">
<path d="M 20.5,14.5 l -4.33,-2.5 -4.33,2.5 0,5 4.33,2.5 4.33,-2.5 0,-5 z" />
</g>
</svg>
```



The same data can be provided in a tabular form, loaded with the Text connector or from a database. For example:

```
NodeKey1, ShapeData
Square Example, |M 1 1 h 9 v 9 h -9 v -9 z
Triangle Example, |M 11 10 h 10 l -5 -10 l -5 10 z
Circle Example, |M 0.5 17 c 0.5 6.667 9.5 6.667 10 0 c -0.5 -6.667 -9.5 -6.667 -10 0 z
Hexagon Example, |M 20.5 14.5 l -4.33 -2.5 l -4.33 2.5 l 0 5 l 4.33 2.5 l 4.33 -2.5 l 0 -5 z
```

Likewise, this data can be used with the **Shapes variable** of the **Shapes visualization** part.

NOTE

When shape paths are loaded from a tabular data, each path must begin with a vertical bar character ("pipe").

Drawing a Circle with Cubic Bézier Curves


It is not possible to create a perfect circle with cubic Bézier curve commands, i.e., the c/C and s/S commands. A simple to use approximation of a circle that is created with just two Bézier curves is as follows:

The c command takes 3 points (x, y) as arguments: the first two are control points and the third is the end point. To draw the lower half of a circle with a diameter of 1, drawing from left to right, you can use these control point values. All points are expressed relative to the starting position. Remember that the y-axis is positive in the downwards direction.

```
controlpoint 1: x = 0.05, y = 0.6667 controlpoint 2: x = 0.95, y = 0.6667 end point: x = 1, y = 0
```

which makes:

c 0.05, 0.6667 0.95, 0.6667 1, 0 z



To draw a complete circle with a diameter of 1, you continue the c command with 3 more points, giving the two control points and the end point of the upper half of the circle. Note that you don't need to repeat the c command:

So, the x-value of the first control point is 5% of the diameter, and the x-value of the second control point is 95% of the diameter.


The y-values are 2/3:s of the diameter. The sign of the relative point depends on the direction in which you are moving. Positive y-values are downwards.

Connector for Text

The Text connector allows the retrieval and processing of delimited Text files (such as CSV, TSV, and so on), either from a disk or from a defined URL.

Steps:

1. Select the Text File Source.



The standard settings controlling how the text file is parsed, is listed. These include the following:

Property	Description	
Skip First N Rows	Specifies the number of rows that will be skipped.	
Data Type Discovery	Specifies how many rows from the text file should be used when automatically determining the data types of the resulting columns.	
Text Qualifier	Specifies if fields are enclosed by text qualifiers, and if present to ignore any column delimiters within these text qualifiers.	
Column Delimiter	Specifies the column delimiter to be used when parsing the text file.	
First Row Headings	Determines if the first row should specify the retrieved column headings, and not be used in data discovery.	

2. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the **Save** button is enabled.

By default, all the generated columns are enabled. You can uncheck the **Select All** box, then check the boxes of the columns that will be enabled.

- 3. You can also opt to load or save a copy of the column definition.
- 4. Click to add columns and specify their properties:

Property	Description	
Name	The column name of the source schema.	
Column Index	The column index controls the position of a column. Must be >= 0.	
Туре	The data type of the column. Can be a Text , Numeric , or Time	
Date Format	The format when the data type is Time .	
Enabled	Determines whether the message should be processed.	

To delete a column, check its \Box or all the column entries, check the topmost \Box , then click $\overline{}$.

5. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged. You can opt to define the <u>Show in Timezone and Source Timezone</u> settings.


Connector for Web Data

The Web Data connector allows the retrieval and processing of JSON, delimited Text (such as CSV, TSV), and XML data that is accessible over HTTP/HTTPS.


Steps:

- 1. Enter the absolute URL of the web data including scheme (HTTP/HTTPS) into the URL field.
- 2. Click Test Connection and Update Settings

 . A successful connection will result to the following:
 - The Connection Successful status is displayed along with some raw data returned by the server.



Connector tries auto discovery of the Data Type.




You can also opt to <u>load or save</u> a copy of the column definition.


- 3. Adjust the Authentication Type, if required.
 - 3.1. Select the Authorization tab.



3.2. Set the required settings:

Authentication Type	Description
None	No authentication needed.






4. The **Headers** tab allows you to enter any custom headers required to be passed to the URL endpoint, typically to provide additional metadata. Enter any key/value pairs you need, and the connector will send them along with request.



- 5. Set the *Body*, if a POST/PUT request is required.
 - 5.1. Select the **Body** tab.



5.2. Set the required settings:

Property	Description	
HTTP Method	Select the appropriate HTTP method for the request from the following options:	
	POST – add new data	

	PUT – replace existing data	
Content Type	Select or enter content-type based on request body (payload) format.	
Request Body	The Request Body for the HTTP POST method.	

- 6. Set the Advanced settings, if needed.
 - 6.1. Select the Advanced tab.

Test Result Author	ization Headers	Body	Advanced
Proxy Server URI			
Content Encoding	None		
Timeout	10		₩
Decimal Separator	Period {.}		▼
Show in Timezone			
Source Timezone	UTC		~

6.2. Set the required settings:

Property	Description	
Proxy Server URI	The HTTP Proxy setting that will allow the connector to reach the endpoint.	
Content Encoding	Select the <i>Content Encoding</i> with the HTTP Header: None, GZip, Deflate, or GZip and Deflate	
Timeout	The length of time to wait for the server response (10 to 300). Default is 10 .	
Decimal Separator	Select either the dot (.) or comma (,) as the decimal separator.	

6.3. You can opt to define the <u>Show in Timezone</u> and <u>Source Timezone</u> settings.

Connector for XML

The XML connector allows the retrieval and processing of XML files, either from a disk, a Text, or from a defined URL.

Steps:

- 1. Select the XML File Source.
- 2. Enter the *Record XPath* which allows the selection of records within the XML document (e.g., //myroot/items/item). This property can be parameterized.
- 3. Select either the dot (.) or comma (,) as the Decimal Separator.
- 4. Click Generate Columns to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the Save button is enabled.

- 5. You can also opt to load or save a copy of the column definition.
- 6. Click to add columns and specify their properties:

Property	Description	
Name	The column name of the source schema.	
XPath	The XPath of the source schema.	
Туре	The data type of the column. Can be a Text, Numeric, or Time	
Date Format	The <u>format</u> when the data type is Time.	
Enabled	Determines whether the message should be processed.	

				_
To delete a column, check its	or all the column entries, check the topmost	\Box	, then click	Ξ.

7. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged. You can opt to define the *Show in Timezone* and *Source Timezone* settings.

DATABASE DATA SOURCES

Connector for Apache Cassandra

The Apache Cassandra connector allows connection to Apache and Datastax Cassandra instances, by executing a pre-defined CQL query, and retrieving the resulting data.

Steps:

1. Enter the following information:

Property	Description
Host	Apache Cassandra host address.
Port	Apache Cassandra host port. Default is 9042.
KeySpace	Namespace that defines data replication in nodes.
User Id	The username used to connect to the Apache Cassandra service.
Password	The password used to connect to the Apache Cassandra service.

- 2. Select whether the parameters should be automatically enclosed in quotes, by checking the **Enclose** parameters in quotes box.
- 3. Enter the CQL Query, which can contain parameters in a similar manner to the database connector.
- 4. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged. You can opt to define the <u>Show in Timezone</u> and <u>Source Timezone</u> settings.

Connector for DolphinDB

The DolphinDB connector allows you to connect and query tables using DolphinDB java API.

Steps:

1. Enter the following information:

Property	Description
Host	DolphinDB host address.
Port	DolphinDB host port. Default is 8848.
User Id	The username used to connect to the DolphinDB service.
Password	The password used to connect to the DolphinDB service. Check the Show Characters box to display the entered password characters.

2. Enter the Query, which can contain parameters in a similar manner to the database connector.

Connector for Elasticsearch 6.x

The Elasticsearch 6.x connector allows you to connect and access data from an Elasticsearch cluster using Transport Client.

NOTE

- To enable the Elasticsearch 6.x connector, refer to <u>Elasticsearch</u> <u>Connectors Dependency Installation</u> for more information on how to copy the provided dependency files to the Lib folder.
- The Elasticsearch 6.x connector supports Elasticsearch 6.x versions.
- Elasticsearch 6.x and <u>Elasticsearch 7.x</u> connectors will not work in a single Panopticon Real Time instance due to conflicting Elasticsearch API dependencies.

Steps:

1. Enter the following information:

Property	Description
Host	The hostname of any node in your Elasticsearch cluster, or localhost for a node on your local machine.
Port	The port running the Elasticsearch HTTP service (default is 9300). If the port you wish to use is different from the default port, change the value to the correct one.
Cluster Name	The cluster name that can be used to discover and auto-join nodes.
Index Name	The Index name in Elasticsearch. This is some type of data organization mechanism that allows partition of data in a certain way.

2. Enter an optional JSON-encoded request body in the Query box.

Connector for Elasticsearch 7.x

The Elasticsearch 7.x connector allows you to connect and access data from an Elasticsearch cluster using Java High Level REST Client.

NOTE

- To enable the Elasticsearch 7.x connector, refer to <u>Elasticsearch</u> <u>Connectors Dependency Installation</u> for more information on how to copy the provided dependency files to the <u>Lib</u> folder.
- The Elasticsearch 7.x connector supports Elasticsearch 7.x versions.
- <u>Elasticsearch 6.x</u> and Elasticsearch 7.x connectors will not work in a single Panopticon Real Time instance due to conflicting Elasticsearch API dependencies.

Steps:

1. Enter the following information:

Property	Description
Host	The hostname of any node in your Elasticsearch cluster, or localhost for a node on your local machine.
Port	The port running the Elasticsearch HTTP service (default is 9300). If the port you wish to use is different from the default port, change the value to the correct one.
User Id	The username used to connect to the Elasticsearch 7.x service.
Password	The password used to connect to the Elasticsearch 7.x service. Check the <i>Show Characters</i> box to display the entered password characters.
Cluster Name	The cluster name that can be used to discover and auto-join nodes.
Index Name	The Index name in Elasticsearch. This is some type of data organization mechanism that allows partition of data in a certain way.

- 2. Enter an optional JSON-encoded request body in the Query box.
- 3. Click Generate Columns

 The columns populate the Output Column section.
- 4. Click to add columns and specify their properties:

Property	Description
Name	The column name of the source schema.
Туре	The data type of the column. Can be a Text, Numeric , or Time
Date Format	The <u>format</u> when the data type is Time .
Enabled	Determines whether the message field should be processed.

To delete a column, check its or all the column entries, check the topmost , then click .

Elasticsearch Connectors Dependency Installation

Dependencies for each supported Elasticsearch version are included in the Panopticon Real Time zip as individual zip archive files:

- Elastic_6X_Dependencies.zip
- □ Elastic_7X_Dependencies.zip.

Steps:

- 1. Select the target Elasticsearch version and unzip the contents of the appropriate dependency zip into the tomcat/webapps/panopticon/WEB-INF/lib folder to enable connectivity for a specific server instance.
- 2. Restart Tomcat.

Connector for Google Analytics


The Google Analytics connector allows you to track and report website traffic using the Google Analytics service. You will need the following to fetch Google Analytics data:

Field	Description
Service Account E-mail	The Service Account ID that is generated while creating credentials for the service account authentication.
Key File	The Key File (.p12) furnished by Google Analytics when you created the Service Account.
Profile ID	The Profile ID of the page you want to access in Google Analytics.

Information on how to configure service account authentication for Google Analytics is discussed here.

Steps:


- 1. Enter the Service Account Email that was generated while creating credentials to the service account authentication.
- 2. Set the Key File that will be used to connect to Google Analytics in Panopticon. Do one of the following:




Path.



- Enter the *Profile ID* of the page you want to access in Google Analytics.
- Enter the Start Date and End Date, if needed.
- Fetch Dimensions And Metrics Click . This populates the Filter By Categories, Dimensions, and Metrics list 5. boxes.
- then select any field from these list boxes. Click



For example:



Click X to remove a field.

Configuring Service Account Authentication for Google Analytics

Before using the Google Analytics connector, the following steps must be performed:

- 1. Configure the Google Analytics Service Account Authentication
- 2. Enable the Analytics API
- Set Edit Permissions to the Service Account ID
- 4. Extracting Profile ID from the URL


Each step is discussed below.

Steps:

The authentication mode needs to be enabled from the account email that you will use.


1. Go to http://console.developers.google.com and log-on using your credentials.

The Google APIs & Services is displayed.




The Google Analytics connector works on a service account authentication mode. To create a service account, you must first create a project.

2. On the APIs & Services section, click Credentials.



Click CREATE CREDENTIALS and choose Service Account Key to create credentials for the service account authentication.

+ CREATE CREDENTIALS



The Create Service Account page displays:

Create service account

Service account name

Display name for this service account

Service account ID * X C

Email address: <id>@keen-bazaar-242206.iam.gserviceaccount.com

Service account description

Describe what this service account will do

CREATE AND CONTINUE

- Grant this service account access to project (optional)
- Grant users access to this service account (optional)

DONE CANCEL


4. Enter the Service Account Name. This is displayed in the Service Account ID box.

Click **Copy to Clipboard** to copy the generated *Service Account Email* to clipboard.


- 5. Click Create and Continue to create the service account.
- 6. You may skip steps 2 and 3 then click **Done**.

The new service account is listed in the Credentials page.

7. To generate the key file, click the service account you created.



8. Select the **Keys** tab, then **Add Key > Create new key**.



The Create Private Key for "<Service Account>" dialog displays.


9. Select P12 Key Type and click Create.

The private key is downloaded. Ensure to copy the private key password and save a copy of the key file.


2. Enabling Analytics API

Follow these steps to enable Analytics API:

 On the APIs & Services section, click ENABLE APIS AND SERVICES to display the API Library page and select Google Analytics API.



The Google Analytics API page is displayed.



Overview

OVERVIEW

About Google

Google's mission is to organize the world's information and make it universally accessible and useful. Through products and platforms like Search, Maps, Gmail, Android, Google Play, Chrome and YouTube, Google plays a meaningful role in the daily lives of billions of people.

The Analytics API provides access to Analytics configuration and report data.

DOCUMENTATION

Additional details

Type: <u>SaaS & APIs</u>
Last updated: 7/22/21
Category: <u>Other</u>


Service name: analytics.googleapis.com

2. Click ENABLE.

3. Setting Edit Permissions to the Service Account ID

Before using the Google Analytics connector, users must request for their service provider account access from the administrator.

- 1. Send the generated service account ID to the Google Analytics administrator.
- The administrator grants permissions to the user in the Admin > User Access Management page in their Google Analytics account.




3. The administrator must ensure to give **Edit** permission to the user.

4. Extracting Profile ID from the URL

Aside from the Service Account ID and the Key File, you also need to extract the Profile ID from the URL in order to connect to the Google Analytics connector in Panopticon Real Time.

1. Go to http://analytics.google.com and sign in.

The Google Analytics account page is displayed.



2. Check the URL. For example: https://analytics.google.com/analytics/web/#/report-home/a141137636w202161341p196007843

All of the digits that follow p is the Profile ID (e.g., 196007843)

Connector for InfluxDB

The InfluxDB connector allows for the retrieval of a JSON data set from the InfluxDB. The database communicates over HTTP(S) where you can define a query in the URL to return the desired data.

Steps:


1. Enter the following information:

Property	Description
URL	InfluxDB host address.
Port	InfluxDB host port. Default is 8086.
User Id	The user Id that will be used to connect to the InfluxDB service.
Password	The password to connect to the InfluxDB service. Check the Show Characters box to display the entered characters.
Database	The name of the database that will communicate over the HTTP(S).
Time out (Secs)	The time out period applied to both the TCP socket and for individual read IO operations. Default is 10 .

- 2. Enter an SQL-like query language into the Query box.
- 3. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged. You can opt to define the *Show in Timezone* and *Source Timezone* settings.

Connector for JDBC Database

The JDBC connector allows the retrieval and processing of data from virtually any database, that has a JDBC driver. It can be used If the database you want to connect to is not listed in the *Connectors* panel.



Steps:


1. Click **Connection Settings** to expand and display the properties you can set.



2. You can either select:



Enter the JNDI resource name to be used.



URL



Enter the *URL* specific to the database's JDBC driver, the *Driver Class Name* specific to the driver, and the *User Id* and *Password*.

Check the **Show Characters** box to display the entered characters.

3. Select the appropriate *SQL Dialect* in the drop-down list to be able to generate the correct *SQL* for the required data repository.



You can select any of the following *SQL dialects*: AnsiSQL, MySQL, Oracle, SQL Server, Sybase IQ/ASA, Sybase ASE, Netezza, Vertica, SQLite, HadoopHive, DB2, PostgreSQL, Impala, Redshift, Informix, Teradata, dBase, SparkSQL.

Default is AnsiSQL.

- 4. Enter the Timeout. Default is 60.
- 5. Check any of the following options when building the query:
 - Enclose parameters in quotes

By default, this option is checked, as the common use case for parameters is a filter \mathtt{WHERE} clause.

Allow in-memory parameter filtering

Allows the whole dataset to be returned, and then filtered in memory. This process is much less efficient than adding the parameter as a \mathtt{WHERE} clause of the SQL query; however, it may be efficient in cases where small sets of records are returned on a very frequent basis.

Use data modification query

Signals that the table is created for writing data. This property is also used for filtering out target data tables for further data update action configuration

• Enable on-demand queries

On-demand queries provide ROLAP functionality to the Altair Visual Data Discovery products, where the aggregation and filtering tasks are largely offloaded to the underlying data repository.


6. When **Table** is selected, the section below is enabled:



7. On the *Table* field, click Load to populate the drop-down list with tables. Select a table.

The SQL query is generated and displayed in the Query text box.

Also, expanding the Join Tables displays the list of tables that you can join.



8. Perform a join by checking one or more tables in the list.


The Left Column and Right Column fields are automatically filled out with the common fields.



You can also opt to select other common fields.

The SQL query is generated and displayed in the Query text box.

public.forex



select all of the columns, check the topmost box.

The SQL query is generated and displayed in the Query text box.

- 11. If the data returned is to be aggregated, then the Aggregate box should be checked. For each selected column, the possible aggregation methods are listed including:
 - Text Columns: Last, First, Count, Group By
 - Date Columns: Count, Min, Max, Group By
 - Numeric Columns: Last, First, Sum, Count, Min, Max, Mean, Group By

The SQL query is generated and displayed on the Query text box.

12. Check the **Parameterize** box and match the parameter to the appropriate column. By default, they will be matched by name.

The appropriate SQL Query is updated in the Query text box.

13. If the data is to be filtered or aggregated on Date/Times, then a valid Date Time field needs to be selected from either a single Date/Time field, or a compound column created from a selected Date and a selected Time column.

Date Time	*	or	▼	+	w

- 14. Click the Query radio button to enable the text box and modify the SQL-like query language.
- 15. You can opt to define the Show in Timezone and Source Timezone settings.



Migration from Database to JDBC Connector

The Database connector from legacy workbooks is not supported in the Web Authoring. To be able to modify the connection settings, you should migrate to the JDBC connector.

Steps:

- On the Workbooks and Folders Summary page, click a legacy workbook with a Database connector data source.
 The workbook is displayed on the Open Workbook in Edit View layout.
- 2. Click **Edit Data Table** open and view the *Workbook Internal Data Table Editor*.
- 3. Click Migrate to JDBC Connector

The settings are now displayed on the JDBC connector pane.

Refer to Connector for JDBC Database to make the necessary changes.

Connector for JDBC Beta

JDBC Beta connector is the new version of <u>JDBC connector</u> and is the recommended connector for any new JDBC connectivity for better performance and configuration UI. Just like JDBC connector, it also allows the retrieval and processing of data from virtually any database, that has a JDBC driver.

Steps:

- 1. On the **Connection** tab, set either of the following connection settings:
 - URL



Enter the *URL* specific to the database's JDBC driver, the *Driver Class Name* specific to the driver, and the *User Id* and *Password*.

Check the **Show Characters** box to display the entered characters.

JNDI Name


JNDI Name	7	(JNDI resource	e name	e as defined	l inside	Context 6	g. j	jdbc/MyD	B)

Enter the JNDI resource name to be used.



- 2. Adjust the Timeout, if needed. Default is 60.
- 3. Query definition and execution can be done, using either the query builder or freeform SQL. To use the query builder, select the **Query Builder** tab. Otherwise, proceed to step 6.


The Use Query Builder option is turned on by default.



- 3.1. Select the appropriate *SQL Dialect* in the drop-down list to be able to generate the correct *SQL* for the required data repository.
- 3.2. In the *Table* field, click Load to populate the drop-down list with tables. Select a table.

The SQL query is generated and displayed in the Preview Query text box.

Also, expanding the Join Tables displays the list of tables that you can join.



You can also opt to select other common fields.

The SQL query is generated and displayed in the Preview Query text box.

Join Table	Left Column	Right Column	
✓ public.forex	forex	▼ forex	
☐ public.industry		▼	
Generate Columns			
Column	Parameterize	Aggregate	
Date Time	▼ or	<u>*</u> +	
Constrain By Date Time From	То		
	ks" LEFT JOIN "public"."forex"	on "stocks"."forex" = "forex"	."forex
1 SELECT * FROM ("public"."stoc	ks" LEFT JOIN "public"."forex" ne columns populate the Outpu		."forex
1 SELECT * FROM ("public"."stoc			."forex
1 SELECT * FROM ("public", "stoc Generate Columns The	ne columns populate the <i>Outp</i> o	ut Column section.	."forex
1 SELECT * FROM ("public", "stoc Generate Columns Click Generate Columns Column	ne columns populate the <i>Outp</i> o	ut Column section.	."forex
1 SELECT * FROM ("public"."stoc Click Generate Columns Column stocks.id	ne columns populate the <i>Outp</i> o	ut Column section. Aggregate Sum	."forex
1 SELECT * FROM ("public"."stoc Click Generate Columns Column stocks.id stocks.region stocks.country stocks.forex	ne columns populate the <i>Outp</i> o	Aggregate Sum Group By	."forex
1 SELECT * FROM ("public", "stoc Click Generate Columns Column stocks.id stocks.region stocks.country	ne columns populate the <i>Outp</i> o	Aggregate Sum Group By Group By	."forex

3.5. Individual columns can be added by checking the corresponding *Column* box in the *Output Column* listing. To select all of the columns, check the topmost box.

The SQL query is generated and displayed in the Preview Query text box.

- 3.6. If the data returned is to be aggregated, then the **Aggregate** box should be checked. For each selected column, the possible aggregation methods are listed including:
 - Text Columns: Count, Group By
 - Date Columns: Count, Group By
 - Numeric Columns: Sum, Count, Min, Max, Group By
- 3.7. Check the **Parameterize** box and match the parameter to the appropriate column. By default, they will be matched by name.

The appropriate SQL Query is updated in the *Preview Query* text box.


3.8. If the data is to be filtered or aggregated on Date/Times, then a valid Date Time field needs to be selected from either a single Date/Time field, or a compound column created from a selected Date and a selected Time column.

3.9. Check the **Constrain by Date Time** box and enter *From* and *To* Date/Time constraints that are assumed to be in this time zone for incorporation into the query.


Date Time

If the query is to filter/constrain the results on Date/Time, the constrain sections are completed.


4. To use freeform SQL, select the **SQL** tab and turn on **Use SQL** toggle button.



4.1. Modify the SQL-like query language in the *User Query* text box.



5. Select the Advanced tab.



Set the following properties, if needed:

Property	Description
Use data modification query	Signals that the table is created for writing data. This property is also used for filtering out target data tables for further data update action configuration
Enable <u>on-demand</u> <u>queries</u>	On-demand queries provide ROLAP functionality to the Altair Visual Data Discovery products, where the aggregation and filtering tasks are largely offloaded to the underlying data repository.

You can opt to define the **Show in Timezone** and **Source Timezone** settings.




Connector for Kx kdb+

The Kx kdb+ input data source allows connection to the Kx kdb+ databases on a polled basis.

Steps:

1. Click Connection Settings to expand and display the properties you can set.



2. Enter or set the following properties:

Property	Description
Host	Kx kdb+ host address.
Port	Kx kdb+ host port. Default is 5001 .
TLS Enabled	Ensure to check if you have started q with TLS only.
User Id	The user Id that will be used to connect to Kx kdb+.
Password	The password that will be used to connect to Kx kdb+.
Timeout	The length of time to wait for the server response in seconds. Default is 30.
Retry Count	Number of connection attempts to be done that can be used for busy Kx kdb+ servers. Default is 0 .

NOTE Host, Port, User Id, and Password can be parameterized.	
--	--


- 3. Check/uncheck the **Enable on-demand queries** box. See On-Demand Queries for more information.
- 4. You can opt to define the Show in Timezone and Source Timezone settings.



5. Check the **Constrain by Date Time** box and enter *From* and *To* Date/Time constraints that are assumed to be in this time zone for incorporation into the query.

If the query is to filter/constrain the results on Date/Time, the constrain sections are completed.

6. When **Table** is selected, the section below is enabled:



You can either:

- Click and select a namespace from the list of all root level namespaces. By default, the selected namespace will be root (backtick `).
- For nested namespaces, enter them in the Namespace box (e.g., panopticon.test) to get the tables
 that were created under these namespaces.
- 7. On the *Table* field, click Load to populate the drop-down list with tables and views. Select a table or view.
- 8. Click Generate Columns

 The columns of the selected table or view populates the Output Column section.
- 9. Individual columns can be added by checking the corresponding Column box in the Output Column listing.
- 10. If the data returned is to be aggregated, then the *Aggregate* checkbox should be selected. For each selected column, the possible aggregation methods are listed including:
 - Text Columns: Group By
 - Date Columns: Count, Min, Max, Group By
 - Numeric Columns: Sum, Count, Min, Max, Group By
 In addition, the qSQL query is generated and displayed on the Query text box.
- 11. Check the *Parameterize* checkbox and match the parameter to the appropriate column. By default, they will be matched by name.

The appropriate qSQL query is updated on the Query text box.

12. If the data is to be filtered or aggregated on Date/Times, then a valid *Date Time* field needs to be selected from either a single Date/Time field, or a compound column created from a selected *Date* and a selected *Time* column.

Date Time or +

13. In kdb+, you can modify the query to regroup the aggregated data per time units (i.e., Seconds, Minutes, Hours, Date, Week, Month). Check the **Period** box, enter the time duration and click the time unit.



14. Enter a qSQL query language into the Query text box.

If a parameter has been defined, the qSQL entry can refer to it.

15. Select the Flatten List Limit.

This allows retrieval of the first 'n' items in the list and produce new columns in the output schema with a dot notation.

For example, if there are two nested fields (BidPrices and OfferPrices) and the flatten list limit selected is five, then the output schema will be:

BidPrices.1, BidPrices.2, BidPrices.3, BidPrices.4, BidPrices.5, OfferPrices.1, OfferPrices.2, OfferPrices.3, OfferPrices.4, OfferPrices.5

If there are less than five items in the list, then the values will be null.

NOTE

Currently, this feature works for the Service subscription type. Also, it only flattens numeric columns.

- 16. Check Pass to function box to activate a connection to a server using a proxy. Enter the value.
- 17. You may also define a Deferred Sync Query.

On-Demand Queries

The default behavior when using data connectors is to retrieve data into memory for visual analysis to then occur, where the data is aggregated and filtered in memory. This retrieval may be the consumption of a whole dataset, or through the use of parameters, the retrieval of a dynamically selected subset of the data. This approach is however limited by the memory of the machine, and the overhead of retrieving and processing large volumes of data on the desktop.

	ited by the memory of the machine, and the overhead of retrieving and processing large volumes of data on the sktop.
<u>Kx</u>	kdb+ and JDBC Database connectors support on-demand queries.
En	able on-demand queries
	demand queries provide ROLAP functionality to the Panopticon products, where the aggregation and filtering ks are largely offloaded to the underlying data repository.
The	e software will dynamically generate q query for:
	Filter domains (Categorical Listing & Min/Max for Numeric Fields)
	Aggregated & Filtered Data returned in the visualizations
	ch filter and visualization are driven by a separately generated q query, ensuing that each query is simplified, and urns the minimum amount of data.
app	s on-demand capability dramatically reduces the amount of data to be transferred across the network and onto the olication and ensures that the heavy data intensive tasks occur in Kx kdb+ instances. However, when using this de, the following functionality is disabled:
	Percentile Filtering
	Copy Raw Data
	Pivot & Unpivot Data Transforms
	Non-Additive Data support
	Shared selection across visualizations
	Numeric Bucketing
	Date/Time Part Specific Options (Decade, Quarter, Weekday, Millisecond, Nanosecond)
	Ranking
	R Transform
	Python Transform

Kx kdb+ - Deferred Sync Query

The Deferred Sync Query feature allows the Kx kdb+ connector to support synchronous and asynchronous reads. The advantage of using this option is that there is no queue on the Kx kdb+ server side, queries are farmed out to slaves and returned to asynchronous instead.

Deferred Sync Query (use {Query} parameter here as a place holder for the target query
{@[neg .z.w;@[value;x;`\$"failed to run query"];`\$"failed to post back"]}["{Query}"]

Checking the **Deferred Sync Query** box would enable the query box:

✓ Deferred Sync Query (use {Query} parameter here as a place holder for the target query)

{@[neg .z.w;@[value;x;'\$"failed to run query"];'\$"failed to post back"]}["{Query}"]

The {Query} parameter is used as a place holder for the target query that is defined in the *Query* builder.

Host Lookup Settings in the Panopticon.properties File


The Panopticon.properties file located in the AppData folder (i.e., c:\vizserverdata), contains majority of properties for controlling the configuration of Panopticon Real Time. Properties below can be used to control host lookup related settings while the host, port, user, and password information are referred together as host info.

Property	Host Lookup	
Attribute	connector.kdb.host.lookup.script	
Description	Full path of the shell script file that is accessible on the server. When set, before making a new kdb+ connection, this script is executed to get the host info. This property helps in overriding connection details entered inside the kdb+ connector UI centrally, and may help when different authentications are set at kdb+ like Kerberos/Custom etc. The output of this script is expected to be a JSON object like below. { "host": "localhost", "port": 5001, "username": "", "password": "" } NOTE: Starting with the 21.2 release, the the kdb+ connection pool feature of Panopticon (kdb.connection.pool.xx) can be used together with the host lookup. So any new connection request from the pool, will first execute the script set here, to get the host info before the pool is looked up for available connections. Examples: For Windows connector.kdb.host.lookup.script=E://Data/host.bat For Linux connector.kdb.host.lookup.script= /etc/panopticon/appdata/host.sh	
Default Value		
Property	Host Lookup	
Attribute	connector.kdb.host.lookup.script.arguments	
Description	Delimited set of arguments to be passed to the script when it is executed. '{host}, {port}, {userid}, {password}' is the default value, and these parameters are mapped to respective settings in the connector UI i.e., the value entered against these settings in the connector UI are passed as arguments to the script.	

	This property can be extended or updated if you want to pass other data table parameters as arguments. System parameter like { _user_id} or { _workbook_folder}, if added to the data table, can also be used. If the value of some parameter is null or empty at the time of execution of the script, two single quotes are passed (") against that parameter, this is to make sure that arguments count matches the arguments set at this property.
Default Value	{host},{port},{userid},{password}
Property	Host Lookup
Attribute	connector.kdb.host.lookup.script.arguments.delimiter
Description	Used to split the arguments set at above property.
Default Value	,
Property	Host Lookup
Attribute	connector.kdb.host.lookup.script.timeout
Description	The timeout (in milliseconds) to wait for the host lookup script to run and return the host info.
Default Value	5000

Connector for ksqIDB

The ksqlDB connector allows executing ksqlDB pull queries and terminating push queries.



Steps:

1. Enter the following properties:

Property	Description
Server URL	ksqIDB host address.
Username	User Id that will be used to connect to ksqIDB.
Password	Password that will be used to connect to ksqlDB.

- 2. Check the **Collection** box to enable and select either:
 - Stream

Immutable and append-only collections which are useful for representing a series of historical facts. Adding multiple events with the same key allows these events to be appended to the end of the stream.

Table

Mutable collections. Adding multiple events with the same key allows the table to only keep the value for the last key. This collection is helpful in modeling change over time and often used to represent aggregations.

- 3. Click Fetch to populate the drop-down list. Select the collection.
- 4. Enter an SQL-like guery language into the Query box.
- 5. Check the From Beginning box to subscribe from the beginning to the latest messages.

From Beginning

If un-checked, you will only be subscribed to the latest messages.

- 6. Enter the Timeout. Default is 5 (in seconds).
- 7. Select either the dot (.) or comma (,) as the Decimal Separator.
- 8. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the **Save** button is enabled.
- 9. You can also opt to load or save a copy of the column definition.
- 10. Click . A new column entry is displayed. Enter or select the following properties:

Property	Description
Name	The column name of the source schema.
Туре	The data type of the column. Can be a Text , Numeric , or Time
Date Format	The <u>format</u> when the data type is Time .
Enabled	Determines whether the message should be processed.

				_
To delete a column, check its	or all the column entries, check the topmost	\Box	, then click	Τ.

11. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged.

You can opt to define the Show in Timezone and Source Timezone settings.

Connector for Livy Spark

Livy is an open-source REST interface for interacting with Apache Stark. It supports executing snippets of code or programs such as Scala, Python, Java, and R in a Spark context that runs locally or in Apache Hadoop YARN.

The Livy Spark connector allows you to run these codes and fetch the data in Panopticon Real Time.

Steps:

1. Enter or select the following properties:

Property	Description
Host	Livy Spark host address.
User Id	User Id that will be used to connect to Livy Spark.
Password	Password that will be used to connect to Livy Spark.
Kind	Currently, the supported kind of connection to be used is pyspark (Interactive Python Spark session).
Request Timeout	Length of time to wait for the server response. Default is 30.

Polling Count	The number of polling done to the Livy Spark server to check if the status of the app is successful. Default limit is 150 .
Polling Frequency (in seconds)	Frequency of the polling. Default is 2.
Script	The script to use.

Connector for MongoDB


The MongoDB connector is an interface used to import MongoDB's schema-less BSON documents into a table schema that Panopticon can interpret and analyze. It uses many BSON structure types and MongoDB query features.

Steps:


1. Enter the following properties:

Property	Description	
URL	Enter either:	
	localhost if the database resides on the same computer, or	
	 enter the IP address and port of the computer where MongoDB is installed (e.g., 192.168.1.1:27017). If no port is specified, the default is 27017. 	
User Id	The user Id if authorization is enabled for MongoDB.	
Password	The password if authorization is enabled for MongoDB.	
Authentication DB	The database where the user is created (default is admin).	
Database	The database that will be used.	
Collection	The collection that will be used.	

2. To make the Query Document feature of MongoDB available in Panopticon, select **Use Query Document**.



The Connector Settings pane updates to display the settings of this query option.



For the *Method* option, select any of the following values:

Find (Default)

Allows you to fetch a document from a MongoDB collection.

Two more configurable settings are available:

Sort

Provide a JSON object that defines the sort criteria, then set the order to either 1 for ascending or -1 for descending (e.g., {"address.building":1}).

Projection

Provide a JSON object to include or exclude from the result of the Find query.

For example, if a document has 9 documents and you only need to display 5, you can either:

select 5 JSON objects, then set the limit value to 1 to display

```
{"cuisine":1, "grades":1, "restaurant_id":1, "name":1, "borough":1}
```

select 4 JSON objects then set the limit value to 0 to hide

{"address.zipcode":0, "address.coord":0, "address.street":0, "address.building":0}

NOTE

_id field is always displayed while executing the Find method. You can opt to set this field to 0 to hide it (e.g., {"_id":0}).

Aggregate

Allows you to add all the columns generated by aggregation into the schema.


In addition, the MongoDB command line interface displays query operations with a JSON style syntax.

Enter your JSON query document. See http://docs.mongodb.org/manual/tutorial/query-documents/ for more information on the Query Documents feature on MongoDB.

For example, queries from the document look like this: db.inventory.find ({type: "snacks"}). The database and collection are already defined in the UI and the *Find* operation is handled in the code. You only need to enter the JSON query:

```
{"type": "snacks"}
```

For more advanced query, it must include surrounding curly braces as well as matching internal braces.



3. Instead of using **Use Query Document**, select the **Parameterize** query option.



Click **Fetch Parameters** to populate the *Parameter* drop-down and select a value. Then select what column to filter on in the *Filter By* drop-down.

- 4. Select either the dot (.) or comma (,) as the Decimal Separator.
- 5. Select the Data Type Discovery. This property specifies how many rows to fetch from the input data source,

when auto generating the schema after clicking



- 6. You can also opt to load or save a copy of the column definition.
- 7. Click . A new row displays in the JSON list box. Enter the necessary information for each column.

Property	Description	
Name	The column name of the source schema. NOTE: It is recommended to name the column the same as its JSON path fo clarity and uniformity.	
JsonPath	The JsonPath of the source schema.	
Туре	The data type of the column. Can be a Text , Numeric , or Time	
Structure	Used for more advanced features and are covered in the Row-Wise Array Expansion, Column-Wise Array Expansion, and Bson-Wise Array Expansion sections. Value is the default structure and will always display data regardless of actual structure.	

	Structure	
	Value ▼	
	Value Row Expanded Array	
	Column Expanded Array	
	Bson Expanded Array	
Column Count	Enabled when Column-Expanded Array structure is selected.	
	Structure Column Count	
	Column Expanded Ai ▼ 0	
	Enter the number of columns for the plugin to generate as columns for that array.	
Date Format	The <u>format</u> when the data type is Time .	
	To parse and format times with higher than millisecond precision, the format string needs to end with a period followed by sequence of upper case S. There can be no additional characters following them.	[
	For example: yyyy-MM-dd HH:mm:ss.SSSSSS	
Enabled	Determines whether the message field should be processed.	

To delete a column, check its or all the column entries, check the topmost, then click

8. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged.

You can opt to define the **Show in Timezone** and **Source Timezone** settings.

Row-Wise Array Expansion

MongoDB's BSON document structure can store array data types. In order to interpret that data, the user must decide how they want those multi-value fields to be displayed.

Row-wise array expansion takes an array of values and expands them in a single column creating a new row for each value in the array. If there are multiple row-expanded arrays in the same document, then the number of rows generated is equal to the largest array size. Additionally, an *Automatic x-axis* column is automatically generated for use as an x-axis value for visualizations using array data.

To use the row-wise array expansion feature, select Row-Expanded Array from the Structure drop-down box.

This feature will only work for an array data type. If the actual data type in MongoDB is not array or the array is empty, the column will not populate.

Column-Wise Array Expansion

MongoDB's BSON document structure can store array data types. In order to interpret that data, the user must decide how they want those multi-value fields to be displayed.

Column-wise array expansion takes an array of values and expands them into multiple table columns creating a number of columns equal to an array specific number set by the user. If there are multiple column-expanded arrays in the same document, the combined number of new columns is appended to the end of the table with their respective array indices and the original columns are removed.

To use the column-wise expansion feature, select Column-Expanded Array in the Structure drop-down box.

The corresponding *Column Count* text box will be enabled, and the user can enter the number of columns for the plugin to generate as columns for that array.

Bson-Wise Array Expansion

MongoDB's BSON document structure can store array data types. In order to interpret that data, the user must decide how they want those multi-value fields to be displayed.

Bson-wise array expansion allows parsing of all the fields of a nested hierarchy in a sub document of a JSON array. During data retrieval, the column value is converted to JSON, and nested columns are flattened based on a JSON parser logic.

To use the Bson-wise expansion feature, select Bson-Expanded Array in the Structure drop-down box.

Connector for OneTick

The OneTick connector allows connection to OneMarketData OneTick tick history databases on a polled basis. In general, it is used to retrieve conflated time series data sets. The connector supports either:

- Execution of a specified OTQ
- Execution of a specified parameterized OTQ
- Execution of a custom SQL Query

Steps:


- 1. Enter the *Context* (for example, **REMOTE**).
- You can either check:
 - Show Local OTQs box to display the local OTQs in the Selected OTQ drop-down list.
 - Show Remote OTQs box to display the remote OTQs in the Selected OTQ drop-down list.

An OTQ can be specified for execution, or a custom SQL query can be executed, through selection of the appropriate radio button:

- OTQs
- Query
- 3. Click **Load** to populate the *Selected OTQ* drop-down list. Select an OTQ.

The list of input parameters that the OTQ expects is displayed. In addition, the basic SQL query is generated allowing the OTQ to be executed and the input parameters specific to the selected OTQ. The following are generic to all OTQs:

Symbol List



- From
- To

These add additional filter criteria such as symbol, and time window onto the basic OTQ.

- 4. Check the Separate DB Name box to generate a separate field for the database name.
- Check the Show per symbol errors as warnings box to proceed with warnings in the log if symbol errors are returned.
 - The result is a fully generated OneTick SQL query. This can be edited as required.
- 6. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged.
 - You can opt to define the Show in Timezone and Source Timezone settings.

Connector for OneTick Cloud

The OneTick Cloud connector allows access to historic market data with no software dependencies by using the OneTick Cloud and their web API.

Steps:

1. Enter the OneTick Cloud WebAPI URL into the WebAPI URL box with the following form:

```
http://<host>/omdwebapi/rest/?params={"context":"DEFAULT","query_type":"otq",
"otq":"1/12/otq/71b50459-8431-48dc-829f
"s":"20150305130802",
"e":"20150305140805",
"timezone":"America/New_York", "response":"csv",
"compression":"gzip"}
```

Where:

- s, e, timezone the start and end time of the query YYYYMMDDhhmmss form. The timezone used to
 interpret this value is taken from the timezone parameter.
- response the supported response format is csv.
- compression if available, this option enables gzip compression of the results stream. Large data should always be pulled with compression on.
- 2. Enter the *User Id* (email) and *Password* to execute the query and retrieve the data. Note that the *User Id* is case sensitive.
- 3. Enter the time window Start Date and End Date.
- 4. Enter the Symbol List. This value filters the query output with matching symbols.
 - To make it work, ensure to include Symbol in the Query URL. Consequently, the data will be filtered out for the input (Symbols) provided in the Symbol List field.
- 5. Enter the *Symbol Pattern*. This value filters the query output with the data for all the symbols with matching pattern.
 - To make it work, ensure to include Symbol_Pattern in the Query URL. Consequently, the data will be filtered (for all the Symbols) with matching pattern provided in the Symbol Pattern field.
- 6. Select either the dot (.) or comma (,) as the Decimal Separator.
- 7. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the **Save** button is enabled.
- 8. You can also opt to load or save a copy of the column definition.

9. Click . A new column entry is displayed. Enter or select the following properties:

Property	Description
Name	The column name of the source schema.
Column Index	The column index controls the position of a column. Must be >= 0.
Туре	The data type of the column. Can be a Text , Numeric , or Time
Date Format	The <u>format</u> when the data type is Time .
Filter	Defined parameters that can be used as filter.
Enabled	Determines whether the message should be processed.

<u> </u>] ,,, , ,, ,, ,, ,,		_
To delete a column, check its	or all the column entries, check the topmost	, then click	

10. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged.

You can opt to define the **Show in Timezone** and **Source Timezone** settings.

Connector for Panopticon Data Extract


The Panopticon Data Extract connector allows retrieval of data extracts created from non-streaming data sources in Panopticon Real Time.

In cases where there is too much data to retrieve into memory, data extract supports summarization and parameterization, and it can become a more powerful option than a number of underlying data sources.

Steps:

1. Select **Panopticon Data Extract** from the *Connectors* panel. The *Panopticon Data Extract Settings* panel displays with the earliest created data extract (e.g., ExcelExtract).

The list of columns is displayed, with the data type found from inspecting the first 'n' rows of the file.




NOTE

To populate the list of columns, the data extract of a connector must be complete after refreshing the data.


You can also filter the list of columns by entering a text in the Search box.

- 2. You can opt to select another data extract to display its list of columns.
- If the data returned is to be aggregated, then check their Column box. For each selected column, the possible aggregation methods are listed including:
 - Text Columns: Group By
 - Date/Time Columns: Group By
 - Numeric Columns: Sum, Count, Min, Max, Mean



Select the Aggregate method in the drop-down list.

4. If you wish to parameterize a specific column, match the parameter to the appropriate column. By default, they will be matched on name.



5. If only a selected Date/Time range of the table/view is to be queried, check the **Constrain** box, and complete the *From* and *To* text boxes, either with values or with parameters.



Connector for Python

The Python connector allows the retrieval of output data from a Python Pyro (Python Remote Objects) process.

For Python connectivity, Python must be first installed, together with the latest version of Pyro4. In addition, Pyro must be initiated manually or through using the batch file **start_Python_connectivity.bat**.


If the scripts utilize additional modules such as Numpy & Scipy in the shipped example, these also need to be installed into the existing Python installation.

Steps:

1. Enter the following fields:

Field	Description	
Host	Python Pyro instance host address.	
Port	Python Pyro host port. Default is 9090 .	
HMAC Key	Set to password.	

2. Select the Serialization Type: Serpent or Pickle.



- Serpent simple serialization library based on ast.literal eval
- Pickle faster serialization but less secure

Modify the configuration.py file located in ..\Anaconda3\Lib\site-packages\Pyro4 to specify the serialization to be used.

For example, if **Pickle** is selected, self.SERIALIZER value should be changed to **pickle** and self.SERIALIZERS ACCEPTED value should be changed to include **pickle**:

```
def reset(self, useenvironment=True):
       Set default config items.
        If useenvironment is False, won't read environment variables settings
(useful if you can't trust your env).
       self.HOST = "localhost" # don't expose us to the outside world by default
       self.NS HOST = self.HOST
       self.NSPORT = 9090 # tcp
       self.NS_BCPORT = 9091 # udp
       self.NS BCHOST = None
       self.NATHOST = None
       self.NATPORT = 0
       self.COMPRESSION = False
       self.SERVERTYPE = "thread"
       self.COMMTIMEOUT = 0.0
       self.POLLTIMEOUT = 2.0 \# seconds
       self.SOCK REUSE = True # so reuseaddr on server sockets?
       self.SOCK NODELAY = False # tcp nodelay on socket?
       self.THREADING2 = False # use threading2 if available?
       self.ONEWAY THREADED = True # oneway calls run in their own thread
       self.DETAILED TRACEBACK = False
       self.THREADPOOL SIZE = 16
       self.AUTOPROXY = True
       self.MAX MESSAGE SIZE = 0 # 0 = unlimited
       self.BROADCAST ADDRS = "<br/>broadcast>, 0.0.0.0" # comma separated list of
broadcast addresses
       self.FLAME ENABLED = False
       self.PREFER IP VERSION = 4 # 4, 6 or 0 (let OS choose according to RFC
3484)
       self.SERIALIZER = "pickle"
       self.SERIALIZERS ACCEPTED = "pickle, marshal, json" # these are the 'safe'
serializers
        self.LOGWIRE = False # log wire-level messages
        self.PICKLE PROTOCOL VERSION = pickle.HIGHEST PROTOCOL
       self.METADATA = True # get metadata from server on proxy connect
       self.REQUIRE EXPOSE = False # require @expose to make members remotely
accessible (if False, everything is accessible)
       self.USE_MSG_WAITALL = hasattr(socket, "MSG_WAITALL") and platform.system()
                # not reliable on windows even though it is defined
!= "Windows"
       self.JSON MODULE = "json"
       self.MAX RETRIES = 0
```

NOTE

The Host, Port, HMAC Key, and Serialization Type fields will be hidden if their corresponding properties are set in the Panopticon properties file.

Field	Corresponding Property in Panopticon.properies
Host	connector.python.host
Port	connector.python.port
HMAC Key	connector.python.password
Serialization Type	connector.python.serializertype

3. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged.

You can opt to define the Show in Timezone and Source Timezone settings.

- 4. Enter the required *Python script* to execute on the active Pyro instance.
- 5. Check the **Use Apache Arrow** box to enable fast serialization of data frames.
- 6. Select whether the parameters should be automatically enclosed in quotes by checking the **Enclose parameters** in quotes box.

Connector for Rserve

The Rserve connector allows the retrieval of an output data frame from a running Rserve process.

For R connectivity, R must be first installed, together with the Rserve library. In addition, R must be open, and the Rserve library must be loaded and initialized.

Steps:

1. Enter the following properties:

Property	Description	
Host	Rserve host address. Default is localhost .	
Port	Rserve host port. Default is 6311 .	
User Id	The user Id that will be used to connect to the Rserve service.	
Password	The password that will be used to connect to the Rserve service.	

NOTE	The Host, Port, User Id, and Password fields will be hidden if their corresponding properties are set in the Panopticon.properties file.		
	Field	Corresponding Property in Panopticon.properies	
	Host	connector.rserve.host	
	Port	connector.rserve.port	
	User Id	connector.rserve.userid	
	Password	connector.rserve.password	

- 2. Enter the required *R Script* to execute on the active Rserve instance.
- 3. Enter the Timeout. Default is 10 (in seconds).
- 4. Select whether the parameters should be automatically enclosed in quotes by checking the **Enclose parameters** in quotes box.
- 5. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged. You can opt to define the *Show in Timezone* and *Source Timezone* settings.

Connector for Shakti (Beta)

The Shakti connector allows connecting to Shakti databases on a polled basis.

Steps:

1. Enter the following properties:

Property	Description	
Host	Shakti host address.	
Port	Shakti host port. Default is 9999.	

- 2. Enter a free text Query.
- 3. Adjust the *Timeout*, if needed. Default is **5** (in seconds).

Connector for Splunk

The Splunk connector allows the retrieval of data from a Splunk instance.

Steps:

1. Enter the following properties:

Property	Description
Host	Splunk host address.
Port	Splunk host port. Default is 8089.
User Id	The user Id that will be used to connect to the Splunk service.
Password	The password that will be used to connect to the Splunk service.

- 2. Select the Search Type:
- Manual

Proceed to step 6 to define a new search query.

Saved Search

Allows you to select in the Saved Search drop-down list.

- 3. Click Fetch Applications to populate the *Application* drop-down list and select one.
- 4. Select whether the parameters should be automatically enclosed in quotes by checking the **Enclose** parameters in quotes box.
- 5. Enter a Search Query.

STREAMING DATA SOURCES

Connector for ActiveMQ

Allows connection to Apache's ActiveMQ message bus on a real-time streaming basis. Specifically, the connector allows Panopticon to subscribe to XML, JSON or FIX based messages that are published on topics. The data format itself is arbitrary, and consequently, the connection includes the message definition.

Steps:

1. Enter the following information:

Property	Description
Broker	The location of the message broker. Default is tcp://localhost:61616.
User Id	The user Id that will be used to connect to the ActiveMQ service.
Password	The password to connect to the ActiveMQ service.
Topic	Accepts topic in topic://topicname.* format and also topicname.*. Therefore, topic://pano.> and pano.> both will work as topic value. Default is topic://topicname.*

2. Check/uncheck the Use durable subscription box.



When connecting to a message bus, it is recommended to disable durable messaging. When it is enabled, this puts a heavier load to the server, and slows down the start and stop of subscriptions.

- 3. Check/uncheck Messages can contain partial data box.
- 4. Select the Message Type.
- 5. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the **Save** button is enabled.

This also populates the *Id column* with the set of columns, of arbitrary type, that can be concatenated to form a unique row identifier.

- 6. You can also opt to load or save a copy of the column definition.
- 7. Click to add columns to the MQ connection that represent sections of the message. Then enter or select:

Property	Description	
Name	The column name of the source schema.	
Fix Tag/JsonPath/Text Column Index/XPath	The Fix Tag/JsonPath/Text Column Index/XPath of the source schema.	
Туре	The data type of the column. Can be a Text , Numeric , or Time	
Date Format	The <u>format</u> when the data type is Time .	
Enabled	Determines whether the message field should be processed.	
Filter	Defined parameters that can be used as filter. Only available for JSON, Text, and XML message types.	

N I	_	_	_
MI	()		_


To parse and format times with higher than millisecond precision, the format string needs to end with a period followed by sequence of upper case S. There can be no additional characters following them.

For example: yyyy-MM-dd HH:mm:ss.SSSSSS

To delete a column, check its \Box or all the column entries, check the topmost \Box , then click $\overline{}$.

- 8. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged. You can opt to define the <u>Show in Timezone and Source Timezone</u> settings.
- 9. For this section:

Real-Time Settings



Refer to **Define Real-Time Settings** for more information.

Connector for Amazon Kinesis - Data Streams

The Amazon Kinesis – Data Streams connector reads records from the given data stream and Shard ID.

Steps:

- 1. Do one of the following:
 - Check the Use Default Credentials Chain box to use the default Access Key ID and Secret Key Access, or
 - Uncheck the Use Default Credentials Chain box and enter the Access Key ID and Secret Key Access.


Use Default Credentials Chain	
Access Key Id	
Secret Access Key	

NOTE

The Access Key ID and Secret Key Access from the AWS account can be configured in three places:


- Two properties at the Panopticon.properties file which is available in the AppData folder of Panopticon Real Time
 - o connector.kinesis.datastreams.accesskeyid
 - connector.kinesis.datastreams.secretaccesskey

If this configuration is used, the Use Default Credentials Chain box is not displayed in the connector UI.



This is the recommended way to provide the credentials.

- AWS credentials provider chain
 - Environment Variables AWS_ACCESS_KEY_ID and AWS_SECRET_ACCESS_KEY
 - Credential profiles file at the default location ~/.aws/credentials on Linux, macOS, or Unix, and C:\Users\USERNAME\.aws\credentials on Windows.



2. Select or define the following properties:

Property	Description
Region	Physical location of the data center. The list is picked up from the <u>Amazon Kinesis Data Streams Endpoints and Quotas</u> page.
Stream	Name of the stream from where you want to pull the data. Click Fetch Streams to load all of the available streams from the AWS account.
Shard Id	Each connector instance or data source is connected to only one shard. Click Fetch Shards to pull all of the shards from the selected stream.
From Beginning	The starting position in the data stream from which to start streaming. Default value is unchecked, which means LATEST. When checked, the starting position is set to TRIM_HORIZON .

NOTE All of the connection settings can be parameterized.

- 3. Select the Message Type.
- 4. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the **Save** button is enabled.

This also populates the *Id Column* with the set of columns, of arbitrary type, that can be concatenated to form a unique row identifier.

- 5. You can also opt to <u>load or save</u> a copy of the column definition.
- 6. Click to add columns to the Amazon Kinesis Data Streams connection that represent sections of the message. Then enter or select:

Property	Description
Name	The column name of the source schema.
Fix Tag/JsonPath/Text Column Index/XPath	The Fix Tag/JsonPath/Text Column Index/XPath of the source schema.
Туре	The data type of the column. Can be a Text, Numeric, or Time
Date Format	The format when the data type is Time .
Enabled	Determines whether the message field should be processed.
Filter	Defined parameters that can be used as filter. Only available for JSON, Text, and XML message types.

NOTE


To parse and format times with higher than millisecond precision, the format string needs to end with a period followed by sequence of upper case S. There can be no additional characters following them.

For example: yyyy-MM-dd HH:mm:ss.SSSSSS

					_
To delete a column, of	check its 🗀	or all the column entries,	check the topmost	, then click	

- 7. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged. You can opt to define the <u>Show in Timezone and Source Timezone</u> settings.
- 8. For this section:

Real-Time Settings



Refer to **Define Real-Time Settings** for more information.

Connector for AMPS

The AMPS connector allows connection to AMPS message bus on a real-time streaming basis. The connector allows Panopticon to subscribe to the Native FIX and XML message support. The data format itself is arbitrary, and in turn the connection includes the message definition.

Steps:

1. Enter the following information:

Property	Description
Host	AMPS host address.
Port	AMPS host port. Default is 9004.
User Id	The user Id that will be used to connect to the AMPS service.
Password	The password to connect to the AMPS service.
Topic	The topic or queue physical name.
Filter	The filter expression.

- 2. Select the *Protocol*. This will specify the format of the headers:
 - Amps (default)
 - Fix
 - NvFix
 - XML
- 3. Select the Message Type. This will specify the format of the data within the message:
 - Fix (default)
 - XML

- NvFix
- JSON

If JSON is selected, the Record Path field is displayed.

Record Path (eq. myroot.items.item)

Enter the record path which allows the identification of multiple records within the JSON document (e.g., myroot.items.item).

- 4. Select from any of the following Subscription Modes:
 - Sow
 - SowAndSubscribe
 - SowAndDeltaSubscribe (default)
 - Subscribe
 - DeltaSubcribe
- 5. Enter the *Order By Statement* in order to limit the returned data. For example:

/orderDate DESC

/custumerName ASC

- 6. Enter any of the following Option/s for the selected Subscription Mode:
 - cancel
 - live
 - no_empties
 - null
 - no_sowkey
 - oof
 - pause
 - replace
 - resume
 - send_keys
 - timestamp

NOTE


Leave the Options box blank if you selected the Subscribe subscription mode.

- 7. Enter the *Batch Size*. This is the number of messages that will be sent at a time as results are returned. Default is **100**.
- 8. Enter the Timeout for the length of time to wait for the server response. Default is 5000.
- 9. Select either the dot (.) or comma (,) as the Decimal Separator.
- 10. Click to the fetch the schema based on the connection details. This populates the list of columns with the data type found from inspecting the first 'n' rows of the input data source.

This also populates the *Id Column* with the set of columns, of arbitrary type, that can be concatenated to form a unique row identifier.

- 11. Click to add columns to the AMPS connection that will represent sections of the message.
- 12. Provide the following information:

Property	Description
Name	The column name of the source schema.
Fix Tag/XPath/Json Path	The Fix Tag/XPath/Json Path of the source schema.
Туре	The data type of the column. Can be a Text, Numeric, or Time
Date Format	The <u>format</u> when the data type is Time.
Filter	Defined parameters that can be used as filter. Only available for Fix, JSON, and XML message types.
Enabled	Determines whether the message field should be processed.



13. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged. You can opt to define the *Show in Timezone* and *Source Timezone* settings.

To delete a column, check its or all the column entries, check the topmost, then click.

14. For this section:

Real-Time Settings Id Column id ¥ [No Time Id] Time Id Column Time Id Column Name None Time Id Barring Time Window (s) 1000 Real-time Limit (ms) Persistent Server Subscription Add Last Update Time and Age Reset Data on

Refer to **Define Real-Time Settings** for more information.

Connector for DolphinDB - Streaming

The DolphinDB streaming connector allows you to connect and subscribe streaming data using DolphinDB Java Streaming API.

Steps:

Reconnect

1. Enter the following information:

Property	Description
Host	DolphinDB - Streaming host address.
Port	DolphinDB - Streaming host port. Default is 8848.
User Id	The user ld that will be used to connect to the DolphinDB - Streaming service.
Password	The password to connect to the DolphinDB - Streaming service. Check the <i>Show Characters</i> box to display the entered password characters.
Table	Table to subscribe against.

2.	Check the From	Beginning box to	subscribe from the	e beginning to the	latest messages.

From Beginning

If un-checked, you will only be subscribed to the latest messages.

3. Click **Fetch Schema** to retrieve the schema of the configured subscription.

This also populates the *Id Column* with the set of columns, of arbitrary type, that can be concatenated to form a unique row identifier.

- 4. You can opt to define the Show in Timezone and Source Timezone settings.
- 5. For this section:

Real-Time Settings

Id Column	id ¥	
Time Id Column	[No Time Id]	*
Time Id Column Name		
Time Id Barring	None	w
Time Window (s)	0	
Real-time Limit (ms)	1000	
Persistent Server Subscription		
Add Last Update Time and Age		
Reset Data on Reconnect		

Refer to <u>Define Real-Time Settings</u> for more information.

Connector for Google Cloud Pub/Sub

The Google Cloud Pub/Sub connector allows connection to Google Cloud Pub/Sub's message bus on a real-time streaming basis. Specifically, the connector allows Panopticon to subscribe to XML, JSON, TEXT or FIX based messages that are published on particular topics. The data format itself is arbitrary, and consequently, the connection includes the message definition.

Steps:

1. Enter the Service Account Credential JSON Text with the generated JSON key (contains the private key) in the following format:

```
{
  "type": "service_account",
  "project_id": "project-id",
  "private_key_id": "some_number",
  "private_key": "----BEGIN PRIVATE KEY----\n...
  =\n----END PRIVATE KEY----\n",
  "client_email": "<api-name>api@project-id.iam.gserviceaccount.com",
  "client_id": "...",
  "auth_uri": "https://accounts.google.com/o/oauth2/auth",
  "token_uri": "https://accounts.google.com/o/oauth2/token",
  "auth_provider_x509_cert_url":
  "https://www.googleapis.com/oauth2/v1/certs",
  "client_x509_cert_url": "https://www.googleapis.com/...<api-name>api%40project-id.iam.gserviceaccount.com"
}
```

NOTE

Ensure that when parameterizing the values in the Credential JSON Text, there is no white space as a single line content.

2. Click to populate the *Topic* drop-down list. Initially, the first topic in the list is displayed in the *Topic* drop-down box.

Select a topic.

3. Click Fetch to populate the Subscription Name drop-down list and select a subscription name.

You can also opt to create a subscription by manually entering the value into the Subscription Name list box.

A subscription name will be automatically generated when it is not entered or selected in the drop-down list. This subscription will be created for connection and will be deleted as soon as its work is done. For example, when starting a presentation mode, a subscription will be created. Upon quitting the presentation mode, the subscription will then be deleted. Pub/Sub can automatically delete inactive subscriptions. This can be done by configuring the minimum required time of inactivity to schedule a subscription for deletion. This time must be longer than the message retention duration.

- 4. Select the *Message Type*.
- 5. Select either the dot (.) or comma (,) as the Decimal Separator.
- 6. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the **Save** button is enabled.

This also populates the *Id Column* with the set of columns, of arbitrary type, that can be concatenated to form a unique row identifier.

- 7. You can also opt to load or save a copy of the column definition.
- 8. Click to add columns to the Google Cloud Pub/Sub connection that will represent sections of the message.
- 9. Provide the following information:

Property	Description
Name	The column name of the source schema.
Fix Tag/XPath/Column Index/Json Path	The Fix Tag/XPath/Column Index/Json Path of the source schema.
Туре	The data type of the column. Can be a Text , Numeric , or Time
Date Format	The format when the data type is Time .
Enabled	Determines whether the message field should be processed.

To delete a column, check its \Box or all the column entries, check the topmost \Box , then click $\overline{}$.

10. Google Cloud Pub/Sub messages can have additional metadata as custom attributes.

Panopticon Google Cloud Pub/Sub connector supports reading these attributes as column values. The generate column logic automatically checks and generates attribute columns if messages received contain attributes.

Additionally, like columns from message data, you can manually add them by clicking . A new entry displays.



Name can be any unique column name within the data source. The attribute name must match to an attribute name in message otherwise it will be treated as null value. Currently all attribute columns are treated as Text columns, we can't change column type.


Check the Enabled box to enable an attribute column.

To delete an attribute column, check its \Box or all the column entries, check the topmost \Box , then click $\overline{}$.

11. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged.

You can opt to define the Show in Timezone and Source Timezone settings.

12. For this section:



Refer to <u>Define Real-Time Settings</u> for more information.

Connector for JDBC Database – Streaming


The JDBC Database -Streaming connector allows subscription to a set of data, upserting existing received values in a JDBC SQL Database, by running micro batched queries.

The database must have the appropriate JDBC driver .jar files and JNDI connections.

Refer to the *Database* section in the *Panopticon Real Time Installation and Troubleshooting Guide* for more information.

Steps:

- 1. You can either select:
 - JNDI Name



Enter the *URL* specific to the database's JDBC driver, the *Driver Class Name* specific to the driver, and the *User Id* and *Password*.

Show characters

Check the **Show Characters** box to display the entered characters.

- 2. Enter the *Timeout* or the length of time to wait for the server response. Default is **60**.
- 3. Enter the Query, which can contain parameters in a similar manner to the database connector.
- Select whether the parameters should be automatically enclosed in quotes, by checking the Enclose parameters in quotes box.
- 5. Click Fetch Schema to retrieve the schema of the configured subscription.

This also populates the *Id Column* with the set of columns, of arbitrary type, that can be concatenated to form a unique row identifier.

- 6. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged.
 - You can opt to define the **Show in Timezone** and **Source Timezone** settings.
- 7. For this section:

Driver Class Name

User Id


Password

Real-Time Settings Id Column id ¥ [No Time Id] Time Id Column Time Id Column Name None Time Id Barring Time Window (s) 1000 Real-time Limit (ms) Persistent Server Subscription Add Last Update Time and Age Reset Data on Reconnect

Refer to **Define Real-Time Settings** for more information.

Connector for Apache Kafka

Allows Panopticon to subscribe to Kafka topics on an external cluster.



Steps:

1. Enter the connection details:

Property	Description
Bootstrap Server	List of host/port pairs of Kafka servers used to bootstrap connections to a Kafka cluster.
	By default, the value is localhost: 9092. However, this can be overridden by specifying another bootstrap server in the <i>External Settings</i> text box (as specified in step 4).
Schema Registry Host	Where the Schema Registry is located. This can be in a different location from the Kafka cluster.
Schema Registry Port	The port number of the schema registry which provides the serving layer for the metadata. Default is 8081 .

2. Enter the *External Settings* to support authentication (i.e., username and password). Note that if the bootstrap server is not secure, then there is no need to authenticate, and you may leave this text box blank.

Below is an example of system settings for an SASL authentication:


```
bootstrap.servers=localhost:9093
sasl.jaas.config=\
  org.apache.kafka.common.security.plain.PlainLoginModule
required \
    username="dwchuser" \
    password="dwchpwd";
```

Fetch Topics


3. Click

The first topic in the *Topic* drop-down list is selected and the schema is displayed.

By default, the Hide Internal Topics toggle button is enabled, and the Avro message type is selected.



Tap the slider to turn it off. The internal Kafka topics are also displayed in the drop-down list.



4. Click the drop-down list to search and select the desired topic.

For non-Avro topics, select the Message Type: Fix, JSON, Text, XML, or Protobuf.

 If Text is selected, confirm the Decimal Separator, Text Qualifier, Column Delimiter, and if the first row of the message includes column headings.



Column Index controls the position of a column, Must be >= 0.


Property	Description
Text Qualifier	Specifies if fields are enclosed by text qualifiers, and if present to ignore any column delimiters within these text qualifiers.
Column Delimiter	Specifies the column delimiter to be used when parsing the text file.
First Row Headings	Determines if the first row should specify the retrieved column headings, and not be used in data discovery.

 If JSON is selected, enter the Record Path which allows the identification of multiple records within the JSON document (e.g., myroot.items.item).



Property	Description
Record Path	The record path that will be queried by the connector's path (e.g., myroot.items.item).

If Protobuf is selected, confirm the Decimal Separator, and enter the Schema Name and Type Name.



Property	Description
Schema Name	The Protobuf schema.
Type Name	The message of Protobuf type that will be sent to Kafka.
File Descriptor	The FileDescriptorSet which: • is an output of the protocol compiler. • represents a set of .proto files, using thedescriptor_set_out option.

- 5. Check the From Beginning box to subscribe from the beginning to the latest messages.
 - If un-checked, you will only be subscribed to the latest messages.
- 6. Select either the dot (.) or comma (,) as the Decimal Separator.

NOTE Prepend 'default:' for the elements falling under default namespace.

7. Click to fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the **Save** button is enabled.

This also populates the *Id Column* with the set of columns, of arbitrary type, that can be concatenated to form a unique row identifier.

- 8. You can also opt to <u>load or save</u> a copy of the column definition.
- 9. For non-Avro message types, except **Protobuf**, click to add columns to the Kafka connection that represent sections of the message. Then enter or select:

Property	Description
Name	The column name of the source schema.
Fix Tag/JsonPath/Text Column Index/XPath	The Fix Tag/JsonPath/Text Column Index/XPath of the source schema.
Туре	The data type of the column. Can be a Text , Numeric , or Time
Date Format	The <u>format</u> when the data type is Time .
Filter	Defined parameters that can be used as filter. Only available for Avro, JSON, Text, and XML message types.
Enabled	Determines whether the message field should be processed.

NOTE

To parse and format times with higher than millisecond precision, the format string needs to end with a period followed by sequence of upper case S. There can be no additional characters following them.


For example: yyyy-MM-dd HH:mm:ss.SSSSSS

8. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged.

You can opt to define the Show in Timezone and Source Timezone settings.

9. For this section:

Real-Time Settings



Refer to **Define Real-Time Settings** for more information.

Connector for Kafka Publisher

The Kafka Publisher connector allows a tuple to be published to a Kafka topic.

Steps:

1. Enter the following properties:

Property	Description
Bootstrap Server	List of host/port pairs of Kafka servers used to bootstrap connections to a Kafka cluster.
	By default, the value is localhost: 9092. However, this can be overridden by specifying another bootstrap server in the <i>External Settings</i> text box.
Schema Registry Host	Where the Schema Registry is located. This can be in a different location from the Kafka cluster.
Schema Registry Port	The port number of the schema registry which provides the serving layer for the metadata. Default is 8081 .

2. To support authentication (i.e., username and password), enter the system settings in the *External Settings* box.

NOTE If the bootstrap server is not secure, then there is no need to authenticate, and you may leave the *External Settings* blank.

Below is an example of system settings for an SASL authentication:

```
bootstrap.servers=localhost:9093
sasl.jaas.config=\
  org.apache.kafka.common.security.plain.PlainLoginModule
required \
    username="dwchuser" \
    password="dwchpwd";
```

3. Click Fetch Topics

to populate the drop-down list and select a Topic.

NOTE

- Ensure that the ability to ping is enabled in the ZooKeeper Host.
 Otherwise, if ping is disabled, the Fetch Topics button will not be able to populate the list of topics and you need to manually enter the topic names.
- For Avro format messages, make sure to select an output topic. This
 populates the list of columns, with the data type found from inspecting
 the first 'n' rows of the file.
- 4. For non-Avro format messages, select **Json** in the *Message Composer* drop-down list box.
- 5. Check the *Use Schema Registry box* to support Avro and JSON serialization formats.
- 6. Enter the *Timeout* or the length of time to wait for the server response. Default is 5 (in seconds).
- 7. Click to add columns to the Kafka connection that represent sections of the message.
- 8. Then enter or select:
 - Name
 - Type (Numeric, Text, or Date/Time)
 - Value (can either be a parameter or data entry that can be used as a publish value)

To delete a column, check its	or all the column entries, check the topmost	, then click	-
•	, ,	,	

Connector for Kx kdb+tick

The Kx kdb+tick input data source allows connection to a Kx kdb+ticker plant on a real-time streaming basis.

Specifically, it allows Panopticon to subscribe to Kx kdb+tick through the definition of *Service*, *Table*, *Symbol*, or directly through *Functional Subscription*.

Steps:

1. Enter the following properties:

Property	Description
Host	Kx kdb+tick host address.
Port	Kx kdb+tick host port. Default is 5010 .
TLS Enabled	Ensure to check if you have started q with TLS only.

User Id	The user Id that will be used to connect to Kx kdb+tick.
Password	The password that will be used to connect to Kx kdb+tick.
Timeout	The length of time to wait for the server response in seconds. Default is 10.

- 2. Select either Subscription Type:
 - Service

Enter the following properties:

Subscription Name (e.g., .u.sub)

NOTE

Instead of entering the table and symbol to subscribe against in the *Table and Symbol text* boxes, you can specify the full subscription syntax in the *Subscription Name* text box. For example:

.u.sub[`table;`symbol]

To subscribe to the trade table and AAPL, AIG, and DOW symbols, enter this in the *Subscription Name* text box:

.u.sub[`trade;`AAPL`AIG`DOW]

• Table to subscribe against (e.g., **trade**)

NOTE

- You may use just a back tick for the table name, intending to subscribe to all available tables.
- When a table name is not entered in the Table text box, then the Symbol text box is disabled meaning it will not be used while doing subscription.
- Symbol to subscribe against (e.g., AAPL)

NOTE

Multiple symbols should be separated by a comma.

- Functional Subscription
 - Enter the functional subscription that needs to be issued (e.g., .u.sub['trade;'])
- 3. Click **Fetch Schema** to retrieve the schema of the configured subscription.

This also populates the *Id Column* with the set of columns, of arbitrary type, that can be concatenated to form a unique row identifier.

4. Check *Constrain subscription to matching symbols* to select the column which contains specific symbols. Otherwise, the filtering against these symbols will not take place.

NOTE

The Constrain subscription to matching symbols only lists sym fields. Therefore, if you select a non sym type in the *Id Column*, it is not recommended to select the default value [Id Column] in the Constrain subscription to matching symbols drop-down list.

- 5. Activate or deactivate *Initialize with historic data*. If unchecked, the data source will only be populated with streaming updates that are subscribed against. If checked, the data source is first initialized against a store of data, after which subscribed streaming updates are then applied.
- 6. Enter the following information:
 - Host
 - Port
 - User Id
 - Password
 - Timeout
 - Query

These entries can be parameterized.

7. Check *Deferred Sync Query* box to allow the Kxkdb+tick data source to support synchronous and asynchronous reads. The advantage of using this option is that there is no queue on the Kx kdb+tick server side, queries are farmed out to slaves and returned to asynchronous instead.

The {Query} parameter is used as a place holder for the target query that is defined in the Query builder.

10. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged.

You can opt to define the Show in Timezone and Source Timezone settings.

12. Select the Flatten List Limit.

This allows retrieval of the first 'n' items in the list and produce new columns in the output schema with a dot notation.

For example, if there are two nested fields (BidPrices and OfferPrices) and the flatten list limit selected is five, then the output schema will be:

BidPrices.1, BidPrices.2, BidPrices.3, BidPrices.4, BidPrices.5, OfferPrices.1, OfferPrices.2, OfferPrices.3, OfferPrices.4, OfferPrices.5


If there are less than five items in the list, then the values will be null.

NOTE

Currently, this feature works for the Service subscription type. Also, it only flattens numeric columns.

13. For this section:

Real-Time Settings



Refer to **Define Real-Time Settings** for more information.

Connector for ksqIDB - Streaming

The ksqlDB - Streaming connector allows executing ksqlDB push queries.

Steps:

Enter the following properties:

Property	Description
Server URL	ksqIDB - Streaming host address.
Username	User Id that will be used to connect to ksqlDB - Streaming.
Password	Password that will be used to connect to ksqlDB - Streaming.

- 2. Check the Collection box to enable and select either:
 - Stream

Immutable and append-only collections which are useful for representing a series of historical facts. Adding multiple events with the same key allows these events to be appended to the end of the stream.

Table

Mutable collections. Adding multiple events with the same key allows the table to only keep the value for the last key. This collection is helpful in modeling change over time and often used to represent aggregations.

- 3. Click Fetch to populate the drop-down list. Select the collection.
- 4. Enter an SQL-like query language into the Query box.
- 5. Check the From Beginning box to subscribe from the beginning to the latest messages.

From Beginning

If un-checked, you will only be subscribed to the latest messages.

- 6. Enter the *Timeout*. Default is **5** (in seconds).
- 7. Select either the dot (.) or comma (,) as the Decimal Separator.
- 8. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the **Save** button is enabled.

This also populates the *Id Column* with the set of columns, of arbitrary type, that can be concatenated to form a unique row identifier.

- 9. You can also opt to load or save a copy of the column definition.
- 10. Click . A new column entry is displayed. Enter or select the following properties:

Property	Description
Name	The column name of the source schema.
Туре	The data type of the column. Can be a Text , Numeric , or Time
Date Format	The <u>format</u> when the data type is Time .
Enabled	Determines whether the message should be processed.


To delete a column, check its or all the column entries, check the topmost, then click.

11. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged.

You can opt to define the Show in Timezone and Source Timezone settings.

12. For this section:

Real-Time Settings



Refer to **Define Real-Time Settings** for more information.

Connector for MQTT

The MQTT connector allows:

- connection to MQTT's message bus on a real-time streaming basis.
- □ Panopticon to subscribe to FIX, JSON, Text or XML based messages that are published on particular topics. The data format itself is arbitrary, and consequently, the connection includes the message definition.
- encrypted/SSL connections using a generated CA certificate file.

Steps:

1. Enter the following properties:

Property	Description		
Broker URL	The location of the message broker. Default is tcp://localhost:1883		
Topic	The topic or the queue physical name. Example: level1/level2/level3/level4 etc. NOTES: You can also opt to use a wild card in the topic name specification. The plus sign symbol (+) can be used as a wild card for any value at one specific level. Example: level1/level2/+/level4 The hash sign symbol (#) can be used as a wild card for any values across more than one level. Example: level1/#/level4		
User Id	The user Id that will be used to connect to MQTT.		
Password	The password that will be used to connect to MQTT.		

2. To allow encrypted connections, you can either:

Upload a CA Certificate file browse to the file source.	by clicking Upload File	Upload Fi	ile	then Browse	Browse	to
After selecting the file, it is d	isplayed with the times	tamp.				
Load Type	Upload File L	ink To File				
	letsencrypt.cer × as of 2022-08-17 11:13	:14	Bro	wse		
To change the certificate, cli	ck × then Browse	Browse to b	browse	e to a new vers	ion of the fi	le.
Link to a CA Certificate file b	by clicking Link to File	Link To Fil	le)	and entering a	File Path.	
Load Type	Upload File L	ink To File				
CA Certificate			(File	Гуре: .crt,.cer,.c	ler,.pem)	

- 3. In MQTT, a topic consists of one or more topic levels. Enter the *Topic Level Separator* to use. Default is / (forward slash).
- 4. Select the Message Type.
- 5. Select either the dot (.) or comma (,) as the Decimal Separator.

NOTE Prepend 'default:' for the elements falling under default namespace.

6. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the **Save** button is enabled.

This also populates the *Id Column* with the set of columns, of arbitrary type, that can be concatenated to form a unique row identifier.

- 7. You can also opt to <u>load or save</u> a copy of the column definition.
- 8. Click to add columns to the MQTT connection that represent sections of the message. Then enter or select:


Property	Description
Name	The column name of the source schema.
XPath/JsonPath/Fix Tag/Column Index	The XPath/JsonPath/Fix Tag/Column Index of the source schema.
Туре	The data type of the column. Can be a Text , Numeric , or Time
Date Format	The <u>format</u> when the data type is Time . NOTE: To parse and format times with higher than millisecond precision, the format string needs to end with a period followed by sequence of upper case S. There can be no additional characters following them. For example: yyyy-MM-dd HH:mm:ss.SSSSSS
Filter	Defined parameters that can be used as filter. Only available for JSON, Text, and XML message types.
Enabled	Determines whether the message field should be processed.


To dolote a column, shook its	or all the column entries, check the topmost	than aliak	_
To delete a column, check its	or all the column entries, check the topmost	then click	

9. Text for topic levels can be consumed as additional columns into the data table.

The *Topic Columns* section shows and allows defining data table columns and mapping them to topic hierarchy levels (index based from left, 0 based).

Like columns from message data, manually add them by clicking . A new entry displays.





Refer to **Define Real-Time Settings** for more information.

Connector for OneTick CEP

The OneTick CEP connector allows connection to OneMarketData OneTick tick history databases on a streaming subscription basis. The connector supports either:

- Execution of a specified OTQ
- Execution of a specified parameterized OTQ


To use the OneTick CEP connector, it requires a JAR file to be added and some configurations to be performed. Further details are provided in the <u>Panopticon Real Time Installation and Troubleshooting Guide</u>.

Steps:

- 1. Enter the Context (for example, REMOTE).
- 2. You can either check:
 - Show Local OTQs box to display the local OTQs in the Selected OTQs drop-down list.
 - Show Remote OTQs box to display the remote OTQs in the Selected OTQs drop-down list.

3. Click **Load** to populate the *Selected OTQ* drop-down list. Select an OTQ.

The OTQ Parameters section displays with the list of input parameters based on the selected OTQ.



- 4. Check/uncheck the Separate DB Name box.
- 5. Click Fetch Schema to populate the *Id Column* list box.


From this list box, select the field which will define a unique data record to subscribe against.

The following are generic to all OTQs:

- Symbol List
- From
- To

These add additional filter criteria such as symbol, and time window onto the basic OTQ.


- 6. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged. You can opt to define the <u>Show in Timezone and Source Timezone</u> settings.
- 7. For this section:



Refer to **Define Real-Time Settings** for more information.

Connector for Panopticon Streams

Retrieves topics using the meta data of applications that are provided by Panopticon Streams Server.



Steps:

- 1. Enter the absolute path, including the http where the Panopticon Streams server is located, in the *Streams Server URL* box (i.e., http://localhost:8080/streams).
- 2. Click Fetch Applications. The first application in the Application drop-down list is selected and the schema of the output topic is displayed, if it is started in the Panopticon Streams server.

This also populates the *Id Column* with the set of columns, of arbitrary type, that can be concatenated to form a unique row identifier.

- 3. Click the *Application* drop-down list box to select another application.
- Check the Show Input Topics box to include input topics in the Topic drop-down list.



- 5. Select a topic. This populates the list of columns, with the data type found from inspecting the first 'n' rows of the
- 6. Check the From Beginning box to subscribe from the beginning to the latest messages.



If un-checked, you will only be subscribed to the latest messages.



- Click to ensure that the latest schema of the topic is being applied.
- 8. Then select:
 - Enabled (determines whether the message field should be processed)
 - Filter (defined parameters that can be used as Filter)
- 9. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged.

You can opt to define the Show in Timezone and Source Timezone settings.

10. For this section:

Real-Time Settings Id Column [Topic Key] ¥ [No Time Id] Time Id Column Time Id Column Name Time Id Barring None Time Window (s) 1000 Real-time Limit (ms) Persistent Server Subscription Add Last Update Time and Age Reset Data on

Refer to **Define Real-Time Settings** for more information.

Connector for RabbitMQ

Reconnect

The RabbitMQ connector allows connection to RabbitMQ's message bus on a real-time streaming basis. Specifically, the connector allows Panopticon to subscribe to XML, JSON, Text or FIX based messages that are published on particular topics.

Steps:

1. Enter the connection details including:

Property	Description
Broker	The location of the message broker.
User Id	The user ld that will be used to connect to RabbitMQ.
Password	The password that will be used to connect to RabbitMQ.

2. Select any of the following Exchange Types:

Exchange Type	Description		
Default	A direct exchange with no name that is pre-declared by the broker. Selecting this exchange type disables the <i>Exchange</i> section (<i>Exchange</i> and <i>Routing Key</i> properties).		
	Exchange Type Exchange Durable Auto Delete Routing Key Explicit Queue	topic	
Fanout	Broadcasts all of the messages it re the routing key is ignored (the <i>Rout</i>	eceives to all of the queues it knows and ting Key field is disabled).	
Direct	0 1	ed on a message routing key. It is ideal for though it can be used for multicast routing	
Topic	A message sent with a particular roqueues that are bound with a match	outing key will be delivered to all of the hing binding key.	
Headers	Exchanges routed based on argum values.	nents containing headers and optional	

3. Depending on the selected *Exchange Type*, select or define the following:

Property	Description
Exchange	Name of the exchange.
Durable	Enable so the exchange can survive a broker restart.
Auto Delete	Enable so the exchange is deleted when the last queue is unbound from it.
Routing Key	The routing key used to deliver messages to queues.
Headers	This field is only available when the message type is Header . Binding a queue to a Headers exchange is possible using more than one header for matching. Setting <i>x-match</i> to any , means just one matching value is sufficient. Setting it to all means that all values must match. Default is x-match=all .

4. Check the *Explicit Queue* box and enter the custom queue name. Then enter or enable the following properties:

Queue Property	Description		
Properties	The custom queue property.		
Durable	Enable so the queue can survive a broker restart.		
Auto Delete	Enable so the queue that had the least consumer will be deleted when that connection closes.		

5. Select the <u>Message Type</u>.

6. Select either the dot (.) or comma (,) as the Decimal Separator.

NOTE Prepend 'default:' for the elements falling under default namespace.

7. Click Generate Columns to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the Save button is enabled.

This also populates the *Id Column* with the set of columns, of arbitrary type, that can be concatenated to form a unique row identifier.

- 8. You can also opt to load or save a copy of the column definition.
- 9. Click to add columns to the RabbitMQ connection that represent sections of the message. Then enter or select:

Property	Description			
Name	he column name of the source schema.			
Fix Tag/Json Path/Text Column Index/Xpath	The Fix Tag/Json Path/Text Column Index/Xpath of the source schema.			
Туре	The data type of the column. Can be a Text , Numeric , or Time			
Date Format	The <u>format</u> when the data type is Time . NOTE: To parse and format times with higher than millisecond precision, the format string needs to end with a period followed by sequence of upper case S. There can be no additional characters following them. For example: yyyy-MM-dd HH:mm:ss.SSSSS			
Filter	Defined parameters that can be used as filter. Only available for JSON, Text, and XML message types.			
Enabled	Determines whether the message field should be processed.			

To delete a column, check its	or all the column entries, check the topmost	, then click	-
-------------------------------	--	--------------	---

- 10. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged. You can opt to define the <u>Show in Timezone and Source Timezone</u> settings.
- 11. For this section:

Real-Time Settings Id Column id ¥ [No Time Id] Time Id Column Time Id Column Name None Time Id Barring 0 Time Window (s) 1000 Real-time Limit (ms) Persistent Server Subscription Add Last Update Time and Age Reset Data on

Refer to <u>Define Real-Time Settings</u> for more information.

Connector for Redis Streams (Beta)

The Redis Streams connector allows you to connect and subscribe to Redis Streams using lettuce API.

Steps:

Reconnect

1. Enter the connection details including:

Property	Description			
Redis Server	Redis Streams host address.			
Subscribed To	Channel to subscribe against.			

2. Check the From Beginning box to subscribe from the beginning to the latest messages.



If un-checked, you will only be subscribed to the latest messages.

- 3. Select the Message Type.
- 4. Select either the dot (.) or comma (,) as the Decimal Separator.



5. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the **Save** button is enabled.

This also populates the *Id Column* with the set of columns, of arbitrary type, that can be concatenated to form a unique row identifier.

- 6. You can also opt to load or save a copy of the column definition.
- 7. Click to add columns to the Redis Streams connection that represent sections of the message. Then enter or select:

Property	Description				
Name	The column name of the source schema.				
Fix Tag/JsonPath/Column Index/XPath	The Fix Tag/JsonPath/Text Column Index/XPath of the source schema.				
Туре	The data type of the column. Can be a Text , Numeric , or Time				
Date Format	The format when the data type is Time . NOTE: To parse and format times with higher than millisecond precision, the format string needs to end with a period followed by sequence of upper case S. There can be no additional characters following them. For example: yyyy-MM-dd HH:mm:ss.SSSSSS				
Filter	Defined parameters that can be used as filter. Only available for JSON, Text, and XML message types.				
Enabled	Determines whether the message field should be processed.				

				$\overline{}$		
		0.41		1 1		
To delete a column, check i	S _	or all the column entries, c	check the topmost	$\overline{}$. then click	

8. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged.

You can opt to define the Show in Timezone and Source Timezone settings.

9. For this section:

Real-Time Settings Id Column id ¥ [No Time Id] Time Id Column Time Id Column Name None Time Id Barring Time Window (s) 1000 Real-time Limit (ms) Persistent Server Subscription Add Last Update Time and Age Reset Data on Reconnect

Refer to <u>Define Real-Time Settings</u> for more information.

Connector for Solace

The Solace connector allows connection to Solace's message bus on a real time streaming basis. Specifically, the connector allows Panopticon to subscribe to messages that are published in particular topics in Solace and consequently, perform operational analytics.

Steps:


1. Enter the connection details including:

Property	Description			
Host	Solace host address.			
VPN Name	Message VPN name. Default is default .			
User Id	The user Id that will be used to connect to Solace.			
Password	The password that will be used to connect to Solace.			

- 2. Enter the *Topic* or the queue physical name.
- 3. Select the Message Type.


Aside from the Fix, Json, Text, and XML message types, Protobuf is also supported in Solace.

If Protobuf is selected, confirm the Decimal Separator, and enter the Schema Name and Type Name.



Property	Description			
Schema Name	The Protobuf schema.			
Type Name	The message of Protobuf type that will be sent to Kafka.			
File Descriptor	The FileDescriptorSet which:			
	is an output of the protocol compiler.			
	• represents a set of .proto files, using thedescriptor_set_out option.			

4. Select either the dot (.) or comma (,) as the Decimal Separator.



5. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the **Save** button is enabled.

This also populates the *Id Column* with the set of columns, of arbitrary type, that can be concatenated to form a unique row identifier.

- 6. You can also opt to load or save a copy of the column definition.
- 7. Click to add columns to the Solace connection that represent sections of the message. Then enter or select:

Property	Description				
Name	ne column name of the source schema.				
Type/JsonPath/Column Index/XPath	The SDTMap Type/JsonPath/Text Column Index/XPath of the source schema.				
Туре	The data type of the column. Can be a Text , Numeric , or Time				
Date Format	The format when the data type is Time . NOTE: To parse and format times with higher than millisecond precision, the format string needs to end with a period followed by sequence of upper case S. There can be no additional characters following them. For example: yyyy-MM-dd HH:mm:ss.SSSSSS				
Filter	Defined parameters that can be used as filter. Only available for Avro, JSON, Text, and XML message types.				
Enabled	Determines whether the message field should be processed.				

			l	_
To delete a column, check its \	_	or all the column entries, check the topmos	 , then click	

- 8. To create a new Timestamp field, enter a new *Timestamp Name* and then select the valid Date/Time from either a single *Date* or *Time* field, or a compound column created from *Date* and *Time* fields.
- 9. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged.

You can opt to define the Show in Timezone and Source Timezone settings.

10. For this section:

Real-Time Settings Id Column id ¥ [No Time Id] Time Id Column Time Id Column Name None Time Id Barring 0 Time Window (s) 1000 Real-time Limit (ms) Persistent Server Subscription Add Last Update Time and Age Reset Data on Reconnect

Refer to <u>Define Real-Time Settings</u> for more information.

Connector for Streams Simulator

The Streams Simulator connector is very similar to the Text connector with the addition of the time windowing of message queue connectors.

Creating the Streams Simulator input data source includes setting for how fast and how many messages are pushed through in each batch.

Steps:

1. Select the Text File Source.

The standard settings controlling how the text file is parsed is listed.

These include:

Property	Description			
Skip First N Rows	Specifies the number of rows that will be skipped.			
Data Type Discovery	Specifies how many rows from the text file should be used when automatically letermining the data types of the resulting columns.			
Decimal Separator	Select either the dot (.) or comma (,) as the Decimal Separator.			
Text Qualifier	Specifies if fields are enclosed by text qualifiers, and if present to ignore any column delimiters within these text qualifiers.			
Column Delimiter	Specifies the column delimiter to be used when parsing the text file.			
First Row Headings	Determines if the first row should specify the retrieved column headings, and not be used in data discovery.			

2. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the **Save** button is enabled.

This also populates the *Id Column* with the set of columns, of arbitrary type, that can be concatenated to form a unique row identifier.


- 3. You can also opt to load or save a copy of the column definition.
- 4. Click . A new column entry is displayed. Enter or select the following properties:

Property	Description		
Name	The column name of the source schema.		
Column Index	The column index controls the position of a column. Must be >= 0.		
Туре	The data type of the column. Can be a Text, Numeric, or Time		
Date Format	The <u>format</u> when the data type is Time .		
Filter	Defined parameters that can be used as filter.		
Enabled	Determines whether the message should be processed.		

To delete a column, check its \square or all the column entries, check the topmost \square , then click -.

- 5. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged.
 - You can opt to define the Show in Timezone and Source Timezone settings.
- 6. Select the Simulation Type:
 - Record

Sends the number of records for each interval of time. By default, records are sent in the same order of the source.



This simulation type allows the specification of the following:

Sort Order



When you select the **Use file sort order**, it will use the default sorting order of the file.

When you either select **Ascending** or **Descending** as the Sort Order, this enables the *Sorted by Column* drop down list.

Select the column that will be used for the sorting.



Playback Set Size

The number of records set to be updated during simulate/playback.

Start Up Set Size


The number of records set to be published initially (on start-up).

Playback Interval (ms)

The update interval period for the record-based playback. Default is 1000 (ms).

Time

Simulates records as they occur in real-time.



This simulation type allows the specification of the following:

Playback Column

The playback column which is a Date/Time type.

Playback Speed

A multiplier which to either speed up or slow down the playback. Default is 1.


- o If 0 < value < 1 slow down
- o If value = 1 records will be published as they occur
- o if value > 1 speed up

NOTE

For time-based simulation, if the Date/Time column have improper dates, it will fail and stop.

- 7. Check the **Loop** box to enable looping through the file.
- 8. For this section:

Real-Time Settings



Refer to **Define Real-Time Settings** for more information.


Connector for Streams Simulator - Extract

The Streams Simulator – Extract connector reads data extracts and outputs the data as a streaming real-time connector, either in batches or based on the values of a timestamp field in the incoming data.

Steps:


1. Select **Streams Simulators - Extract** from the *Connectors* panel. The *Streams Simulator – Extract Settings* panel displays with the first data extract in the drop-down list (e.g., BitcoinOrders).

The list of columns is displayed, with the data type found from inspecting the first 'n' rows of the file. This also populates the *Id Column* with the set of columns, of arbitrary type, that can be concatenated to form a unique row identifier.



You can also filter the list of columns by entering a text in the Search box.

2. You can opt to select another data extract to display its list of columns.




- If the data returned is to be aggregated, then check their Column box. For each selected column, the possible aggregation methods are listed including:
 - Text Columns: Group By
 - Date/Time Columns: Group By
 - Numeric Columns: Sum, Count, Min, Max, Mean



Select the Aggregate method in the drop-down list.

4. If you wish to parameterize a specific column, match the parameter to the appropriate column. By default, they will be matched on name.




5. If only a selected Date/Time range of the table/view is to be queried, check the **Constrain** box, and complete the *From* and *To* text boxes, either with values or with parameters.



- 6. Select the Simulation Type:
 - Record

Sends the number of records for each interval of time. By default, records are sent in the same order of the source.



This simulation type allows the specification of the following:

Playback Set Size


The number of records set to be updated during simulate/playback.

Playback Interval (ms)

The update interval period for the record-based playback. Default is 1000 (ms).

Time

Simulates records as they occur in real-time.



This simulation type allows the specification of the following:

Playback Column

The playback column which is a Date/Time type.

Playback Speed

A multiplier which to either speed up or slow down the playback. Default is 1.


- o If 0 < value < 1 slow down</p>
- If value = 1 records will be published as they occur
- o if value > 1 speed up

NOTE

For time-based simulation, if the Date/Time column have improper dates, it will fail and stop.

- 7. Check the **Loop** box to enable looping through the file.
- 8. For this section:

Real-Time Settings



Refer to **Define Real-Time Settings** for more information.

Connector for StreamBase 7.1

The StreamBase 7.1 connector allows connection to the StreamBase CEP engine instance on a real-time streaming basis.

To use the StreamBase connector, Streambase 7.1 redistributable must be installed.

 $\label{lem:reambase.com/products/streambasecep/download-streambase/} for more information in downloading StreamBase products. \\$

Steps:

1. Enter the following properties:

Property	Description
Primary URL	Primary URL of the StreamBase 7.1. Default is sb://localhost:10000 .
Secondary URL	Secondary URL of the StreamBase 7.1.
	NOTE: More than two StreamBase server URLs can be specified by comma separation.
User Id	User Id that will be used to connect to StreamBase 7.1.
Password	Password that will be used to connect to StreamBase 7.1.

2. Click Fetch Streams to return a list of updated streams. Selection of a stream returns a list of available Id columns for the stream.

This populates the *Id Column* with the set of columns from the schema of type sym and the text array such as Character/Boolean/GUID, etc. The selected *Id Column* can be used to select a key column to manage data updates and inserts.


- 3. Enter the *Predicate* expression to force emission.
- 4. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged. You can opt to define the *Show in Timezone* and *Source Timezone* settings.
- 5. Select whether the parameters should be automatically enclosed in quotes, by checking the **Enclose** parameters in quotes box.
- 6. For this section:

Real-Time Settings Id Column Symbol Time Id Column [No Time Id] Time Id Column Name Time Id Barring None Time Window (s) 0 Real-time Limit (ms) 1000 Reset Data on Reconnect

Refer to <u>Define Real-Time Settings</u> for more information.

Connector for StreamBase LiveView

The StreamBase LiveView connector allows connection to the StreamBase LiveView instance on a real-time streaming basis.



Steps:

1. Enter the following properties:

Property	Description
Primary URL	Primary URL of the StreamBase LiveView. Default is Iv://localhost:10080/.
User Id	User Id that will be used to connect to StreamBase LiveView.
Password	Password that will be used to connect to StreamBase LiveView.

2. Do one of the following:

• Select the **Table** radio button then click to return a list of updated *Tables*, or

By default, the whole table will be subscribed against. To subscribe against a subset, enter a predicate.

The ${\tt IN}\,$ syntax is recommended for use of parameters to support multiple values. The square bracket notation should be used for the ${\tt IN}\,$ clause.


Example: color IN [{color}]

Select the required table.

Select the **Query** radio button, enter a full query, then click

- Select whether the parameters should be automatically enclosed in quotes by checking the Enclose parameters in quotes box.
- 4. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged. You can opt to define the *Show in Timezone* and *Source Timezone* settings.
- 5. Enter the Id Column Name.

LiveView supplies a unique Id for each row. This Id field is by default given a title of Key.



Refer to **Define Real-Time Settings** for more information.

Connector for WebSocket

The WebSocket connector is very similar to the Streams Simulator connector, except that rather than looping through a file, it would either connect through web sockets, long polling, or repeatedly poll an external URL for new records to process.

Steps:

1. Enter the connection details:

Property	Description
Path	The path to which the WebSocket server will respond to.
User ID	The User ID that will be used to connect to the WebSocket server.
Password	The password that will be used to connect to the WebSocket server.
	Check the Show Characters box to display the entered characters.
Request Body	For both the HTTP and ws:// POST requests sent to the WebSocket server.
Timeout	The length of time to wait for the server response (10 to 300). Default is 10 .

- 2. Select the Message Type.
- 3. Select either the dot (.) or comma (,) as the Decimal Separator.

NOTE

Prepend 'default:' for the elements falling under default namespace.

4. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the **Save** button is enabled.

This also populates the *Id Column* with the set of columns, of arbitrary type, that can be concatenated to form a unique row identifier.

- 5. You can also opt to load or save a copy of the column definition.
- 6. Click to add columns to the WebSocket connection that represent sections of the message. Then enter or select:

Property	Description
Name	The column name of the source schema.
JsonPath/Text Column Index/XPath	The JsonPath/Text Column Index/XPath of the source schema.
Туре	The data type of the column. Can be a Text , Numeric , or Time
Date Format	The <u>format</u> when the data type is Time .
Filter	Defined parameters that can be used as filter.
Enabled	Determines whether the message field should be processed.

NOTE	To parse and format times with higher than millisecond precision, the format string needs to end with a period followed by sequence of upper case S. There can be no additional characters following them.
	For example: yyyy-MM-dd HH:mm:ss.SSSSSS

- 7. Date/Time values of output data and Date/Time inputs, where supported, is by default unchanged. You can opt to define the *Show in Timezone* and *Source Timezone* settings.
- 8. For this section:

Real-Time Settings Id Column id ¥ [No Time Id] Time Id Column Time Id Column Name None Time Id Barring 0 Time Window (s) 1000 Real-time Limit (ms) Persistent Server Subscription Add Last Update Time and Age Reset Data on

Refer to **Define Real-Time Settings** for more information.

Defining Real-Time Settings


Connectors for streaming data sources have a common section for defining real-time settings. Follow the steps below to select a key column or concatenated key for the streaming time series window.

Steps:

Reconnect


1. After generating columns or fetching schema on the streaming connector, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated.

Consequently, on the *Real-Time Settings* section, the *Id Column* drop-down list displays with the set of columns, of arbitrary type.




2. Select a key column to manage data updates and inserts. In some cases, select multiple key columns to form a unique row identifier.

Real-Time Settings




3. You may opt to check the Add Last Update Time and Age box.



This allows the latest update time and its age to be highlighted by the defined color range in the output dashboard. Refer to <u>Highlighting the Latest Data in Real Time Streaming Connectors</u> for more information.

4. A streaming time series window can be generated by creating a compound key with the *Id Column*, plus a separately specified *Time Id* column. The *Time Id* column can be from the source dataset, or alternatively automatically generated.




If the Time Id column is selected, then a scrolling time window can be specified. As new data arrives from the subscription, new time slices will automatically be added, and old ones will be deleted.


Select either:

Automatic Time Id.



Date/Time Id column either from the source data or automatically generated.





- 5. Define or select the following information:
 - Time Id Column Name for Automatic Time Id


- Time Id Barring
 - Select the barring period. This conflates the data set to a defined granularity or any of the following time intervals.
- Time Window (s). Default is 0.
- 6. Modify the Real-time Limit to vary the data throttling. This defaults to **1000** milliseconds.



- 7. Check the Persistent Server Subscription box. This means that it will not be purged.
 - If not checked, Panopticon Real Time can purge or cancel the subscription if it is orphan and is running out of memory. Note though that it can be purged for other reasons as well, depending on how the user has set it up.
- 8. Check the Reset Data on Reconnect box to flush out the stale data and reload data after reconnection.

Defining Real-Time Settings for Apache Kafka and Panopticon Streams Connectors

For the Apache Kafka and Panopticon Streams connectors, on the *Real-Time Settings* section, the key provided from the Kafka subscription is automatically selected as the *Id Column*.




Follow the steps below to select a key column or concatenated key for the streaming time series window.

Steps:


- 1. After generating columns or fetching schema on the streaming connector, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated.
 - Consequently, on the *Real-Time Settings* section, the *Id Column* drop-down list displays with the set of columns, of arbitrary type.

Real-Time Settings



2. Select a key column to manage data updates and inserts. In some cases, select multiple key columns to form a unique row identifier.


Real-Time Settings



3. You may opt to check the Add Last Update Time and Age box.




Real-Time Settings



This allows the latest update time and its age to be highlighted by the defined color range in the output dashboard. Refer to Highlighting the Latest Data in Real Time Streaming Connectors for more information.


4. A streaming time series window can be generated by creating a compound key with the *Id Column*, plus a separately specified *Time Id* column. The *Time Id* column can be from the source dataset, or alternatively automatically generated.




If the Time Id column is selected, then a scrolling time window can be specified. As new data arrives from the subscription, new time slices will automatically be added, and old ones will be deleted.

Select either:

Automatic Time Id



Date/Time Id column either from the source data or automatically generated



- 5. Define or select the following information:
 - Time Id Column Name for Automatic Time Id
 - Time Id Barring

Select the barring period. This conflates the data set to a defined granularity or any of the following time intervals.

- Time Window (s). Default is 0.
- 6. Modify the Real-time Limit to vary the data throttling. This defaults to 1000 milliseconds.




7. Check the Persistent Server Subscription box. This means that it will not be purged.

If not checked, Panopticon Real Time can purge or cancel the subscription if it is orphan and is running out of memory. Note though that it can be purged for other reasons as well, depending on how the user has set it up.


8. Check the Reset Data on Reconnect box to flush out the stale data and reload data after reconnection.

Previewing Streaming Data

Opening data through a streaming connector displays the **Start Preview** button on the *Data Source Preview* section. For example, opening a data source using the Kdb+ Tick connector displays the following preview:



Initially there is no data. Clicking the Start Preview button displays the data and refreshes the values depending on the defined Auto Refresh period. The Start Preview button eventually changes to



Click to stop refreshing values of the streaming data.

Highlighting the Latest Data in Real Time Streaming Connectors

In the real time streaming connectors, there is an option to force flushes, so that output dashboards can visually highlight the latest and age of data and present whether they are stale or not.

Color is used to highlight when an item has changed. Follow the steps below to on how to configure the visualization of age in real time streaming connectors.

Steps:


- 1. Open a streaming connector and define the connection details.
- Check the Add Last Update Time and Age box.



3. Click Start Preview to confirm the selection and retrieve the record set into the Data Table Editor layout.

In the Data Sources Preview window, two columns are added:


_LastUpdateTime - Date/Time column which updates on all rows that were inserted or updated.



_LastUpdateAge - Numeric column which represents the seconds since rows were last touched in a flush.
 This is updated on all rows.




- 4. Click then to save the data table and exit the Data Table Editor layout. The Open Workbook in Design Mode layout displays.
- Add a visualization and select the column/s that will have the color highlight.Example:



In this Table visualization, the **_LastUpdateAge** column is added in the <u>Color variable</u> and will be used as the highlight for the **overwrap** record.

6. To define the color settings, select **_LastUpdateAge** under the *Color* variable list.



In the example above the Range is 1 (Min) to 5 (Max) seconds with the color palette **White-Red** and the colors are **Reversed**. This means that when the **_LastUpdateAge** value is updated, the background color of the **overwrap** row will be red and will fade to white over the next 5 seconds.



You can then easily view whether the data are updated or stale.

Parameterization of Connection Settings for Data Sources

Connecting to data sources typically requires application login. To be able to connect, you may need to enter the following information, depending on the connector:

Host Name

□ Port

Server Name

User ID


Password

Database

This information is then stored in XML files detailing user and group permissions in workbooks. To secure data access and avoid storing connection information in the workbook, it is recommended to parameterize these fields in connectors.

Steps:

- 1. On the *Parameters* pane of the *Data Table Settings*, define the connection settings you will use for the connector. Such as the following:
 - Host
 - User
 - Pwd
 - Server
 - DB
 - Port




- 2. Click on a data source. The Data Source Settings pane is displayed.
- 3. Parameterize the entries in the pane.

For example:



Parameterization of Time Zones in Data Connectors

Aside from selecting a Windows time zone name in the *Show in Timezone* field of the following data connectors, you can now parameterize the time zone per connection:



Selecting a Windows time zone



Entering a parameterized time zone

- □ JSON
- □ Text
- □ XML
- Apache Cassandra
- □ InfluxDB
- JDBC Database
- Kx kdb+
- MongoDB
- OneTick
- OneTick Cloud
- Python
- □ ActiveMQ
- □ AMPS
- □ Google Cloud Pub/Sub
- □ JDBC Database Streaming
- Apache Kafka
- Kx kdb+tick
- MQTT
- OneTick CEP
- Panopticon Streams
- □ RabbitMQ
- Solace


Streams	Simulator
---------	-----------

- □ StreamBase 7.1
- □ StreamBase LiveView
- WebSocket

In the <u>Parameters</u> pane of the <u>Data Table Editor</u> layout page, the following dynamic parameterization formats are supported:

- Windows Timezone ID
- IANA
- □ Custom: GMT +/- hours:minutes

For example:



Refer to the table below for the list of Windows time zone and IANA names that you can use:

Windows Name	IANA Name
Alaskan Standard Time	"America/Anchorage"
Arabian Standard Time	"Asia/Dubai"
Atlantic Standard Time	"America/Halifax"
Caucasus Standard Time	"Asia/Yerevan"
Cen. Australia Standard Time	"Australia/Adelaide"
Central America Standard Time	"America/Guatemala"
Central Asia Standard Time	"Asia/Almaty"
Central Europe Standard Time	"Europe/Budapest"
Central European Standard Time	"Europe/Warsaw"
Central Pacific Standard Time	"Pacific/Guadalcanal"
Central Standard Time	"America/Chicago"
China Standard Time	"Asia/Shanghai"
Dateline Standard Time	"Etc/GMT+12"


E. Africa Standard Time "Australia/Brisbane" E. Europe Standard Time "Asia/Nicosia" E. South America Standard Time "America/Sao_Paulo" Time Eastern Standard Time "America/New_York" Egypt Standard Time "Africa/Cairo" GMT Standard Time "Europe/London" Greenland Standard Time "Pacific/Honolulu" India Standard Time "Asia/Calcutta" Iran Standard Time "Asia/Calcutta" Iran Standard Time "Asia/Calcutta" Iran Standard Time "Asia/Seoul" Mountain Standard Time "Asia/Seoul" Mountain Standard Time "Asia/Seoul" New Zealand Standard Time "Pacific/Auckland" New Zealand Standard Time "Asia/Irkutsk" North Asia East Standard Time "Asia/Irkutsk" North Asia Standard Time "Asia/Irkutsk" North Asia Standard Time "America/Santiago" Pacific SA Standard Time "America/Santiago" Pacific Standard Time "America/Los_Angeles" Russian Standard Time "America/Los_Angeles" Russian Standard Time "America/Los_Angeles" SA Pacific Standard Time "America/Los_Angeles" SA Western Standard Time "America/Los_Angeles" SA Western Standard Time "America/Los_Angeles" Samoa Standard Time "America/Los_Angeles" Samoa Standard Time "America/Los_Angeles" Singapore Standard Time "Asia/Fapai" South Africa Standard Time "Asia/Singapore" South Africa Standard Time "Asia/Singapore" South Africa Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Taipei" Tasmania Standard Time "Asia/Tokyo" US Eastern Standard Time "Asia/Tokyo" US Eastern Standard Time "Asia/Tokyo"		
E. Europe Standard Time "Asia/Nicosia" E. South America Standard Time "America/Sao_Paulo" Time Eastern Standard Time "America/New_York" Egypt Standard Time "Europe/London" Greenland Standard Time "Pacific/Honolulu" India Standard Time "Asia/Calcutta" Iran Standard Time "Asia/Jerusalem" Korea Standard Time "Asia/Seoul" Mountain Standard Time "Asia/Novosibirsk" New Zealand Standard Time "Pacific/Honolulu" North Asia East Standard Time "Asia/Novosibirsk" New Zealand Standard Time "Asia/Novosibirsk" North Asia Standard Time "Asia/Irkutsk" North Asia Standard Time "Asia/Irkutsk" North Asia Standard Time "Asia/Krasnoyarsk" Pacific SA Standard Time "America/Santiago" Pacific Standard Time "America/Santiago" Pacific Standard Time "America/Santiago" Pacific Standard Time "America/Cayenne" SA Eastern Standard Time "America/Cayenne" SA Pacific Standard Time "America/Bogota" SA Western Standard Time "America/Bogota" SA Western Standard Time "America/La_Paz" Samoa Standard Time "Asia/Singapore" South Africa Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Taipei" Tasmania Standard Time "Asia/Tokyo"	E. Africa Standard Time	"Africa/Nairobi"
E. South America Standard Time "America/Sao_Paulo" Eastern Standard Time "Africa/Cairo" GMT Standard Time "Europe/London" Greenland Standard Time "Pacific/Honolulu" India Standard Time "Asia/Calcutta" Iran Standard Time "Asia/Jerusalem" Korea Standard Time "Asia/Seoul" Mountain Standard Time "Asia/Novosibirsk" N. Central Asia Standard Time "Pacific/Auckland" New Zealand Standard Time "Asia/Irans" North Asia East Standard Time "Asia/Iransoyarsk" Pacific Standard Time "Asia/Krasnoyarsk" Pacific Standard Time "America/Los_Angeles" Russian Standard Time "America/Los_Angeles" Russian Standard Time "America/Los_Angeles" SA Pacific Standard Time "America/La_Paz" Samoa Standard Time "Asia/Singapore" SA Western Standard Time "Asia/Singapore" South Africa Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Taipei" Tasmania Standard Time "Australia/Hobart" Tokyo Standard Time "Asia/Tokyo"	E. Australia Standard Time	"Australia/Brisbane"
Eastern Standard Time "America/New_York" Egypt Standard Time "Europe/London" Greenland Standard Time "Pacific/Honolulu" India Standard Time "Asia/Calcutta" Iran Standard Time "Asia/Jerusalem" Korea Standard Time "Asia/Jerusalem" Korea Standard Time "Asia/Novosibirsk" N. Central Asia Standard Time "Pacific/Auckland" New Zealand Standard Time "Asia/Irans" North Asia East Standard Time "Asia/Iransovarsk" Pacific SA Standard Time "Asia/Iransovarsk" Pacific Standard Time "America/Los_Angeles" Russian Standard Time "America/Los_Angeles" Russian Standard Time "America/Los_Angeles" Russian Standard Time "America/Los_Angeles" SA Pacific Standard Time "America/Los_Angeles" SA Western Standard Time "America/Los_Angeles" SA Western Standard Time "America/La_Paz" Samoa Standard Time "Asia/Bangkok" Singapore Standard Time "Asia/Singapore" South Africa Standard Time "Asia/Singapore" South Africa Standard Time "Asia/Iransovarsk" Pacific Standard Time "America/La_Paz" Samoa Standard Time "Asia/Bangkok" Singapore Standard Time "Asia/Singapore" South Africa Standard Time "Asia/Singapore" South Africa Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Taipei" Tasmania Standard Time "Australia/Hobart" Tokyo Standard Time "Asia/Tokyo"	E. Europe Standard Time	"Asia/Nicosia"
Egypt Standard Time "Africa/Cairo" GMT Standard Time "Europe/London" Greenland Standard Time "Pacific/Honolulu" India Standard Time "Asia/Calcutta" Iran Standard Time "Asia/Jerusalem" Korea Standard Time "Asia/Jerusalem" Korea Standard Time "Asia/Seoul" Mountain Standard Time "Asia/Seoul" Mountain Standard Time "Asia/Novosibirsk" N. Central Asia Standard Time "Pacific/Auckland" New Zealand Standard Time "America/St_Johns" North Asia East Standard Time "Asia/Irkutsk" North Asia Standard Time "Asia/Krasnoyarsk" Pacific SA Standard Time "America/Santiago" Pacific Standard Time "America/Cayenne" SA Eastern Standard Time "America/Cayenne" SA Pacific Standard Time "America/Bogota" SA Western Standard Time "America/Bagota" SA Western Standard Time "America/La_Paz" Samoa Standard Time "Pacific/Apia" SE Asia Standard Time "Pacific/Apia" SE Asia Standard Time "Asia/Bangkok" Singapore Standard Time "Asia/Singapore" South Africa Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Taipei" Tasmania Standard Time "Asia/Taipei" Tokyo Standard Time "Asia/Tokyo"		"America/Sao_Paulo"
GMT Standard Time "Europe/London" Greenland Standard Time "America/Godthab" Hawaiian Standard Time "Asia/Calcutta" Iran Standard Time "Asia/Jorusalem" Korea Standard Time "Asia/Jorusalem" Korea Standard Time "Asia/Jorusalem" Mountain Standard Time "Asia/Jorusalem" N. Central Asia Standard Time "Asia/Novosibirsk" New Zealand Standard Time "Pacific/Auckland" Newfoundland Standard Time "Asia/Irkutsk" North Asia East Standard Time "Asia/Irkutsk" North Asia Standard Time "Asia/Krasnoyarsk" Pacific SA Standard Time "America/St_Johns" North Sia Standard Time "America/St_Johns" North Asia Standard Time "Anerica/Santiago" Pacific Standard Time "America/Cayenel" SA Eastern Standard Time "Europe/Moscow" SA Eastern Standard Time "America/Cayenne" SA Western Standard Time "America/La_Paz" Samoa Standard Time "Pacific/Apia" SE Asia Standard Time "Pacific/Apia" SE Asia Standard Time "Asia/Singapore" South Africa Standard Time "Asia/Singapore" South Africa Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Taipei" Tasmania Standard Time "Australia/Hobart" Tokyo Standard Time "Asia/Tokyo"	Eastern Standard Time	"America/New_York"
Greenland Standard Time "America/Godthab" Hawaiian Standard Time "Pacific/Honolulu" India Standard Time "Asia/Calcutta" Iran Standard Time "Asia/Jerusalem" Korea Standard Time "Asia/Jerusalem" Korea Standard Time "Asia/Seoul" Mountain Standard Time "Asia/Novosibirsk" N. Central Asia Standard Time "Pacific/Auckland" New Zealand Standard Time "Asia/Irkutsk" North Asia East Standard Time "Asia/Irkutsk" North Asia Standard Time "Asia/Irkutsk" North Asia Standard Time "America/St_Johns" North Asia Standard Time "Asia/Irkutsk" North Asia Standard Time "Asia/Irkutsk" North Asia Standard Time "America/Los_Angeles" Russian Standard Time "Europe/Moscow" SA Eastern Standard Time "America/Los_Angeles" SA Pacific Standard Time "America/Cayenne" SA Western Standard Time "America/La_Paz" Samoa Standard Time "Pacific/Apia" SE Asia Standard Time "Asia/Bangkok" Singapore Standard Time "Asia/Singapore" South Africa Standard Time "Asia/Singapore" South Africa Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Tokyo" Tokyo Standard Time "Asia/Tokyo"	Egypt Standard Time	"Africa/Cairo"
India Standard Time "Pacific/Honolulu" India Standard Time "Asia/Calcutta" Iran Standard Time "Asia/Jerusalem" Korea Standard Time "Asia/Jerusalem" Korea Standard Time "Asia/Seoul" Mountain Standard Time "America/Denver" N. Central Asia Standard Time "Pacific/Auckland" New Zealand Standard Time "America/St_Johns" North Asia East Standard Time "Asia/Irkutsk" North Asia Standard Time "Asia/Krasnoyarsk" Pacific SA Standard Time "America/Santiago" Pacific Standard Time "Europe/Moscow" SA Eastern Standard Time "America/La_Paz" Samoa Standard Time "Pacific/Apia" SE Asia Standard Time "Pacific/Apia" SE Asia Standard Time "Asia/Singapore" South Africa Standard Time "Asia/Singapore" South Africa Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Tokyo" "Asia/Tokyo"	GMT Standard Time	"Europe/London"
India Standard Time "Asia/Calcutta" Iran Standard Time "Asia/Jerusalem" Korea Standard Time "Asia/Jerusalem" Mountain Standard Time "Asia/Denver" N. Central Asia Standard Time "Asia/Novosibirsk" New Zealand Standard Time "Pacific/Auckland" Newfoundland Standard Time "Asia/Intusk" North Asia East Standard Time "Asia/Krasnoyarsk" Pacific SA Standard Time "America/Santiago" Pacific Standard Time "America/Los_Angeles" Russian Standard Time "America/Cayenne" SA Pacific Standard Time "America/La_Paz" Samoa Standard Time "Asia/Bangkok" Singapore Standard Time "Asia/Singapore" South Africa Standard Time "Asia/Singapore" South Africa Standard Time "Asia/Taipei" Tasmania Standard Time "Asia/Taipei" Tasmania Standard Time "Asia/Tokyo"	Greenland Standard Time	"America/Godthab"
Iran Standard Time "Asia/Jerusalem" Korea Standard Time "Asia/Jerusalem" Mountain Standard Time "America/Denver" N. Central Asia Standard Time "Asia/Novosibirsk" New Zealand Standard Time "Pacific/Auckland" Newfoundland Standard Time "America/St_Johns" North Asia East Standard Time "Asia/Krasnoyarsk" Pacific SA Standard Time "America/Santiago" Pacific Standard Time "America/Los_Angeles" Russian Standard Time "Europe/Moscow" SA Eastern Standard Time "America/Cayenne" SA Western Standard Time "America/La_Paz" Samoa Standard Time "Pacific/Apia" SE Asia Standard Time "Asia/Bangkok" Singapore Standard Time "Asia/Singapore" South Africa Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Taipei" Tasmania Standard Time "Australia/Hobart" Tokyo Standard Time "Asia/Tokyo"	Hawaiian Standard Time	"Pacific/Honolulu"
Israel Standard Time "Asia/Jerusalem" Korea Standard Time "Asia/Seoul" Mountain Standard Time "America/Denver" N. Central Asia Standard Time "Pacific/Auckland" New Zealand Standard Time "America/St_Johns" North Asia East Standard Time "Asia/Irkutsk" North Asia Standard Time "Asia/Krasnoyarsk" Pacific SA Standard Time "America/Santiago" Pacific Standard Time "America/Los_Angeles" Russian Standard Time "Europe/Moscow" SA Eastern Standard Time "America/Cayenne" SA Western Standard Time "America/La_Paz" Samoa Standard Time "Pacific/Apia" SE Asia Standard Time "Asia/Bangkok" Singapore Standard Time "Asia/Singapore" South Africa Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Taipei" Tasmania Standard Time "Asia/Tokyo"	India Standard Time	"Asia/Calcutta"
Korea Standard Time "Asia/Seoul" Mountain Standard Time "America/Denver" N. Central Asia Standard Time "Asia/Novosibirsk" New Zealand Standard Time "Pacific/Auckland" Newfoundland Standard Time "America/St_Johns" North Asia East Standard Time "Asia/Irkutsk" North Asia Standard Time "Asia/Krasnoyarsk" Pacific SA Standard Time "America/Santiago" Pacific Standard Time "America/Los_Angeles" Russian Standard Time "Europe/Moscow" SA Eastern Standard Time "America/Cayenne" SA Pacific Standard Time "America/Bogota" SA Western Standard Time "America/La_Paz" Samoa Standard Time "Pacific/Apia" SE Asia Standard Time "Asia/Bangkok" Singapore Standard Time "Asia/Singapore" South Africa Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Taipei" Tasmania Standard Time "Australia/Hobart" Tokyo Standard Time "Asia/Tokyo"	Iran Standard Time	"Asia/Tehran"
Mountain Standard Time "America/Denver" N. Central Asia Standard Time "Asia/Novosibirsk" New Zealand Standard Time "Pacific/Auckland" Newfoundland Standard Time "America/St_Johns" North Asia East Standard Time "Asia/Irkutsk" North Asia Standard Time "Asia/Krasnoyarsk" Pacific SA Standard Time "America/Santiago" Pacific Standard Time "Europe/Moscow" SA Eastern Standard Time "America/Cayenne" SA Pacific Standard Time "America/Bogota" SA Western Standard Time "America/La_Paz" Samoa Standard Time "Pacific/Apia" SE Asia Standard Time "Asia/Bangkok" Singapore Standard Time "Asia/Singapore" South Africa Standard Time "Asia/Singapore" South Africa Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Taipei" Tasmania Standard Time "Asia/Tokyo"	Israel Standard Time	"Asia/Jerusalem"
N. Central Asia Standard Time "Asia/Novosibirsk" New Zealand Standard Time "Pacific/Auckland" Newfoundland Standard Time "America/St_Johns" North Asia East Standard Time "Asia/Irkutsk" North Asia Standard Time "Asia/Irkutsk" Pacific SA Standard Time "America/Santiago" Pacific Standard Time "America/Los_Angeles" Russian Standard Time "Europe/Moscow" SA Eastern Standard Time "America/Cayenne" SA Pacific Standard Time "America/Bogota" SA Western Standard Time "America/La_Paz" Samoa Standard Time "Pacific/Apia" SE Asia Standard Time "Asia/Bangkok" Singapore Standard Time "Asia/Singapore" South Africa Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Taipei" Tasmania Standard Time "Australia/Hobart" Tokyo Standard Time "Asia/Tokyo"	Korea Standard Time	"Asia/Seoul"
New Zealand Standard Time "Pacific/Auckland" Newfoundland Standard Time "America/St_Johns" North Asia East Standard Time "Asia/Irkutsk" North Asia Standard Time "Asia/Krasnoyarsk" Pacific SA Standard Time "America/Santiago" Pacific Standard Time "America/Los_Angeles" Russian Standard Time "Europe/Moscow" SA Eastern Standard Time "America/Cayenne" SA Pacific Standard Time "America/Bogota" SA Western Standard Time "America/La_Paz" Samoa Standard Time "Pacific/Apia" SE Asia Standard Time "Asia/Bangkok" Singapore Standard Time "Asia/Singapore" South Africa Standard Time "Africa/Johannesburg" Sri Lanka Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Taipei" Tasmania Standard Time "Australia/Hobart" Tokyo Standard Time "Asia/Tokyo"	Mountain Standard Time	"America/Denver"
Newfoundland Standard Time "America/St_Johns" North Asia East Standard Time "Asia/Irkutsk" Pacific SA Standard Time "America/Santiago" Pacific Standard Time "America/Los_Angeles" Russian Standard Time "Europe/Moscow" SA Eastern Standard Time "America/Cayenne" SA Pacific Standard Time "America/Bogota" SA Western Standard Time "America/Bogota" SA Western Standard Time "Pacific/Apia" SE Asia Standard Time "Pacific/Apia" SE Asia Standard Time "Asia/Bangkok" Singapore Standard Time "Africa/Johannesburg" South Africa Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Taipei" Tasmania Standard Time "Australia/Hobart" Tokyo Standard Time "Asia/Tokyo"	N. Central Asia Standard Time	"Asia/Novosibirsk"
North Asia East Standard Time "Asia/Irkutsk" North Asia Standard Time "Asia/Krasnoyarsk" Pacific SA Standard Time "America/Santiago" Pacific Standard Time "America/Los_Angeles" Russian Standard Time "Europe/Moscow" SA Eastern Standard Time "America/Cayenne" SA Pacific Standard Time "America/Bogota" SA Western Standard Time "America/La_Paz" Samoa Standard Time "Pacific/Apia" SE Asia Standard Time "Asia/Bangkok" Singapore Standard Time "Asia/Singapore" South Africa Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Taipei" Tasmania Standard Time "Asia/Tokyo"	New Zealand Standard Time	"Pacific/Auckland"
North Asia Standard Time "Asia/Krasnoyarsk" Pacific SA Standard Time "America/Santiago" Pacific Standard Time "America/Los_Angeles" Russian Standard Time "Europe/Moscow" SA Eastern Standard Time "America/Cayenne" SA Pacific Standard Time "America/Bogota" SA Western Standard Time "America/La_Paz" Samoa Standard Time "Pacific/Apia" SE Asia Standard Time "Asia/Bangkok" Singapore Standard Time "Asia/Singapore" South Africa Standard Time "Africa/Johannesburg" Sri Lanka Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Taipei" Tasmania Standard Time "Australia/Hobart" Tokyo Standard Time "Asia/Tokyo"	Newfoundland Standard Time	"America/St_Johns"
Pacific SA Standard Time "America/Santiago" Pacific Standard Time "Europe/Moscow" SA Eastern Standard Time "America/Cayenne" SA Pacific Standard Time "America/Cayenne" SA Pacific Standard Time "America/Bogota" SA Western Standard Time "America/La_Paz" Samoa Standard Time "Pacific/Apia" SE Asia Standard Time "Asia/Bangkok" Singapore Standard Time "Asia/Singapore" South Africa Standard Time "Africa/Johannesburg" Sri Lanka Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Taipei" Tasmania Standard Time "Australia/Hobart" Tokyo Standard Time "Asia/Tokyo"	North Asia East Standard Time	"Asia/Irkutsk"
Pacific Standard Time "America/Los_Angeles" Russian Standard Time "Europe/Moscow" SA Eastern Standard Time "America/Cayenne" SA Pacific Standard Time "America/Bogota" SA Western Standard Time "America/La_Paz" Samoa Standard Time "Pacific/Apia" SE Asia Standard Time "Asia/Bangkok" Singapore Standard Time "Asia/Singapore" South Africa Standard Time "Africa/Johannesburg" Sri Lanka Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Taipei" Tasmania Standard Time "Australia/Hobart" Tokyo Standard Time "Asia/Tokyo"	North Asia Standard Time	"Asia/Krasnoyarsk"
Russian Standard Time "Europe/Moscow" SA Eastern Standard Time "America/Cayenne" SA Pacific Standard Time "America/Bogota" SA Western Standard Time "America/La_Paz" Samoa Standard Time "Pacific/Apia" SE Asia Standard Time "Asia/Bangkok" Singapore Standard Time "Asia/Singapore" South Africa Standard Time "Africa/Johannesburg" Sri Lanka Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Taipei" Tasmania Standard Time "Australia/Hobart" Tokyo Standard Time "Asia/Tokyo"	Pacific SA Standard Time	"America/Santiago"
SA Eastern Standard Time "America/Cayenne" SA Pacific Standard Time "America/Bogota" SA Western Standard Time "America/La_Paz" Samoa Standard Time "Pacific/Apia" SE Asia Standard Time "Asia/Bangkok" Singapore Standard Time "Asia/Singapore" South Africa Standard Time "Asia/Colombo" Sri Lanka Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Taipei" Tasmania Standard Time "Australia/Hobart" Tokyo Standard Time "Asia/Tokyo"	Pacific Standard Time	"America/Los_Angeles"
SA Pacific Standard Time "America/Bogota" SA Western Standard Time "America/La_Paz" Samoa Standard Time "Pacific/Apia" SE Asia Standard Time "Asia/Bangkok" Singapore Standard Time "Asia/Singapore" South Africa Standard Time "Africa/Johannesburg" Sri Lanka Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Taipei" Tasmania Standard Time "Australia/Hobart" Tokyo Standard Time "Asia/Tokyo"	Russian Standard Time	"Europe/Moscow"
SA Western Standard Time "America/La_Paz" Samoa Standard Time "Pacific/Apia" SE Asia Standard Time "Asia/Bangkok" Singapore Standard Time "Asia/Singapore" South Africa Standard Time "Africa/Johannesburg" Sri Lanka Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Taipei" Tasmania Standard Time "Australia/Hobart" Tokyo Standard Time "Asia/Tokyo"	SA Eastern Standard Time	"America/Cayenne"
Samoa Standard Time "Pacific/Apia" SE Asia Standard Time "Asia/Bangkok" Singapore Standard Time "Asia/Singapore" South Africa Standard Time "Africa/Johannesburg" Sri Lanka Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Taipei" Tasmania Standard Time "Australia/Hobart" Tokyo Standard Time "Asia/Tokyo"	SA Pacific Standard Time	"America/Bogota"
SE Asia Standard Time "Asia/Bangkok" Singapore Standard Time "Asia/Singapore" South Africa Standard Time "Africa/Johannesburg" Sri Lanka Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Taipei" Tasmania Standard Time "Australia/Hobart" Tokyo Standard Time "Asia/Tokyo"	SA Western Standard Time	"America/La_Paz"
Singapore Standard Time "Asia/Singapore" South Africa Standard Time "Africa/Johannesburg" Sri Lanka Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Taipei" Tasmania Standard Time "Australia/Hobart" Tokyo Standard Time "Asia/Tokyo"	Samoa Standard Time	"Pacific/Apia"
South Africa Standard Time "Africa/Johannesburg" Sri Lanka Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Taipei" Tasmania Standard Time "Australia/Hobart" Tokyo Standard Time "Asia/Tokyo"	SE Asia Standard Time	"Asia/Bangkok"
Sri Lanka Standard Time "Asia/Colombo" Taipei Standard Time "Asia/Taipei" Tasmania Standard Time "Australia/Hobart" Tokyo Standard Time "Asia/Tokyo"	Singapore Standard Time	"Asia/Singapore"
Taipei Standard Time "Asia/Taipei" Tasmania Standard Time "Australia/Hobart" Tokyo Standard Time "Asia/Tokyo"	South Africa Standard Time	"Africa/Johannesburg"
Tasmania Standard Time "Australia/Hobart" Tokyo Standard Time "Asia/Tokyo"	Sri Lanka Standard Time	"Asia/Colombo"
Tokyo Standard Time "Asia/Tokyo"	Taipei Standard Time	"Asia/Taipei"
	Tasmania Standard Time	"Australia/Hobart"
US Eastern Standard Time "America/Indianapolis"	Tokyo Standard Time	"Asia/Tokyo"
	US Eastern Standard Time	"America/Indianapolis"

Vladivostok Standard Time	"Asia/Vladivostok"
W. Australia Standard Time	"Australia/Perth"
W. Central Africa Standard Time	"Africa/Lagos"
W. Europe Standard Time	"Europe/Berlin"
West Asia Standard Time	"Asia/Tashkent"
West Pacific Standard Time	"Pacific/Port_Moresby"
Yakutsk Standard Time	"Asia/Yakutsk"

Searching for Columns

Search Columns allows you to immediately find a particular column in the data preview.


Enter the name of the column in the Search Columns box.




Delete the column name to discard the search and display all of the columns in the data preview.

Making a Duplicate of a Data Source

Click the **Duplicate** icon of a data source in the *Data Sources* list.



The data source is duplicated.



You can use some of the settings of the original data source and modify to create a new one.

Rearranging Data Sources


The order of the data sources in the Data Table Editor layout can be rearranged.


Steps:

1. Click on a data source you want to move.

The **Hand Hover** Y icon displays along with the blue marker before or after a data source where you can drop

4. Drag and drop the data source to the desired position.






■ Save 5. Click the Save button.

When saved, the notification displays.


Deleting Data Sources

Highlight a data source in the Data Sources panel and click .






A data source used in a joined data table can also be deleted.



After the data source is removed, the join is also deleted.



ADDING CALCULATED COLUMNS

NOTE

- User defined columns can only be added when there is an available data source.
- The user-defined columns are added in the topmost data source in the Data Sources list or in the joined or combined data source.
- An <u>auto key</u> can only be created once.
- Ranking requires a numeric source column.
- <u>Time bucketing</u> requires a time source column and each source column can only be used once.
- Numeric bucketing requires a numeric source column.
- <u>Text grouping</u> requires a text source column.
- The added user-defined column displays on the *Data Preview* with a pen symbol which allows its modification.


Adding an Auto Key Column

An automatic key field simply adds a new text column with a unique value for each row of the data source.

Steps:


1. On the Data Sources pane, click Calculated Columns.

The Calculated Columns pane displays.




2. Click New Column > Auto Key.


The auto key instance is displayed on *Connector Settings* with **Auto Key** as the default title.



- 3. You may opt to modify the auto key's Title.
- 4. Click Refresh Preview . The new auto key is added and displayed on the Data Preview.



As all visualizations show aggregated data through defined aggregations, the auto-key field can be used to display each individual row, and can be found in the data table:




Adding a Calculated Column

Create new columns based on calculations using data from existing columns in your data table.


In all cases, this new column is calculated for every row in the data set.

Steps:

- On the Data Sources pane, click Calculated Columns.
 The Calculated Columns pane displays.
- 2. Click New Column > Calculated.




The Numeric Calculated Column pane displays.



- 3. Fill in the Title field.
- 4. Check the Set Type Manually box. The Type drop-down list box is enabled.



5. Select either:




Numeric

The most common type of calculation that allows creation of new numeric columns.

Text

Allows new text columns to be created based on input string manipulation.



NOTE

Other types of calculations include:

- <u>Time Series Calculation</u>
- <u>Time Window Calculation</u>
- <u>Time Period Calculation</u>
- 6. Build an expression by double-clicking in the list of available Functions and Columns.



You can also use parameters in the expression.

To search for a particular column or function, enter it in the Search Columns/Search Functions box.



Or enter one or more characters/alphabets into the *Search Columns* box and the suggested list of columns that matched the entries will be displayed.

For example, after entering 1, the list will be displayed such as below:



- 7. Set the designed display Format (for example 0.0 %).
- 8. Click Validate to validate the formula.
- 9. Click Refresh Preview . The new calculated column is added and displayed in the Data Preview.

Numeric Calculations

Numeric calculations allow new numeric columns to be created.

They typically use one or more of the following operators:

Operator	Name	Description
!	Logical NOT	Logical NOT.
%	Integer Division	Integer Division
&	Logical AND	Logical AND.
*	Multiply	Multiplies two numbers.
+	Add	Adds two numbers.
-	Subtract	Subtracts two numbers.
/	Divide	Divides two numbers.
<=	Less than or equals	Less than or equals to.
<>	Not Equals	Not Equals.
=	Equals	Equals.
>=	Greater than or equals	Greater than or equals to.
٨	Raises to the power	Raises number to the power of number2, number1 ^ number2.
1	Logical OR	Logical OR

And one or more of the following functions:

Function	Description
ABS	Absolute value, which can be used as ABS(X).
ATAN	ArcTangent function which can be used as ATAN(X).
CEIL	Ceiling function. Examples: CEIL(-3.2) = -3, CEIL(3.2) = 4.
cos	Cosine function which can be used as COS(X), where X is a real-type expression. COS returns the cosine of the angle X in radians.
COSH	Cosine Hyperbolic function which can be used as COSH(X).
COTAN	Cotangent function which can be used as COTAN(X).
EXP	Exponential function which can be used as EXP(X).
FLOOR	Floor function. Examples: FLOOR(-3.2) = -4, FLOOR(3.2) = 3.
HEX2DEC	Converts a hexadecimal number to decimal. Example: HEX2DEC("FF") = 255
IF	Conditional Statement The IF(b, case1, case2) function provides branching capability. • If b is True, then it returns case 1.

	If b is False, then it returns case 2.
	If b is a numeric value 1, it is equal to True.
	If b is a numeric value 0, it is equal to False.
	NOTE: By default, the function returns a value of data type Text. To force the data type to numeric, you can either use "Set type manually" or do a calculation with a numeric value, such as multiply by 1.
	Examples: IF([Actual] >= [Budget], "Good job", "Not done") IF([Some_Number] = 0, 0, 1/[Some_Number])*1
INTPOW	Raises Base to an integral power. Example: INTPOW(2, 3) = 8. Note that the result of INTPOW(2,3.4) = 8 as well.
ISNULL	If the measure Is Null or NaN, then 1 is returned, else 0 is returned.
LN	Natural Log which can be used as LN(X).
LOG	10 Based Log which can be used as LOG(X).
LOGN	The LogN function returns the log base N of X. Example: LOGN(10, 100) = 2
MAX	Maximum of two input values. Example: MAX(2, 3) = 3
MIN	Minimum of two input values. Example: MIN(2, 3) = 2
MOD	Remainder of division. Example: MOD(7, 3) = 1
POW	Raises Base to any power. For fractional exponents or exponents greater than MaxInt, Base must be greater than 0.
RANDOM	RND(X) generates a random INTEGER number such that $0 \le \text{Result} \le \text{int}(X)$. If X is negative, then result is $\text{int}(X) \le \text{Result} \le 0$. RANDOM(X) generates a random floating point number such that $0 \le \text{Result} \le X$. If X is negative, then result is $X \le \text{Result} \le 0$.
REGEX_EXTRACT	Returns matching data from the value based on regex. Expression is REGEX_EXTRACT("value", "regex")
REGEX_EXTRACT_GROUP	Like the REGEX_EXTRACT function, apart from the third "group" parameter, which defines which group, as defined by the regex expression, to return. Group is a string parameter and can contain either an integer value or a group name. Examples:
	 REGEX_EXTRACT_GROUP("some123", "([a-z]*)(\d*)", "1") = "some" REGEX_EXTRACT_GROUP("some123", "([a-z]*)(\d*)", "2") = "123"
SIGN	SIGN(X) returns -1 if X<0; +1 if X>0, 0 if X=0; it can be used as SQR(X).
SIN	Sinus function which can be used as SIN(X), X is real-type expression. SIN returns the sine of the angle X in radians.
SINH	Sine Hyperbolic function which can be used as SINH(X).

SQR	Square function which can be used as SQR(X).
SQRT	Square Root function which can be used as SQRT(X).
TAN	Tangent function which can be used as TAN(X).
TRUNC	Discards the fractional part of a number. Examples: TRUNC(-3.2) = -3 and TRUNC(3.2) = 3

Calculation Aggregation

Calculation aggregation is sometimes needed with calculated columns.

If the calculation aggregate is used, any calculated columns will be re-executed up the hierarchy, so that the calculation is done on group-level aggregates instead of row-level values. Furthermore, each term in the calculation will be summed by default, but this can be controlled if a different aggregation is needed.

The aggregation applied to each column included in the calculation expression can be specified using the following syntax:

[term:aggregate]

For example:

[exposure:sum]/[risklimit:mean]

[exposure]/[risklimit:mean] also has the same result since no aggregation specified defaults to sum.

NOTE

Most of the Panopticon aggregation methods are supported, except those that involve more than one column.

You can specify any of the following functions:

abs
abssum
count
countdistinct
countnonzero
harmonicmean
level
max
mean
min
neg
percentofweightparent
percentoftotalreference
pos
product
siblingrank

_		
	std	ΔV
_	อเน	-

- □ stdevp
- □ sum

Text Calculations

Text calculations allow new text columns to be created based on input string manipulation.

They typically use one or more of the following operators:

Function	Description	
CONCAT	Concatenates two strings together.	
DEC2HEX	Converts a decimal number to hexadecimal. Example: DEC2HEX(255, 2) = "FF"	
FIND	Returns the starting position of a text string within another text string.	
IFTEXT	Returns a string based on the expression being evaluated to true or false.	
LEFT	Returns the left most characters from a string producing a new string.	
LEN	Returns the number of characters in a string.	
LOWER	Returns the input string in lower case.	
MID	Returns the characters from the middle of a text string, given a starting position and length.	
PROPER	Converts a text string to proper case; the first letter in each word in uppercase, and all other letters in lower case.	
REPLACE_ALL	Replaces all of the instances of the pattern_to_replace with the replacement_text. For example: replace_All(input_text, pattern_to_replace, replacement_text) replace_All("ABA", "A", "X") = "XBX" NOTE: Only input_text may be null. Special cases: If input_text is null, the result is null. If pattern_to_replace is empty, it's considered to occur at every position in the input_text (including before the first and after the last character).	
REPLACE_FIRST	Replaces the first instance of the pattern_to_replace with the replacement_text. For example: Replace_First(input_text, pattern_to_replace, replacement_text) Replace_First("ABA", "A", "X") = "XBA" NOTE: Only input_text may be null. Special cases: If input_text is null, the result is null. If pattern_to_replace is empty, it's considered to occur at every position in the input_text (including before the first and after the last character).	

RIGHT	Returns the right most characters from a string producing a new string.
TRIM	Returns the input string stripped of leading or following spaces.
UPPER	Returns the input string in upper case.

In addition, the **IF** calculation can be used on text inputs to define the condition, to produce numeric output. Example: IF([SIDE]="BUY",[SIZE],-[SIZE])

Calculation Data Type

The data type of a calculation will default to text if a text column is used in the calculation.	This type can be set
manually by checking the "Set type manually" checkbox.	

Set type manually			
And then picking the a	pprop	oriate output data type.	
Set type manually	4	Numeric	¥

Asymmetric Reporting

An asymmetric report combines the values of two dimensions or text columns. The combination of these two fields through the text concatenation provides greater flexibility for visual display, whether in a hierarchy, on a text axis, or through cross tabbing into rows and columns.

Time Series Calculations

Calculated fields can be:

numeric columns or numeric time series

text time series

If one of the expressions used is a time series measure, then the result will be a new numeric time series calculated column.

As with standard calculated columns, time series calculated columns are calculated for every time slice and every item within the data set.

Example Numeric Calculations

```
Forecast Variance = ( [Actual] - [Forecast] ) / [Forecast]
Holding = [NumberofShares] * [LastPrice]
```

Example Text Time Series Calculation

time	anger	joy	sad
10/12/2020 00:00:00	20.00	100.00	0.00
10/12/2020 00:00:00	60.00	50.00	20.00
10/12/2020 00:00:00	80.00	10.00	30.00
10/12/2020 00:00:00	40.00	0.00	60.00

Sample fields

Transforming to enable time series, the time axis values will be based on the time column.

Sample expression for the calculated text column **Dominant**, calculates emotion with highest value at each time point:

```
IFTEXT(([anger] > [joy]) & ([anger] > [sad]), "Anger", IFTEXT([joy] > [sad],
"Joy", "Sadness"))
```

NOTE

- Text time series columns (calculated or not) cannot be used in the breakdown.
- When the time series transform is switched off in time series calculation columns, an error message will be displayed "Can't use time series functions, the time series transform is not enabled." Switch the time series transform on to fix the issue.

Time Window Calculations

Time Window calculations allow new columns to be created that are based on a defined time window.

There are several additional functions:

Function	Description
COUNT_TIMEWIN	Like SUM_TIMEWIN, but simply returns the number of time slices between the defined time window, that have non-null values.
CUMSUM_TIMEWIN	The cumulative sum of Time Series value between start and end times. Alias for SUM_TIMEWIN("Measure",TimeWindowStart,Now).
LOOKUP	The value of a Time Series measure at a specific time.
MAX_TIMEWIN	The maximum value between the start and end times.
MEAN_TIMEWIN	The mean value of the Time Series between the start and end times.
MIN_TIMEWIN	The minimum value between the start and end times.
NOW	Returns the system Date/Time in default or provided format. Example: NOW() or NOW("yyyy MMM dd HH:mm:ss").
PRODUCT_TIMEWIN	The product of the Time Series values between the start and end times.
STDEV_TIMEWIN	The standard deviation of the time series between the start and end times.
STDEVP_TIMEWIN	The population standard deviation of the time series between the start and end times.
SUM_TIMEWIN	The sum of Time Series values between start and end times.

And three additional measures:

Function	Description
SnapshotTime	The time slice at the Snapshot Time
TimeWindowEnd	The Time slice at the end of a time window
TimeWindowStart	The Time slice at the start of a time window

NOTE When using Time Windows calculations, fields referenced by the calculation should be enclosed in double quotes and NOT square brackets.

For example, using the Time Series column **PRICE**, the following calculations can be created:

Function	Description
Difference Between Start and End of Time Window	LOOKUP("PRICE",TimeWindowStart)-LOOKUP("PRICE",TimeWindowEnd)
Time Window Maximum value across	MAX_TIMEWIN("PRICE", TimeWindowStart, TimeWindowEnd)
Time Window Standard Deviation	STDEV_TIMEWIN("PRICE", TimeWindowStart, TimeWindowEnd)
Variance since Time Window Start	([PRICE] - LOOKUP("PRICE",TimeWindowStart)) / LOOKUP("PRICE",TimeWindowStart)

Time Period Calculations

Time Period calculations are like Time Window calculations but relative to the current time slice.

Function	Description
CONTINUE_NPREV	Checks if there was a value in a previous time slice, N time slices back, and a value for the current time slice. When you have the case "previous had value, and current has a value", this function returns 1. Otherwise, it returns 0.
	One use case can be to "mark" that a series has a value (not NULL) in the current time slice, when it also had a value in a previous time slice.
	CONTINUE_NPREV is related to LEAVE_NPREV and JOIN_NPREV.
COUNT_NPREV	Returns the number of non-null time slice values across the defined range. Otherwise, returns 0.
DATEADD	Adds an integer value to a specified DATEPART of an input date value, returning the modified value. Valid DATEPART values are YEARS, MONTHS, DAYS, HOURS, MINUTES, SECONDS, MILLISECONDS, MICROSECONDS, and NANOSECONDS.
DATEDIFF	The count of the specified DATEPART boundaries crossed between the specified StartDate and EndDate.
	Valid DATEPART values are YEARS, MONTHS, DAYS, HOURS, MINUTES, SECONDS, MILLISECONDS, MICROSECONDS, and NANOSECONDS.

DATEDIFF2 The total amount of elapsed time between the StartDate and EndDate expressed in a given unit. Valid DATEPART values are YEARS, MONTHS, DAYS, HOURS, MINUTES. SECONDS, MILLISECONDS, MICROSECONDS, and NANOSECONDS. DATEDIFF_TO_NOW The total amount of elapsed time from Date until NOW expressed in given Valid DATEPART values are YEARS, MONTHS, DAYS, HOURS, MINUTES, SECONDS, MILLISECONDS, MICROSECONDS, and NANOSECONDS. DATEDIFF TO TODAY The total amount of elapsed time from Date until Today(start of day) expressed in given unit. Valid DATEPART values are YEARS, MONTHS, DAYS, HOURS, MINUTES, SECONDS, MILLISECONDS, MICROSECONDS, and NANOSECONDS. **DELTA_NPREV** Alias for "Measure"-NPREV("Measure",number). Calculates the change from the value N time slices previous, to the current value. For example, the current time slice counts as 1, the preceding as 2 and the next as 3 time slices previous. That way, the function always considers N consecutive time slices/values – not N consecutive spaces between values. So, if the current value is 2, and the value three steps back (counting the current value as 1) was 5, then DELTA_NPREV is -3. DELTA NPREV is related to DELTA PCNT NPREV DELTA PCNT NPREV Alias for "Measure"/NPREV("Measure",number)-1. Works exactly like DELTA NPREV, but instead of delivering the nominal value of Value(N=3)-Value(N=1), it calculates the difference divided by Value(N=3), For example, moving from 5 to 2 gives you DELTA=-3 and DELTA PCNT = -0.60 (-3/5). DELTA PCNT NPREV is related to DELTA PCNT. FALL NPREV Detects if a series has had a decreasing value when comparing the current time slice to a previous time slice. If the current value was lower, then the function returns 1. Otherwise, it returns 0. FALL NPREV is related to GAIN NPREV. GAIN NPREV Detects if a series has had an increasing value when comparing the current time slice to a previous time slice. If the current value was higher, then the function returns 1. Otherwise, it returns 0. GAIN NPREV is related to FALL NPREV. JOIN NPREV Checks if there was a null value in a previous time slice. N time slices back. while there is a value for the current time slice. When you have the case "previous was NULL, and current has value", this function returns 1. Otherwise, it returns 0. One use case can be to "mark" that a series had a NULL in a previous time JOIN NPREV is related to LEAVE NPREV and CONTINUE NPREV. LEAVE NPREV Check if there was a value in a previous time slice, N time slices back, while there is NULL for the current time slice. When you have the case "previous had value, and current is NULL", this function returns 1. Otherwise, it returns One use case can be to "mark" that a series has a NULL in the current time slice, when it had a value in a previous time slice. LEAVE NPREV is related to JOIN NPREV and CONTINUE NPREV. MAX NPREV The maximum value of current time and the value n time slices before that.

MIN_NPREV	The minimum value of current time and the value n time slices before that.
NPREV	The value of a measure n time slices previous of the current time.
PRODUCT_NPREV	The product of the values n time slices previous of the current time.
	The Simple Moving Average for the n time slices up to and including the current time slice.
	Alias for SUM_NPREV("Measure",number)/number.
STDEV_NPREV	Calculates the standard deviation for a number of preceding time slices.
_	Calculates the population standard deviation for a number of preceding time slices.
SUM_NPREV	The sum of the values n time slices up to and including the current time slice.
TO_POSIX	Converts timestamp values to posix.
TO_POSIXMILLIS	Converts timestamp values to posixmillis.
_	If input date is within the period compared to the current timestamp, then the measure is returned, otherwise null is returned.
	Usage Example:
	withinperiod(period, date, measure)
	where period is either of ["WTD", "MTD", "QTD", "YTD"]
	"WTD" = week to date
	"MTD" = month to date
	"QTD" = quarter to date
	"YTD" = year to date

NOTE

When using Time Period calculations, fields referenced by the calculation should be enclosed in double quotes and NOT square brackets.

For example, using the Time Series column **PRICE**, the following calculations can be created,


Change in Price compared to previous time slice	[PRICE] - NPREV("PRICE",1)
Change in Price compared to 5 time slices previously	[PRICE] - NPREV("PRICE",5)
% Change in Price compared to Previous Time slice	([PRICE] - NPREV("PRICE",1)) / NPREV("PRICE",1)
5 Period Moving Average	SUM_NPREV("PRICE",5)/5
20 Period Moving Average	SUM_NPREV("PRICE",20)/20

Parameterization in Calculated Columns

Given Table 1:


Group	Name	Value
X	Α	2.00
X	В	3.00
Υ	С	4.00

Creating a new numeric parameter **X** with a value of **7**:



Then adding calculated columns AddOne = [Value] + 1 and AddX = [Value] + {X} will result to:

Group	Name	Value	AddOne	AddX
X	А	2.00	3.00	9.00
X	В	3.00	4.00	10.00
Υ	С	4.00	5.00	11.00



Sample 1


Below is the defined breakdown in a Table visualization:




This Table visualization is showing the grouping of the columns based on the breakdown hierarchy with **AddOneSum**, **AddXsum**, **AddOneCalc**, **AddXCalc** as Visual Members with the corresponding aggregates and the **X** value is set to **7**:

Column	Aggregate		
Value	Sum		
AddOneSum	Sum		
AddXSum	Sum		
AddOneCalc	Calculation		
AddXCalc	Calculation		





Adding an *Action Dropdown* in the dashboard with a **Set Parameter** mode:




And given Table 2:


Value	
	0
	1
	7
	12

Will result to these Table values:





Set X 1 ▼



X=1

國 🗸






Group Name **							
		Value	AddOneSum	AddXSum	AddOneCalc	AddXCalc	
_X	A	2.00	3.00	14.00	3.00	14.00	
	В	3.00	4.00	15.00	4.00	15.00	
X Total		5.00	7.00	29.00	6.00	17.00	
_Y	С	4.00	5.00	16.00	5.00	16.00	
Y Total		4.00	5.00	16.00	5.00	16.00	
Grand Tota	al	9.00	12.00	45.00	10.00	21.00	

Adding Ranking Columns


Adding a new ranking column requires a numeric source column.

Steps:


- On the *Data Sources* pane, click **Calculated Columns**.
 The *Calculated Columns* pane displays.
- 2. Click New Column > Ranking.



The *Ranking Column* pane displays which lets you create new numeric columns based on ranking other columns in your data source. The rank is calculated for each row across each time period.



- 3. Fill in the Title field.
- 4. Select a numeric Source Column.
- Define whether the column should be ranked:
 - Ascending
 - Descending
- 6. Click Refresh Preview . The new ranking column is added and displayed in the Data Preview.




Adding Time Buckets – Categorical Time Analysis

Time based data can be represented as continuous Time Series and displayed in time series visualizations such as the Line Graph. However, there are circumstances when data analysis does not require continuous time, but instead requires time grouping and aggregation. Time parts support this categorical use of time.


To group and aggregate time-based data, a Date/Time column should be present in the data table.

Steps:


- On the Data Sources pane, click Calculated Columns.
 The Calculated Columns pane displays.
- 2. Click New Column > Time Bucket.



The Date/Time column (e.g., **Maturity Date**) that will be used for the time bucketing is displayed under the *Calculated Columns* pane and the *Time Bucket Column* pane also displays.



- 3. Enter the Title Prefix.
- 4. Enter the Title Suffix.
- Select the required time buckets.
- 6. Click Refresh Preview . The new time bucketing column is added and displayed in the Data Preview.



This process adds additional text columns to the data table which can be used in:

- Hierarchies / Breakdowns
- Filters
- Color Variables
- Detail Variables


Once selected the new time bucket columns will appear in the data table schema listing.

As an example, the data set below relates to a EURO dominated Bond universe:


Each individual bond represents a row within the data set and has associated properties represented by each column.

The Maturity Date represents the date to which the Bond matures.


By creating the Year Time Part, a Bar graph of Maturity Year can be displayed:



Similarly using the Month Time Part, a Bar graph of cumulative issuance by Month can be displayed:



Using the ISODate Time Part, a Bar graph of cumulative issuance by ISO Date can be displayed.



Adding Identity Bucketing


Numeric data is represented as a continuous set of values in displays and filters. However, there are circumstances when the numeric values are not continuous, but instead discrete categories, to be grouped and filtered upon.

Numeric fields can be converted into text in the underlying data repository, but then sort order is treated as text, rather than numeric.


To group and aggregate numeric data, numeric columns should be present in the data table.

Steps:

- On the Data Sources pane, click Calculated Columns.
 The Calculated Columns pane displays.
- 2. Click New Column > Numeric Bucket.




The numeric bucket instance is displayed on the *Data Sources Settings* with **Numeric Bucket** as the default title, also the *Numeric Bucket Column* pane displays.



You may opt to modify the numeric identity bucket Title.


3. Select **Id** in the *Bucketing Mode* drop-down list box.

Numeric Bucket Column





- 4. Select the numeric Source Column and Format.
- 5. Click Refresh Preview . The new numeric identify bucket column is added and displayed in the Data Preview.



These new identity columns can then be used as categories in the breakdown, and as categorical filters:





Adding Numeric Sign Bucketing


Numeric data is represented as a continuous set of values in displays and filters. Sometimes it may be necessary to divide the data into positive and negative subsets. This can be achieved with Sign bucketing.

Steps:

- On the Data Sources pane, click Calculated Columns.
 The Calculated Columns pane displays.
- 2. Click New Column > Numeric Bucket.



The numeric bucket instance is displayed on the *Data Sources Settings* with **Numeric Bucket** as the default title, also the *Numeric Bucket Column* pane displays.



You may opt to modify the numeric sign bucket Title.


3. Select the numeric Source Column.

Numeric Bucket Column




4. Select **Sign** in the *Bucketing Mode* drop-down list box.

Numeric Bucket Column



5. Click Refresh Preview . The new numeric sign bucket column is added and displayed in the Data Preview.



Adding Numeric Equal Distance Bucketing

Numeric data is represented as a continuous set of values in displays and filters. Sometimes it may be necessary to divide the data into equal sized bucket subsets.

For example, for the 1 Day Change %(USD) column, the minimum value is -0.35 and the maximum value is 0.21 when you specify 2 buckets, the equal distance ranges will be the following:

-0.35, -0.07

-0.07, 0.21

Meanwhile, if you specify 3 buckets, the equal distance ranges will be the following:

-0.35, -0.17

□ -0.17, 0.02

□ 0.02, 0.21


These can be achieved with Equal Distance bucketing and is commonly used when producing histograms.

Steps:


1. On the Data Sources pane, click Calculated Columns.

The Calculated Columns pane displays.

2. Click New Column > Numeric Bucket.




The numeric bucket instance is displayed on the *Data Sources Settings* with **Numeric Bucket** as the default title, also the *Numeric Bucket Column* pane displays.



You may opt to modify the numeric equal distance bucket Title.

- 3. Select the numeric Source Column.
- 4. Select **Equal Distance** in the *Bucketing Mode* drop-down list box.

Numeric Bucket Column




Numeric Bucket Column




- 5. Enter the Number of Buckets. This value can be parameterized.
- 6. Tap the Manual Bucket slider to turn it on.

The Names text box are enabled. For this example, 2 text boxes are available based on the specified Number of Buckets in step 5.



- Enter the bucket Names.
- 8. Click Refresh Preview . The new numeric equal distance bucket column is added and displayed in the Data Preview.



This new user defined column can be used in a visualizations breakdown to display data samples.



Adding Numeric Manual Bucketing

Numeric data is represented as a continuous set of values in displays and filters. Sometimes it may be necessary to manually specify customized limits. This can be achieved with Manual bucketing.

Steps:


1. On the Data Sources pane, click Calculated Columns.

The Calculated Columns pane displays.

2. Click New Column > Numeric Bucket.




The numeric bucket instance is displayed on the *Data Sources Settings* with **Numeric Bucket** as the default title, also the *Numeric Bucket Column* pane displays.




You may opt to modify the numeric manual bucket Title.

- 3. Select the numeric Source Column.
- 4. Select **Manual** in the *Bucketing Mode* drop-down list box.



Numeric Bucket Column




The Limits and Bucket Name fields are displayed.

- 5. Specify the customized limits of a bucket:
 - Enter the *Infinity* value in the *Limits* box with the minimum limit value of the bucket.

+ Interval

This value is displayed in the *Bucket Name* box replacing the **-Infinity** value.






• Enter the *Infinity* value in the *Limits* box with the maximum limit value of the bucket.

This value is displayed in the Bucket Name box replacing the Infinity value.

Numeric Bucket Column






The range of the limits is now displayed in the *Bucket Name* box.

- You can opt to modify the Bucket Name.
- 6. To add more buckets, click

 Another bucket definition box is displayed.




Note that the preceding Infinity bucket value is now the minimum limit value of the new bucket.

7. Replace the *Infinity* value in the *Limits* box with the maximum limit value of the new bucket.

This value is displayed in the Bucket Name box replacing the Infinity value.


Numeric Bucket Column




To delete manual bucket range limits, click their corresponding button. The *Bucket Name* value is adjusted based on the available limits.

8. After you are done adding buckets, click Refresh Preview . The new numeric manual bucket column is added and displayed in the Data Preview.

The new Manual bucket column will appear in the output data schema.



This new user defined column can be used in a visualizations breakdown to display data samples.




Adding Numeric Equal Density Bucketing


Numeric data is represented as a continuous set of values in displays and filters. Sometimes it may be necessary to divide the data into equal density bucket subsets. This can be achieved with equal density bucketing.

Steps:

- On the Data Sources pane, click Calculated Columns.
 The Calculated Columns pane displays.
- 2. Click New Column > Numeric Bucket.




The numeric bucket instance is displayed on the *Data Sources Settings* with **Numeric Bucket** as the default title, also the *Numeric Bucket Column* pane displays.




You may opt to modify the numeric equal density bucket Title.

- 3. Select the numeric Source Column.
- 4. Select **EqualDensity** in the *Bucketing Mode* drop-down list box.

Numeric Bucket Column






- 5. Enter the Number of Buckets. This value can be parameterized.
- 6. Tap the Manual Bucket slider to turn it on.

The Names text box are enabled. For this example, 3 text boxes are available based on the specified Number of Buckets in step 5.




- 7. Enter the bucket Names.
- 8. Click Refresh Preview . The new numeric equal density bucket column is added and displayed in the Data Preview.



For this example, the minimum value of the Source Column (1 Day Change %) is -0.35 and the maximum value is 0.12. When there are three buckets, the ranges will be:

- Range1: -0.11, -0.03
- Range2: -0.03, -0.01
- Range3: -0.01, 0.09

This can then be used in a visualizations breakdown to display data samples.



Adding Text Groupings


New custom text groupings can be dynamically added to a data source.

Steps:

- On the *Data Sources* pane, click **Calculated Columns**.
 The *Calculated Columns* pane displays.
- 2. Click New Column > Text Grouping.



The text grouping instance is displayed with the default title (e.g., **Region Groups**) based on the initially selected *Source Column* (e.g., **Region**) on the *Text Grouping Column* pane.




+ Mapping


You may opt to modify the text group column Title.

3. Select a Source Column.


4. Proceed to adding the custom text groups by clicking A new instance of a grouping is displayed.



5. Click this instance and define the Values and Groups.




6. Continue adding the Values and Groups.



Values not mapped to a group, will be assigned the input value.

7. Click Refresh Preview . The new text grouping column is added and displayed in the Data Preview.



These new custom group columns can be used identically to a source text column, categorizing and filtering data.


Modifying User-Defined Columns

A generated column can be modified.

Steps:

- 1. Modifying user-defined columns can be done either by clicking:
 - the Edit button of a generated column title in the Data Preview
 - the Calculated Columns button on the Data Sources Settings pane and clicking the generated column to be modified.

The corresponding user-defined settings is displayed.



2. Modify the properties or settings and click




to save the changes.

Creating a Duplicate of a Calculated Column

Make a copy of a generated calculated column and modify to create a new one.


Steps:

1. On the Data Sources Settings, click Calculated Columns to display the available user-defined columns.



Click the **Duplicate** button of a Calculated Column.

A copy of the duplicated calculated column is displayed on the Calculated Column pane.




- 3. You can opt to modify the properties of the duplicate column.
- 4. Click Refresh Preview . The duplicate calculated column is added and displayed in the Data Preview.

Removing User-Defined Columns

Generated columns can be deleted.

Steps:

- 1. Deleting user-defined columns can be done either by clicking:
 - the Edit button of a generated column title in the Data Preview.
 The user-defined column settings are displayed.
 - the Calculated Columns button on the Data Sources Settings pane
 The list of user-defined columns is displayed.



2. Click and Save to delete the user-defined column and save the changes.

DATA TABLE COLUMNS SETTINGS

The Columns pane in the Data Table Editor layout allows:

- modification of the column names
- modification of the numeric or Date/Time format
- □ setting the <u>numeric default aggregation</u>
- □ setting the Min and Max range of numeric columns
- creating a <u>custom sort order</u>




Modification of the Column Names


The name of columns retrieved from the data source can be modified.

Steps:

- 1. On the Data Sources panel, click a data source to display its settings.
- 2. Click Columns. The Columns pane displays with the list of available columns in the data source.




3. Select the column name or names that you want to modify, then enter the new name and click \checkmark .



Once the column name is modified, the button is displayed. Click this button to revert to the original column name.

4. Click Refresh Preview . The new column names are displayed on the Data Preview.




Modification of the Numeric or Date/Time Column Format

The format of the numeric or Date/Time columns retrieved from the data source can be modified.


Steps:

- 1. On the Data Sources panel, click a data source to display its settings.
- 2. Click Columns. The Columns pane displays with the list of available columns in the data source.




3. Click the drop-down list and select the *Format* for the numeric or Date/Time column.

NOTE The checkbox for numeric or Date/Time columns are enabled and can be selected.




To modify the format of several numeric and/or Date/Time columns, check their corresponding boxes. The *Default Display Format* drop-down list is enabled.



You can either:

 select a format in the Default Display Format drop-down list. This format will be applied to all the checked columns.



modify the format for each checked column. The Default Display Format value will be Mixed. Connector Settings Transform settings Columns Q Filter by title All types ∜ Title Type Default Display Max Custom Sort Aggregation Order Region Text Country Text Exchange Text Name Symbol Text ISIN Text SEDOL Text Close(local) Numeric * \$#,##0 Sum Mcap(local) Numeric * #,##0.00 Sum Mcap(USD) #,##0.001 * Sum Industry Text Supersector 1 Day Close Numeric * #.##0.00 1 Week Close #,##0.00 2 Week Close Numeric * #,##0.00 Sum 1 Month Close Numeric * #,##0 ٥ Sum

Once the column format is modified, the $^{\circ}$ button is displayed. Click this button to revert to the original column format.

Sum

Refresh Preview 4. Click . The new column format is applied and displayed on the Data Preview.

#,##0.00


#,##0.00

2 Month Close

3 Month Close

Numeric *

Numeric *




Setting the Default Aggregation for Numeric Columns


Setting the default <u>aggregation</u> of numeric columns can be done on the *Columns* pane of the *Data Table Editor* layout.

Steps:


- 1. On the Data Sources panel, click a data source to display its settings.
- 2. Click Columns. The Columns pane displays with the list of available columns in the data source.



3. Click the drop-down list and select the *Default Aggregation* for the numeric columns. Default is **Sum**.





To modify the default aggregation of several numeric columns, check their corresponding boxes. The *Default Aggregation* drop-down list is enabled.




You can either:

 select an aggregation in the Default Aggregation drop-down list. This aggregation will be applied to all the checked columns.








To revert to the default original default aggregation (\mathbf{Sum}), click $^{\circ}$.

4. Click Refresh Preview . The new default aggregation for the numeric column is applied and displayed on the Data Preview.




Setting the Min and Max Range for Numeric Columns

Setting the *Min* and *Max* values, for the **Fixed Range** of X and Y variables in visualizations, can be done on the *Columns* pane of the *Data Table Editor* layout.

For example, these numeric columns or fields have the following fixed Min and Max ranges:

Column	Min	Max
Age	4	12
Start	1	5
End	6	10


On the visualization, when the **Age** column is dragged to the X variable, the *Min* and *Max* values are applied.




Follow the steps below to modify the *Min* and *Max* fixed range.

Steps:


1. On the Data Sources panel, click a data source to display its settings.



2. Click Columns. The Columns pane displays with the list of available columns in the data source.




3. To set the fixed range for a single numeric column, enter the *Min* and *Max* values.



To set the fixed range for several numeric columns, check their corresponding boxes and enter their *Min* and *Max* values.

For example:


Column	Min	Max
Age	6	10
Start	2	4
End	6	8



4. Click the **Save** button.

When saved, the notification displays.


On the visualization, when the **Age** column is dragged to the *X* variable, the set *Min* and *Max* values are applied.




Filtering Data Source Columns

You can limit the data source columns that are being displayed by:


entering the title of a particular column into the Filter by Title box.




entering one or more characters into the Filter by Title box and the suggested list of columns that matched the entries will be displayed.



□ clicking the *All Types* drop-down list and checking the box of the data column type.



The data columns that matched the selected type are displayed.



DATA STORAGE

Data storage depends on the data table type (Published, Saved and so on), and the connection type (Database, Excel, CSV, and so on). Specifically:

- Database (relational and tick history) or Message Queue
 - No physical data storage.
- □ Flat Files (Excel, CSV, Text, XML and SVG)

If configured as a saved data table / workbook, no copy of the spreadsheet is made; instead, the path to the original file is stored, allowing updates to be accessed.

If the data table / workbook is published, a snapshot of every defined Excel spreadsheet is copied to the server. To update a **published** spreadsheet, the data table must be again connected to the source spreadsheet and then re-published.

[4] THE DATA LIBRARY PAGE


The *Data Library* page allows creation and management of reusable data tables outside workbooks. Data tables from the data library can be used by multiple workbooks server wide.

Some important concepts to remember:

- Bringing data inside workbooks is done through data tables.
- A data table contains metadata for data source connection settings, data query, schema definition, calculated columns, transforms, etc.
- One data table can use only one data connector to connect to a data source.
- ☐ Two or more data tables can be joined to create a new joined data table.
- Data table permissioning and sharing between users or groups is done similarly like workbooks (i.e., using folder tree).
- There are four types of data tables. The first three resides at the Data Library, the fourth one, called **linked data tables**, will be part of workbooks and will reference one of the three types from Data Library.

Data Table Type	Description
Data Store	Users can opt to store data closer to Panopticon server in an embedded database.
Live	Direct connection to source data.
Joined	Two or more different types of data tables joined together creating a new data table.
Linked	Resides inside workbooks and points to one of the data tables from Data Library.

The Data Library page is composed of the following sections.




Data Library Page Sections and Descriptions

Section	Description
1	Folders List of folders where data tables can be saved, exported, or imported.
2	Folder Context Menu Allows you to: Create a data table and joined data table Assign folder permissions on your workspace Import or export data table bundles Create, rename, or remove folders
3	Search Data Table Entering text will filter data tables which can include: Those that are available in data store Live data tables Joined data tables Extracts
4	Toolbar Allows you to: Display the data tables list either on List View or Grid View Copy or move data tables to other folders Import data table to data store Clear and import data table to data store Delete data tables
5	New Legacy Extract Allows accessing data by retrieving only the required results into memory, by querying on demand, pushing aggregation, and filtering tasks to underlying big data repositories, or queryable data extracts.
6	New Joined Data Table Allows you to join data tables created in the data library.
7	New Data Table Allows you to create a data table.
8	List of Data Tables and Data Extracts Data tables and data extracts created in the data library.
9	Data Table Context Menu Allows you to: Export data table bundles Copy or move data tables to other folders Rename or remove data tables View details of the data table


DATA LIBRARY DISPLAY VIEW

Data Tables can be displayed either on a *List* or *Grid View*.

On the toolbar, click **Grid View** . The data tables are displayed as thumbnails.



Or click **List View** . The data tables are displayed in a standard listing.



On either display view style, clicking on a data table title or thumbnail displays the data table on the *Data Table Editor*.

ADDING A NEW DATA TABLE IN THE DATA LIBRARY


You can add data tables that can be joined or imported to data stores in the *Data Library* page. These data tables will also be available in the *Add and Edit Data Table Wizards* that are available in a workbook.

Steps:

1. Create a new data table by doing one of the following:



• Right-click on a folder or subfolder then select **New Data Table** in the context menu.




The New Data Table dialog displays.



Create

2. Enter the name of the data table then click

The data source groups you can select are displayed.



3. Click a data source group tab.

File/URL

Then select one of these data sources:

•	<u>Azure</u>	Google Cloud	• JSON
•	MS Excel (legacy)	MS Excel (xlsx)	• <u>\$3</u>
•	SmartWorks IoT	SmartWorks IoT Write	• <u>SVG</u>
•	<u>Text</u>	Web Data	• <u>XML</u>

Database

Then select one of these data sources:


• <u>Cassandra</u>	DolphinDB	Elasticsearch 6.x
Elasticsearch 7.x	Google Analytics	• <u>InfluxDB</u>
• <u>JDBC</u>	JDBC Beta	• Kx kdb+
• <u>KsqlDB</u>	• <u>LivySpark</u>	MongoDB
• <u>OneTick</u>	OneTick Cloud	Panopticon Data Extract
• <u>Python</u>	• Rserve	Shakti Beta
• <u>Splunk</u>		

Streaming

Then select one of these data sources:

ActiveMQ	<u>Amazon Kinesis – Data</u> <u>Streams</u>	• AMPS
DolphinDB - Streaming	Google Cloud Pub/Sub	JDBC Database - Streaming
• <u>Kafka</u>	Kafka Publisher	• Kdb+ Tick
KsqlDB – Streaming	• MQTT	OneTick CEP
Panopticon Streams	RabbitMQ	Redis Streams
• <u>Solace</u>	Streams Simulator	Streams Simulator - Extract
StreamBase 7.1	StreamBase LiveView	• <u>WebSocket</u>


The Data Table Editor displays. The example below displays the connector settings for the MS Excel (legacy) data source.



See Working with the Data Table Editor for more information.

WORKING WITH DATA TABLE EDITOR

Most of the sections in this editor are available in <u>Workbook Internal Data Table Editor</u>. However, you can only create a single data table in this editor. To join data tables, you can use the <u>Joined Data Table Editor</u>.




Data Table Editor Sections and Definitions

Section	Description
1	Back Exit the Data Table Editor and go to the Data Library page.
2	Data Table Name Name of the data table. To modify, use the Rename option in the context menu.
3	Displays the data source that you will connect to. Click to select another data source. Other data table definitions are displayed including the description and the auto refresh period (in seconds).
4	Data Table Parameters Add or manage data table parameters.
5	Search Columns Allows searching of columns on the Data Preview.

Section	Description
6	Data Preview Executes the queries to return and display preview of the data table you are creating. NOTE: The maximum number of rows displayed in the Data Preview is 100.
7	Calculated Columns Allows you to view and manage the <u>calculated columns</u> .
8	New Column Options Allows you to add any of the following columns: Auto Key Calculated Ranking Time Bucket Identity, Sign, Manual, Equal Density, and Equal Distance numeric buckets Text Grouping
9	Group and Sort Columns When the Column Order is set to Sorted, the columns are grouped by type (Text, Date/Time, then Numeric) and sorted alphabetically.
10	Connector Settings Displays the connector settings of the data source and allows for <u>limiting the amount of data to be returned.</u>
11	Import to Data Store Allows you to import the data table to a data store.
12	Refresh Preview Allows you to refresh the data preview.
13	Save Data Table Saves the data table definition.
14	Row Limits Settings Allows setting of the <u>row limit</u> of data sources.
15	Collapse Data Preview Collapse the Data Preview pane. Click to expand the Data Preview pane.

Clicking **Transform Settings** a displays the *Transform Settings* pane.



Transform Settings

Allows you to:

Pivot or unpivot retrieved data.

Transform data to enable time series analysis including interpolation.


Run an R or Python script for data transformation.

Lists of orders to be reconstructed into an Order Book and conflated for output display.

Clicking Columns b displays the Columns Settings pane.


Transform

Settings



Section	Description
Columns Settings	Allows you to:
	View the column <u>data type</u>
	Rename the column names
	Select the <u>numeric</u> or Date/Time <u>format</u>
	Select the <u>numeric default aggregation</u>
	Define the Min and Max range of numeric columns
	Define <u>custom sort order</u>

Clicking **Advanced** Gisplays the *Advanced Settings* pane.



Section	Description
Advanced	Allows you to:
	Enter custom <i>Error Message</i> that will be displayed when an error occurs while fetching data. Can be parameterized.
	Retrieve <u>external aggregates</u>

IMPORTING TO DATA STORE

Data Table Editor allows you to store data closer to Panopticon server in an embedded database.

To be able to use data store, you would need to set the following properties. By default, Panopticon supports MonetDB, so default values correspond to it.


Also. MonetDB JDBC driver is packaged with Panopticon server. For other data store types, refer to *JDBC Driver Installation* section of the installation guide.

Property	Data Store
Attribute	datastore.connection.schema
Description	Name of the database schema to be used for creating or managing objects inside database.
Default Value	dbo
Property	Data Store
Attribute	datastore.type
Description	Controls which data store connector should be used. Valid values are MonetDB ", MSSQLServer and PostgreSQL .
Default Value	MonetDB
Property	Data Store
Attribute	datastore.connection.jndi
Description	JNDI resource name for the connection e.g., jdbc/MyDB . More details on how to configure JNDI is at <i>JNDI Connection Details</i> section of the server Installation Guide.
Default Value	
Property	Data Store
Attribute	datastore.connection.url
Description	JDBC connection URL for the database e.g., jdbc:monetdb://localhost:49153/PanopticonDataStore This property value is discarded If datastore.connection.jndiproperty is set.
Default Value	
Property	Data Store
Attribute	datastore.connection.driverclassname
Description	Fully qualified Java class name of the JDBC driver used for the connection.
Default Value	org.monetdb.jdbc.MonetDriver
Property	Data Store
Attribute	datastore.connection.username
Description	Username for the connection. Only required when using connection URL.

Default Value	
Property	Data Store
Attribute	datastore.connection.password
Description	Password for the connection. Only required when using connection URL.
Default Value	


Steps:

1. Select or create the data table you want to import to data store.



2. Click Import Data to Store

The notification dialog displays that the data table has been imported to data store.




Removing a Data Table from Data Store

You can also delete the data table from the data store.

Steps:

- 1. Select a data table that has been imported to data store.
- 2. Click Clear Data from Store


A notification displays.



3. Click Yes

WORKING WITH JOINED DATA TABLE EDITOR

The Joined Data Table Editor allows you to join two or more data tables to create a new joined data table. This editor is composed of the following sections:




Join Data Table Editor Sections and Definitions

Section	Description
1	Back Exit the Data Table Editor and go to the Data Library page.
2	Data Table Name Name of the data table. To modify, use the Rename option in the context menu.
3	Data Table Settings Description of the data table and the auto refresh period (in seconds).
4	Data Table Parameters Add data table parameters. The inherited data table parameters from the joined data tables are displayed.
5	Search Columns Allows searching of columns on the Data Preview.

Section	Description					
7	Data Preview Executes the queries to return and display preview of the joined data table you are creating. NOTE: The maximum number of rows displayed in the Data Preview is 100. Calculated Columns Allows you to view and manage the calculated columns. The inherited calculated columns					
8	from the joined data tables are also displayed. New Column Options Allows you to add any of the following columns: • Auto Key • Calculated • Ranking • Time Bucket • Identity, Sign, Manual, Equal Density, and Equal Distance numeric buckets					
9	Text Grouping Group and Sort Columns When the Column Order is set to Sorted, the columns are grouped by type (Text, Date/Time, then Numeric) and sorted alphabetically.					
10	Join Settings Displays the data tables that are being joined and the join keys. You can also opt to delete any of the data tables by clicking.					
11	Join Type Displays the join type used.					
12	Add Data Table Displays the Add Data Table dialog where you can select data tables to join. Add Data Table Root > Organization Name ↑ Connector Type Last Modified Last Modified By BidOfferTrade MS Excel (xlsx) Live Feb 14, 2023 5:36 PM designer BitCoinOrders Text Live Feb 14, 2023 5:36 PM designer StocksJoined Multiple Joined Feb 14, 2023 5:36 PM designer StocksStatic MS Excel (legacy) Live Feb 14, 2023 5:36 PM designer StocksTimeSeries MS Excel (legacy) Live Feb 14, 2023 5:36 PM designer					
	These data tables were created in the <i>Data Table Editor</i> .					
13	Join Key Allows you to select the join keys of the data tables that will be joined.					
14	Refresh Preview					


Section	Description			
	Allows you to refresh the data preview.			
15	Save Join Data Table Saves the join data table definition.			
16	Join Types Allows you to define: Left Outer Join Right Outer Join Full Outer Join Inner Join Cross Join			
15	Collapse Data Preview Collapse the Data Preview pane. Click to expand the Data Preview pane.			

Clicking **Transform Settings** a displays the *Transform Settings* pane.



Section	Description			
Transform Settings	Allows you to:			
	Pivot or unpivot retrieved data.			
	Transform data to enable <u>time series analysis</u> including interpolation.			
	Run an <u>R</u> or <u>Python</u> script for data transformation.			
	Lists of orders to be <u>reconstructed into an Order Book</u> and conflated for output display.			

Clicking **Advanced** b displays the *Advanced Settings* pane.



Section	Description	
Advanced	Allows you to: Enter custom <i>Error Message</i> that will be displayed when an error occurs while fetching data. Can be parameterized.	
	Retrieve <u>external aggregates</u>	

Joining Multiple Data Tables in the Joined Data Table Editor

In this section, we will discuss how to join the following data tables using two common fields.

Sample Data Table 1 (e.g., BidOfferTrade - Price)


#	abc Item	(L) isodatetime	# ask_price	# ask_volume	# bid_price	# bid_volume
1	Price	01/17/2008	17.75	2.00	17.65	1.00
2	Rate	01/17/2008	17.70	2.00	17.64	1.00
3	Price	01/17/2008	17.74	1.00	17.61	1.00

Sample Data Table 2 (e.g., BidOfferTrade - Trade)

#	abc AggressivePassiveDark	abc RatePrice	abc Side	(L) ISODateTime	# TradeID	# trade_price	# trade_volume
1	Aggressive	Price	Buy	01/17/2008	1.00	17.79	200.00
2	Dark	Rate	Sell	01/17/2008	2.00	17.65	100.00
3	Dark	Price	Buy	01/17/2008	3.00	17.72	100.00
4	Passive	Price	Sell	01/17/2008	4.00	17.71	200.00

Steps:

- 1. Create a new joined data table by doing one of the following:
 - New Joined Data Table
 on the Data Library page, or
 - Right-click on a folder or subfolder then select **New Data Table** in the context menu.




The New Data Table dialog displays.




Create

2. Enter the name of the joined data table then click


The Joined Data Table Editor displays.



- 3. On the Join Settings pane, click + Add Data Table. The Add Data Table dialog displays.
- 4. Click the data tables that will be joined. Selected data tables are now highlighted.




CloseThe selected data tables are now added under the *Join Settings* pane.




5. To join the data tables, click the **Join** ico

The icon changes to and the *Join Settings* pane displays the join types you can use.




6. Select the join Type:

Join Type	Description			
Left Outer Join	Keeps all rows from the left table. When there are no matching values from the right table, empty values will be returned.			
Right Outer Join	Keeps all rows from the right table. When there are no matching values from the left table, empty values will be returned.			






The Left Column and Right Column drop-down lists are displayed.



- 8. Select the unique ID from the *Left Column* data table from the drop-down list that will be used to match the unique ID from the *Right Column* data table (e.g., **Item**).
- 9. Select the unique ID from the *Right* data table from the drop-down list (e.g., **RatePrice**).



10. Click Refresh Preview then click to expand the Data Preview pane.

The selected join type is displayed in the *Join* definition box and the data table of the joined data sources is loaded on the *Data Sources Preview* area.


For the Left Outer Join, the joined table now displays seven rows based on the Item join key of the left table.



• For the *Right Outer Join*, the joined table now displays seven rows based on the **RatePrice** join key of the right table.



 For the Full Outer Join, the joined table now displays all rows that are matching or not matching based on the Item/RatePrice join keys of both tables.



 For the Inner Join, the joined table now displays seven rows based on the Item/RatePrice join keys of both tables.




• For the *Cross Join*, the joined table now displays twelve rows based on the combination of each row from the first table with each row from the second table.

Note that Join Keys definition is not available.



11. Now, let us add new left and right join keys. Click + Join Key on the Join Settings pane.

A new Left Column and Right Column entry displays.



- 12. Select the left and right join keys (e.g., **isodatetime** and **ISODateTime**)
- 13. Again, select the join Type.
- 14. Click Refresh Preview

The selected join type is displayed in the *Join* definition box and the data table of the joined data sources is loaded on the *Data Sources Preview* area.

• For the Left Outer Join, the joined table now displays three rows based on the Item and **isodatetime** join keys of the left table.

All of the rows from the left table are kept. Note that for the rows with no matching values from the right table, empty values are returned.



• For the Right Other Join, the joined table now displays four rows based on the RatePrice and ISODateTime join keys of the right table.

All of the rows from the right table are kept. Note that for the rows with no matching values from the left table, empty values are returned.



For the Full Outer Join, the joined table now displays six rows from both tables. The first row is based on the
 Item/RatePrice and isodatetime/ISODateTime join keys of both tables while the next five rows are those
 that did not match the join keys.



 For the Inner Join, the joined table now displays one row based on the Item/RatePrice and isodatetime/ISODateTime join keys of both tables.



• For the *Cross Join*, the joined table now displays twelve rows based on the combination of each row from the first table with each row from the second table.

Note that Join Keys definition is not available.



- 15. To delete left and right join keys in the *Join Settings* pane, click
- 16. Click to save the join. Once saved, a notification message displays.



UNION ALL OF MULTIPLE DATA TABLES

There are occasions where the source data is held across multiple disparate repositories so that the rows of the data set are distributed. In this case, instead of doing a join, perform a Union All.

Common use cases for union all include:


- Performance data to its benchmark.
- ☐ Historical data from a database to current streaming data from a message bus.

Union All is done based on column position and requires data type match between data sources.

Steps:

- To join the data sources, click the **Join** button
 The *Join Settings* pane displays.
- 2. Select Union All then click Refresh Preview

The result of the union all is displayed in the Data Source Preview.



3. Click Save . Once saved, a notification displays.




Joined Data Table Error Message

If there is an error in the join definition, the **Join** icon or *Left/Right Column* drop-down is marked with a red border. Consequently, the preview is not displayed.

For example, if the join keys have different data types, an error message is displayed:

"A panopticon.developer.tables.standalone.TimeColumn column from the left table in the join is not compatible with a panopticon.developer.tables.standalone.NumericColumn column in the right."



Make the necessary changes to make the join work.

CREATING DATA EXTRACTS

One of the methods in accessing data is by retrieving only the required results into memory, by querying on demand, pushing aggregation and filtering tasks to underlying big data repositories, or queryable data extracts.

This is commonly known as a ROLAP implementation, where the product is dynamically writing data queries to the underlying data repository and retrieving aggregated and filtered datasets. Given the on-demand nature of this method it is more suitable to exploratory data analysis but requires dynamic query generation.

This section discusses the steps and guidelines on how to create data extracts.


Steps:

On the Data Library page, click
 The New Data Extract dialog displays.



2. Enter the name of the data extract then click

The Extract Settings page displays.




Section/Panel	Description
1	Connector drop-down list Includes the non-streaming connectors to extract data from.
2	Name of the data extract. Click the button to go back to the Data Library page.
3	Save Save the changes made on the Extracts tab.
4	Refresh Data Refresh the data after modifying and saving changes on the Data Extract page.

	You can also opt to click Cancel Refresh Data Cancel Refresh Data
5	Details Display the details of the data extract including the number of rows, columns, cells, status, and the last time it was updated.
6	Connectors Select the connector that will be used for the data extract.
7	Refresh Data Preview Refresh the data preview.
8	Expand Data Preview Expand the Data Preview panel.

- 3. Enter the *Name* of the data extract. This should be unique and should only contain letters (a to Z), numbers (0 to 9), and underscores.
- 4. Click or press **Enter** to apply the name.
- 5. Define the data extract settings of any of the following data sources:

• <u>Azure</u>	• <u>Cassandra</u>	DolphinDB
ElasticSearch 6.x	ElasticSearch 7.x	Google Analytics
Google Cloud	• InfluxDB	• JDBC
JDBC Legacy	• JSON	• Kx kdb+
• KsqlDB	• <u>LivySpark</u>	MongoDB
MS Excel (legacy)	MS Excel (xlsx)	• <u>OneTick</u>
OneTick Cloud	• <u>Python</u>	• Rserve
• <u>\$3</u>	Shakti Beta	• <u>Splunk</u>
• <u>Text</u>	Web Data	• <u>XML</u>


- 6. Click to save and display the details of the data extract.
- 8. Click to go back to the *Data Library* page. The new data extract is added in the list.



DATA LIBRARY TOOLBAR AND CONTEXT MENU

The Data Library page has a toolbar and context menus that allow you to:

Data Library Context Menu




NOTE The Extract Bundle option is not available for data extracts.

Data Library Toolbar



□ Data Library Folder Context Menu



The Data Table toolbar options include:

Toolbar Option	Description
<u>Display View</u>	Display data tables either by List View or Grid View.
Сору	Copy a data table to permissioned folder.
Move	Move a data table to permissioned folder.
Import Data to Store	Import or merge workbooks.
Clear and Import Data to Store	Clear the earlier imported data and import again to the data store.
Remove	Remove data tables.

The Data Table Context Menu options include:

Toolbar Option	Description
Rename	Rename a data table.
Move	Move a data table to permissioned folder.
Сору	Copy a data table to permissioned folder.
Export Bundle	Export a bundle of the data table including the data files.
View Details	View the details of the data table which include connector or data tables used, workbook usages, Date/Time last modified, and the user who did the last change.
Remove	Remove data tables.

The Data Library Folder Context Menu options include:

Toolbar Option	Description
Rename	Rename a folder under your workspace.

New Folder	Create a <u>new data table folder</u> and assign the allowed or denied groups and users.
New Data Table	Create a <u>new data table</u> .
New Joined Data Table	Create a new joined data table.
Permissions	Define the <u>allowed</u> or <u>denied</u> subfolder or personal folder permissions.
Export Bundle	Export a bundle of a data table including the data files.
Import Bundle	Import a bundle of a folder including the data tables.
Remove	Remove folder. NOTE: Folders can be deleted if they do not contain any data.


Copying Data Tables

Copy data tables to other permissioned folders.

Steps:

- 1. On the *List* or *Grid* view, select one or several data tables then:
 - right-click and select Copy on the context menu, or
 - click the **Copy** icon on the toolbar.

The Copy Data Table dialog displays with the folder or subfolders the user is allowed to copy the data tables to.



- 2. Select the folder or subfolder.
- 3. Click Copy

The data tables are copied to the selected folder.


Moving Data Tables

Move data tables to other permissioned folders.

Steps:


- 1. On the *List* or *Grid* view, select one or several data tables then:
 - right-click and select Move on the context menu, or
 - click the **Move** icon on the toolbar.

The Move Data Table dialog displays with the permissioned folders.



2. Select a folder or subfolder.





The data table is moved to the selected folder.


Clearing and Importing Data Table to Data Store

Clear the earlier imported data and import again to the data store.

Steps:

- 1. Select the checkbox of the data tables you want to import again to data store.
- 2. Click on the toolbar.

The notification dialog displays that the data table has been imported to data store.




3. Click Close

Exporting Bundle for a Data Table or Folder

Allows you to download data table bundle with the associated files.

Steps:


1. Right-click on a data table or folder and select **Export Bundle** on the context menu.



Folder Context Menu

Data Table Context Menu

A notification message displays.



The **Include Data Files** checkbox is selected by default. This means the associated data files will be included in the download.

2. Click . A copy of the workbook or folder bundle is downloaded.

Importing a Folder Bundle


Import a bundle of a folder including the data tables.

NOTE


- Users will only be able to import a bundle to folders where they have WRITE permission.
- Existing data tables with the same name as the uploaded data tables will be archived, only if the new data table differs from the current one.
 Consequently, the uploaded version will be the current one.
- The bundle must not exceed the value set in the property file.upload.size.max.bytes in the Panopticon.properties.
- The exported folder structure is maintained when uploading the bundle. If the folders do not exist on the server, they will be created.
- After importing, if there are duplicate data table titles, their folder name will prefix the title.

Steps:

1. Right-click on a folder and select **Import Bundle** on the context menu.



The Import Bundle dialog displays.



- 2. To import a bundle, you can either:
 - Drag it from your desktop and drop on the dialog, or
 - Click Choose Bundle to Import and select one on the Open dialog that displays.

The name of the selected bundle is displayed on the dialog box.

3. To replace existing data tables, select the **Replace existing data table** checkbox.



Creating Data Library Folders




Users that log on with a Designer role:


- will have their own personal folder created and displayed on the *Data Library* page (i.e., **My Workspace**). This personal folder is where Designers can create <u>data tables</u> and <u>joined data tables</u>.
- is not allowed to create a folder on the root folder.

Steps:

1. On the **Data Library page**, right-click on any folder in your workspace, and select **New Folder**.




The Create Folder dialog displays.



NOTE

- The Designer user is available under the Allowed section by default with Read, Write, and Modify permissions.
- Removing the Designer user will mean they will not have access to this folder and its subfolders.
- 2. Enter a Folder Name.
- 3. Proceed to defining the authorization to <u>Allowed</u> or <u>Denied</u> groups and users.
- 4. Click Create

The new folder is displayed on the expanded Folder hierarchy list and on the Folders/Workbooks list.



NOTE

- Folders and subfolders can be deleted if they do not contain any data.
- The folders and subfolders on the *Data Library* page will also be available on the *Workbooks, Webhooks*, and *Themes* pages.

[5] BUILDING A WORKBOOK

After all the data configurations are saved in the *Data Table Editor* layout, the *Workbook* layout is displayed into either any of two modes:

Design Mode


This mode allows you to create Panopticon workbooks and add or change elements in the dashboards.


View Mode

This mode lets you use your Panopticon workbooks and dashboards to analyze data.


It is easy to switch between these modes.

On the *View Mode* view, click the **Edit** icon.





The Design Mode view displays.




To go back to the View Mode, click the View

• View

icon.

USING THE OPEN WORKBOOK IN DESIGN MODE



Property	Description
1	Back Exit the Workbook in Design Mode to go back to the Workbooks page
2	Data Table Selected data table
3	Search Columns Allows searching of columns in the selected data table
4	Data Table Columns Columns to drag to dashboard visualizations and parts
5	Workbook Data Table Editor Displays <u>Data Table Editor</u> layout where you can further configure the data table.
6	Edit Data Table Opens the Edit Data Table Wizard. Enabled when the data table was added using the Add Data Table Wizard.
7	Add Data Table

Property	Description
	Opens the <u>Add Data Table Wizard</u>
8	Dashboard Selected dashboard where you can add, edit, and delete <u>visualizations</u> , <u>filters</u> , <u>actions</u> , and <u>general parts</u> You can also <u>create</u> , edit, <u>duplicate</u> , <u>rearrange</u> , and <u>delete</u> dashboards.
9	Columns Columns dragged to the X variable of the visualization
10	Breakdown, Columns, and Rows Allows definition of hierarchical.structures for the visualization
11	Visualization Variables and Filters Variables and filters that can be defined for the visualization
12	New Dashboard Add new dashboard. You can also opt to select a template to use.
14	Workbook Theme Select the workbook theme
15	Toolbar <u>Toolbar options</u> in the <i>Workbook in Design Mode</i>
16	View Go to Workbook in View Mode
17	Show Details Displays information available in the <u>Details variable</u> of a visualization
18	Filters Filters added on the dashboard
19	Visualization Context Menu See Context Menu for more information.

In this mode, you can also perform the following operations:

Add	<u>dashboard</u>	parameters

- □ Perform <u>synchronization</u>
- Morph visualizations
- □ Create <u>actions</u> and <u>global filters</u> for the workbook
- View and clear <u>active filters</u>
- □ Define the <u>workbook theme</u>
- Interact with the visualizations

These features are discussed in detail below.


CREATING A DASHBOARD

A dashboard may consist of several parts including: <u>visualizations</u>, <u>legends</u>, <u>filters</u>, <u>action controls</u>, <u>labels</u>, and <u>images</u>.

NOTE

- You can begin designing your dashboard only after the <u>data is available</u> to the workbook.
- You must be in Design Mode to create a new dashboard or alter an existing dashboard.


By default, after <u>creating a workbook</u>, a dashboard (named **Dashboard1**) is displayed on the *Open Workbook in Design Mode* view. The dashboard name by default is editable. You can enter a descriptive dashboard <u>name</u>.



Each blank canvas represents a single dashboard. You can add as many dashboards as you like to a workbook. These appear as tabs at the top of the screen. Switch between dashboards by clicking on the appropriate tab.

You can also opt to select from the available dashboard templates of the selected theme.


If there are several dashboards added, such as the example below, click the icon to expand the drop-down list and display all of the available dashboards and select one to display.



Dashboard Editor Product Tour


For first time users, a product tour in the dashboard is provided with the following steps:

1. Add Data.




Follow the steps then click Next.

2. Add Parts to Your Dashboard.



Follow the steps then click Next.

Configure Part Settings



4. Click **Got it** to close the product tour.

You can also opt to:

- □ Click **End Tour** in any of the steps to close the product tour.
- Click any of the buttons on the top right of the product tour to go to the desired step.


Reset the Workbook Editor Tour

You can reset the workbook editor tour to view the tooltips again the next time you edit a workbook.

Steps:


1. Click the user icon on the top right corner.

The Profile panel displays.




2. Click the View Profile link.

The User Profile page displays.



3. Click Reset Workbook Editor Tour.

A notification displays.




Setting the Dashboard Properties

You can set the general settings of a dashboard including the export option, action mode, global filters and resetting filters when parameters are updated.


Steps:

1. On the *Dashboard and Workbook Settings* pane, click the **Dashboard** tab then the **Options** button.






The Dashboard pane updates to display the Dashboard Settings.



- 2. Enter a Description of the dashboard. Hovering on a dashboard tab displays this description.
- 3. Set the Export option:



Disabled

Disables the ability to copy data in a visualization or export raw data.

Data Enabled

Enables the ability to copy the highlighted data in a visualization and paste into another application such as MS Excel.

Raw Data Enabled (default)

Exports the raw data from the data source.

- 4. Tap the **Auto Action Mode** slider to turn it on. This means the <u>automatic parameterization</u> on the visualizations on the dashboard is available.
- 5. Tap the **Global Filters Enabled** slider to turn it on. This means that the global filters defined for the workbook will be applied on the dashboard. This is enabled by default.
- 6. Tap the **Reset Filters on Parameter Update** slider to turn it on. This means that when the dashboard parameters are updated, the filters in the dashboard are reset accordingly.
- 7. Click the Save icon on the toolbar to save the changes.


 When saved, the notification is displayed.

Setting the Workbook Properties

You can set the general settings of a workbook including the layout and PDF output.

Steps:


1. On the *Dashboard and Workbook Settings* pane, click the **Workbook** tab.




2. Click the Options



The Workbook Settings pane is displayed.





- 3. Define the layout properties of the workbook:
 - Min Width Default is 300.
 - Min Height Default is 300.
 - Max Width The allowed range value is greater than 0 and less than 2560.
 - Max Height The allowed range value is greater than 0 and less than 2048.
- 4. The Show Wait Animation when Reloading slider is enabled by default. Tap the slider to turn it off.
- The Automatically Update Thumbnail slider is enabled by default. This means the thumbnail of the workbook will be based on the currently displayed dashboard when saving.

Other options include:

- Select a dashboard and save the workbook. To lock this thumbnail image, tap the slider to turn the Automatically Update Thumbnail off.
- Select an External Image. To do so, tap the slider to turn the Automatically Update Thumbnail off and click the Choose File button. Select the thumbnail image in the Open dialog that displays.
- Enter the Visualization NaN Symbol. This value will be used for the not a number (NaN) values in the visualizations.
- 7. Select the <u>Double Click</u> behavior that will be applied to the visualization. The default is **Drill**. Other options are **Filter In**, **Default Action**, or **None**.
- 8. The Selection in Popup slider is enabled by default. Tap the slider to turn it off.
- 9. Select the Parameters Assignment Scope: Workbook or Dashboard.
- 10. The Allow Empty Parameter Value slider is enabled by default. Tap the slider to turn it off.

NOTE

- Not all Action parts support empty string character values since they do not work against a string parameter. For example, Action Date Picker, Action Date Range Picker, or the Numeric Action Slider.
- Action parts that support empty string parameter values include:
 - Action Drop Down Multiple Selection can deselect all items to get empty string as a parameter value.
 - Action Drop Down Include List can set the parameter to empty if no values are included.
 - Action Text Box setting with no value in the text box will set the parameter to an empty string.
- 11. The PDF Report settings are defined on a workbook basis. Set the following PDF output properties:

Property	Description
Page Size	Page size. Default is A4 .
Scale	Page scale. Default is 100 .
Orientation	Select Landscape or Portrait.
Image Quality	Image resolution. Options include:
	 Desktop – No scaling applied and uses less space. For viewing in the PDF viewer.
	Print – Higher quality and uses more space. For printing page to the size specified in the report.
	Ultra – Very high quality and uses a lot of space. For printing large versions.
Margin	Page margin. Default is 48.
Header	The header to be displayed on the PDF output. Default is:
	\$WorkbookName - \$DashboardName \$Date \$Time
Footer	The footer to be displayed on the PDF output. Default is: Page \$PageNum of \$PageCount
Add Table of Contents	Tap the slider to turn it on and add table of contents to the PDF output.
Table of Contents Title	Title of the Table of Contents.

12. Click the Save



icon on the toolbar to save the changes.



⊘ Saved!


notification is displayed.


Rearranging Dashboards


The order of the dashboards in a workbook can be rearranged.

Steps:

- 1. Click on a dashboard tab you want to move.
 - The icon displays along with the blue marker before or after a dashboard where you can drop the item.
- 2. Drag and drop the dashboard to the desired position.








Making a Duplicate of a Dashboard


Make a copy of a dashboard and modify to create a new one.

Steps:

1. Right-click on the dashboard tab and select **Duplicate** on the context menu.



A duplicate of the dashboard is added.



You may opt to rename the dashboard.

2. Click the Save button.


When saved, the saved! notification is displayed.

Renaming Dashboards


Dashboard names can be modified.

Steps:

- 1. To rename a dashboard, you can highlight the name either by:
 - double-clicking on the name, or




• right-clicking on the dashboard and selecting **Rename** on the context menu.



2. Enter a unique name and click .


An error message displays if a dashboard with the same name already exists.



Deleting Dashboards

Steps:

1. Right-click on the dashboard tab and select **Remove** on the context menu.



The dashboard is deleted.

When saved, the

2. Click the Save icon on the toolbar to save the changes.

Saved!


Adding Dashboard Parameters

In addition to the parameters of the associated data tables that are used by visualizations and other parts on the dashboard, a Designer user can add new dashboard parameters which can be value sources inside <u>actions</u> and the title of visualizations and parts.

notification is displayed.


Steps:

1. On the Dashboard and Workbook Settings pane, click the Dashboard tab.




2. Click + New Parameter


A New Parameter instance is displayed.



3. Click on this new instance.



- 4. Enter the Name of the parameter then click ...
- 5. Select the data *Type*: **Text**, **Numeric**, or **Time**.
- 6. Select the Mode: Text or Data
 - For the **Text** mode, enter the *Default Value* then click \checkmark . You can enter several default values, separated by a comma.




NOTE


For the Time type, the following formats for the default value are accepted:

- "yyyy-MM-dd"
- "yyyy-MM-ddTHH:mm:ss"
- "yyyy-MM-ddTHH:mm:ss.SSS"


To prompt the parameter input when opening the workbook, tap the **Prompted** slider to turn it on. The dashboard parameter instance changes to allow specification of the following:



- To encrypt the value upon entry, tap the **Masked** slider to turn it on.
- Add a custom *Input Validation*. This can be any regular expression (e.g., "A-Z{3}")
- The workbook will not be opened unless it passes the validation. Enter an *Error Message* to help in defining a better input to match the regular expression (e.g., "Enter another value.")



For the **Data** mode, the parameter is given a data-driven value either **Once** or **Live**.
 Then select the *Data Table*, *Column*, and *Aggregate*.




For this sample data table:

Category	id	num
X	а	1
X	b	1
X	С	1
Υ	d	2
Υ	е	2
Υ	f	2
Z	g	3
Z	h	3
Z	i	3

If **Once** is the selected **Data** mode, the parameter is given a data-driven value once, at workbook startup and open, but it is not repeated when the data table is refreshed.

The first time you open the workbook and **X** is the *category*, the parameter *datadriven_num_sum* is **3**.




Changing the category to Y, the parameter datadriven_num_sum is still 3.




However, if **Live** is the selected **Data** mode, the data-driven parameter is updated "live" and kept in sync with the data value.

The first time you open the workbook and **X** is the *category*, the parameter *datadriven_num_sum* is **3**.



Changing the *category* to **Y**, the parameter *datadriven_num_sum* is updated to **6**.



- 7. Repeat steps 2 to 6 to add more parameters.
- 8. Click the Save icon on the toolbar to save the changes.

 When saved, the notification is displayed.

Deleting Dashboard Parameters

To delete a dashboard parameter, click on an instance in the list and then click $\stackrel{\text{\tiny{1}}}{=}$.


Dashboard Design

Before you can perform the other dashboard settings, you must first add visualizations, controls, or general parts on the dashboard.

To add the dashboard parts, you can either:

- Use the <u>dashboard templates</u> in the workbook themes, or
- Double-click or draw a rectangle on the dashboard canvas.


A rectangle shape displays on the dashboard canvas, with an instruction "Use the settings to create a part." The corresponding definition of the selected part can be done on the <u>Select Part pane</u>.




The Select Part Pane

The Select Part pane has three tabs to define the settings of the dashboard visualization or part.

☐ On the **Visual** tab






Part	Description
Combination Visualizations (Legacy)	Combination Graphs allow combining multiple variables as layers in a series graph sharing a common x-axis. Unlike other visualizations, the Text, Numeric and Time Combination Graphs allow combination of many variables, based on different columns of a data table, each rendered independently, using a selected visualization.
Snapshot Visualizations	Some of the most common use cases for data visualization software require the system to display information about a data set as it exists at a particular point in time. These snapshot visualizations are extremely useful for understanding relative quantitative and qualitative measures and enable users to gain a comprehensive understanding of complex data sets very quickly. You must populate visualizations with data columns for them to function.
Time series Visualizations	The ability to handle very large quantities of multivariate time series data is an essential element in a complete visual analysis system. Altair Panopticon offers a range of specialized data visualizations, including Horizon Graphs, Stack Graphs, and Line Graphs, designed specifically to make analyzing historical data easier and more efficient. The software's ability to connect to traditional row-oriented relational databases or column-oriented databases is key to supporting fast, responsive multi-dimensional analysis of large data sets. Our time series capabilities are especially important for users in global investment banks, hedge funds, proprietary trading firms, and exchanges.

IMPORTANT


The new Axis Graphs (X-Axis Graph and Y-Axis Graph) are different from the legacy visualizations in many aspects. See <u>Axis Graphs</u> for more information.



When adding a visualization part, the shelves are turned off by default.




To display the shelves, right-click on the visualization and select **Show Shelves** in the context menu.



The corresponding shelves of the visualization are displayed (e.g., Columns, Rows, Breakdown).




☐ On the **Control** Tab:



Part	Description
<u>Legends</u>	Link legends to visualizations using drag and drop commands. Four types of legend are supported: <u>Timeseries</u> , <u>Color</u> , <u>Icon</u> , and <u>Shape</u> .
<u>Filters</u>	Filter data in order to highlight outliers, patterns and trends. Filters must be populated with data columns for them to function.
Actions	Allow actions to be executed against pre-defined selections and can be used to provide inputs to filtered data sets.





Part	Description
Text Label	These can be completely independent of your data. Add labels and explanatory text to help users better understand how to use a dashboard using text boxes. Or link them up to a data column for dynamic displays.
Relative Layout Pane	Allows resizing of the visualizations in a dashboard.
<u>Iframe</u>	Allows a web page to be displayed within a dashboard or page.
Image Box	These are also independent of your data. Add logos or other graphics to your dashboards using Image Boxes.
JavaScript Part	Allows the designer of a workbook to include a bespoke JavaScript code inside a dashboard.
Tab Panel	Supports a tabbed panel within a dashboard where visuals can be assigned to each tab.

Once you have items from the Select Part pane on the dashboard canvas, you can move them around, resize or remove.


Using the Dashboard Templates

You can start your dashboard design by using the available dashboard templates of the selected workbook theme.


Steps:

1. In the Select Template pane, click a dashboard template from the selected theme (i.e., Light2023).


To search for a particular template, enter it into the *Search Template* box. You can also enter one or more characters into the *Search Template* box and the suggested list of templates that matched the entries will be displayed.



The corresponding parts of the selected template (e.g., 2x2 Grid + Filter) are displayed.



- 2. Click the parts and define their properties on the Select Part pane.
- 3. To add another dashboard, click then select a template.




4. Repeat step 2 to define the properties of the parts in the selected template.


Dashboard Canvas Grid Lines

When moving, resizing, or adding more visualizations and parts, grid lines help guide when parts are aligned with or are the same size as other parts.

For example, if two parts have the same y position, a line is drawn between the parts, indicating that they are aligned. A less obvious guideline is displayed if the center of the two parts is aligned.




Guidelines are also be drawn if the width or height match any other part. This is drawn as two lines on either side of the size matches, for all parts that match. For example, if two parts have the same width, horizontal lines will be drawn on the sides of both parts with the same width.




Maximizing Visualizations or Parts

Each visualization includes a **Maximize** icon at the top right of the control.




Clicking this icon causes the dashboard visualization or part to be maximized, and the icon changes from ** to **



Clicking the **Minimize** icon minimizes the visualization or part.


Expanding Visualizations or Parts

You can expand the currently selected part or visualization to consume the available space along the vertical or horizontal axis. This works as a way of quickly resizing a visualization or part to fit some area.



Clicking the **Expand**

icon expands the selected part.




Splitting Visualizations or Parts to Create a New One

You can slit a visualization or part in any single axis direction.

Steps:

1. Click on a visualization or part. The border is highlighted.



- 2. Click on the any of the following **Split** icons, where the part that is being split ends up on the size of the resize handle:
 - Top




Left



Right



Bottom




Resizing Visualizations or Parts

Steps:

1. Click on a visualization or part. The border is highlighted.




2. Click on one of the corners and drag to the required size.






- Selected multiple parts will only be resized of they are aligned on the screen. If multiple parts are far from one another, only the part currently being resized will be affected.
- It's not possible to make the bounding box of all selected parts larger, only the divisions between parts that make up the bounding box can be moved around. For example, in the image below, resizing the left part from the right adorner will take space from the left, it won't make both parts wider.




Moving Visualizations or Parts

Steps:

- 1. Click on a visualization or part. The border is highlighted.
- 2. Hover on the top middle button. The mouse pointer changes to $\stackrel{\leftarrow}{\leftarrow}$
- 3. Move the visualization or part to the new location.



4. Release the mouse.



DASHBOARD PART TOOLBAR

Copying, pasting, and removing selected dashboard parts can be done on the toolbar:



The toolbar options include:

Toolbar Option	Description	Windows Keyboard Shortcut
Copy	Copy one or several selected dashboard parts.	Ctrl + C
Cut	Cut one or several selected dashboard parts.	Ctrl + X
<u>Paste</u>	Paste one or several selected dashboard parts.	Ctrl + V
Remove	Delete one or several selected dashboard parts.	
<u>Undo</u>	Undo the activity done on the workbook.	Ctrl + Z
Redo	Redo the activity done on the workbook.	Ctrl + Y


You may also opt to use the Windows keyboard shortcut options.

Cutting or Copying Selected Dashboard Part


Copy or cut one or more selected parts that can be pasted in the dashboards of the workbook.

Steps:

1. Click on a visualization or part to be copied. The border is highlighted.



To copy or cut several parts, click one and then use the **Ctrl** key to select more. The border of the selected parts is highlighted.




2. To copy or cut, click **Cut** or **Copy** on the toolbar.

The **Paste** icon is enabled.

Pasting Selected Dashboard Part

After copying or cutting one or more dashboard parts, click **Paste** on the toolbar.

If you initially chose to copy, a duplicate of the dashboard part is displayed.



You can opt to <u>move</u> the original or duplicate to the desired location of the dashboard or paste to other dashboards in the workbook.

Deleting Selected Dashboard Part

Delete any unwanted dashboard part.

Steps:

- 1. Click on a visualization or part to be deleted. The border is highlighted.
 - To delete several parts, click one and then use the **Ctrl** key to select more. The border of the selected parts is highlighted.
- 2. To delete, you can either:
 - click the **Remove** icon on the toolbar, or
 - click **Delete** on the keyboard.

Undo or Redo

Click the **Undo** toolbar icon




Once you have clicked undo, the **Redo** toolbar icon is enabled, allowing you to reverse the undo.

ALIGNING OR DISTRIBUTING DASHBOARD PARTS


Selected dashboard parts can be automatically aligned (by row or column) or distributed (horizontally or vertically) using the *Layout* pane.

Steps:


1. Click a dashboard part then use then use the **Ctrl** key to select more. The selected dashboard parts are highlighted, and the *Layout* pane is displayed.




- 2. On the Layout pane, click any of these options:
 - Align Vertically Top
 The selected dashboard parts are aligned at the top of the dashboard canvas.




Align Vertically Center






Align Vertically Bottom

The selected dashboard parts are aligned at the bottom of the dashboard canvas.



Align Horizontally Left


The selected dashboard parts are aligned at the left of the dashboard canvas.



Align Horizontally Center


The selected dashboard parts are aligned at the horizontal center of the dashboard canvas.

+ +




Align Horizontally Right

The selected dashboard parts are aligned at the right of the dashboard canvas.





Distribute Horizontally

Adjusts the size of dashboard parts to be distributed horizontally in the dashboard. You can then opt to align in row or column.



Distribute Vertically





PANOPTICON VISUALIZATIONS

Panopticon supports a wide range of information visualizations that are designed for fast comprehension and easy interpretation of static, time series, real time streaming, and historic data sets.

As no visualization is ideal for every purpose, the appropriate visualization for the analytical task at hand must be used. Here are some general recommendations:

Analytical Task	Recommended Visualization
Read numeric values quickly	Table / Pivot Table
Performance against a KPI	Bullet Graph, Tile, Ticker Tile, Donut Gauge
Performance across a single variable for a small number of data elements, with different magnitudes	Bar Graph, Tile, Ticker Tile
Performance across a single variable for a small number of data elements, each with similar magnitudes	Dot Plot
Performance across a single variable for a large number of data items	Heat Map
Performance across a single variable for a large number of data items, which have different importance values	Treemap, Circle Pack
Performance across a hierarchical or grouped dataset	Treemap, Circle Pack
Correlation between two categories of data	Heat Matrix, Network Graph
Relationships between categories of data	Network Graph
Correlation between two or more numeric data columns	Scatter Plot
Geographic correlations of data	Map Plot Geographic Scatter Plot
Correlation over both a single numeric data column and various categories of data	Dot Plot
Trending performance across ordered categories	Dot Plot
Trending performance between two numeric variables	Numeric Line Graph
Trending performance between three numeric variables	Surface Plot (& 3D)
Trending performance across time	Line Graph
Time based Ranking	Line Graph with Ranking Axis
Time Based Contributions	Stack Graph
Time Based Correlations between time series	Horizon Graph
Time Based Transactions	Needle Graph
Financial Time Series Distributions	Candle Stick or OHLC Graph
Auction Price & Interest/Volume Distribution	Numeric Needle Graph
Geospatial Area Densities	Shapes
Spread between two time series	Spread Graph


Read numeric values quickly	Table / Pivot Table
Performance against a KPI	Bullet Graph, Tile, Ticker Tile, Donut Gauge

For more information on these visualizations, refer to the <u>Altair Visualizations</u> document.

Adding Visualizations to the Dashboards


After double-clicking or drawing a rectangle on the dashboard canvas, click on a visualization that you want to add from the *Select Part* pane.

The properties and components of the selected visualization are displayed. For example, here are the properties for the Table visualization:



Each visualization consists of five components:

- Settings section
- Breakdown Items
- Variable Shelf
- □ <u>Filters</u>
- Visualization Display Area




Each component is discussed in detail below.

VISUALIZATION GENERAL SETTINGS

Clicking on a visualization displays the *Visualization Settings* pane which are specific to its capabilities and functions. The settings are grouped into the following sections: <u>Breakdown</u>, <u>Axes</u>, <u>Variables</u>, <u>Filters</u>, Options (<u>General</u> and <u>Sync</u>).

General

All of the visualizations have these general settings:



Property	Description
<u>Title</u>	Title of the visualization, with multiple row structure. Can be 0 or more.
Add Title Row	Click to add more title rows. Settings for each title row can be done in the <i>Style</i> section.

Header Controls	Displays header controls such as Export Excel, Toggle Display Mode, Maximize, Rubber Band Zoom, and Rubber Band Selection. Can be Floating (default), Fixed, or disabled.
Shelves	Tap the slider to display the Shelf Variable and Breakdown.
Visible Shelves	Check the boxes of the shelves that will be displayed in the visualization.
Double click mode	Sets the behavior to be performed when double-clicking on a visualization value.
Zoom	Enable to reset the zoom on data reload.
Automatic Parameterization	Select the automatic parameterization status: On , Off , or Inherit (default).
Data Table	Allows you to switch to another data table in the workbook to be used in the visualization.
Recalculate Automatic Range on Breakdown Change	Tap the slider for variables with automatic range/mapping to be recalculated when the visible depth is changed in the visualization.
Help Text	The added Help text can be displayed for the visualization.


Visualization Title Rows

Allows you to add multiple title rows in the visualization. In addition to data-driven dashboard parameters, the *Title* can contain an informative summary and/or single KPI values on rows below the first row such as below:




Steps:

1. Enter the visualization's *Title*, if needed.




2. To add more titles, click




Then enter the Title.


For each title row, a corresponding *Title Row* section is added in the *Style* pane.




To set the style of the visualization title rows, click Style
 The page updates to display the Style pane.



4. For all title rows, set the *Foreground*, *Background*, *Alignment*, *Font* type, style, style (**Bold** and/or **Italic**) in the *Title* section.



5. You can opt to set these properties for each row in the corresponding *Title Row* sections.



Double Click Mode

This setting determines the action that will be performed when double-clicking on a visualization value.



Inherit

The action is inherited from the set double-click option under **Workbook** properties. The default is **Drill**. Other options are **Filter In**, **Default Action**, or **None**.

Dril

Drills into lower-level details of the selected item.

□ Filter In

Filters the dashboard to include selected items.

Default Action


Performs the default Action that is defined for the selected item.

None

Disables the double-click feature.

Automatic Parameterization

Determines whether parameters are to be automatically updated or the setting will be inherited from the workbook property.




□ On


When turned on, parameters can be automatically updated within a dashboard by right-clicking on a visualization item and selecting it from the context menu with the lightning icon.

The <u>dashboard parameter</u> values to be passed will include all possible data table values of the selected visualization.

For example, if there are **Region** and **Industry** dashboard parameters, and the associated data table of the visualization has a **Region** but no **Industry** column, then the *Automatic Parameterization* option will only include:




However, if the associated data table of the visualization has Region and Industry columns, then the *Automatic Parameterization* option will include both:



Off
 Automatic parameterization on the visualization based on the dashboard parameters is turned off.

Panopticon Web Authoring Guide




In some circumstances, it may be appropriate to disable this automatic parameterization, and instead utilize more configurable navigation <u>actions</u>.

□ Inherit


The automatic parameterization is inherited from the workbook property.

Help Text

Help text can be entered into a visualization's settings pane.



When the text has been added, the help icon appears to the right of the visualization title.



Clicking on the help icon, displays the associated help text.



Modifying the Data Table that is Associated to the Visualization

You can easily switch to another data table to use in the visualization.


Steps:

1. Click on a visualization on a dashboard.

The associated data table is displayed on the Data Table pane.

Click the Options button. The Visualization Settings pane is displayed along with the current data table being used.

For example:




3. Select another data table in the Data table drop-down list.

The visualization is updated to reflect the data setting in the new associated data table.

NOTE

Any changes in the schema in the newly selected data table will cause variable with missing measures to be invalidated. In addition, breakdowns with missing dimensions will be invalidated.

Sync



Synchronization determines whether the visualization should interact with other elements on the same dashboard:

Property	Description
Row Filtering	Tap the slider to turn it on. This causes the visualization to use the categorical and numeric filters on the dashboard.
Time Filtering	Tap the slider to turn it on. This causes the visualization to use any time filters on the dashboard.
Selection	Tap the slider to turn it on. This means, the items selected in another visualization will also be selected on this visualization.
Focus	Tap the slider to turn it on. This means, when focus is set on another visualization the system will also set focus on this visualization.


You can also enable the **Synchronized Variables** of the visualizations in a dashboard.

Synchronization of the Shared Variables in the Visualizations of a Dashboard


The synchronized variables of a visualization can be shared with other visualizations using the same data table.

Steps:


1. On the Dashboard and Workbook Settings pane, click the Dashboard tab and then the Synch button.




2. Click . The *Main* visualization is displayed. By default, this is the first defined visualization of the dashboard. For example:



3. Click on this visualization. All the available data tables in the workbook are displayed and the corresponding data table of the main visualization is also indicated.



4. You can opt to check one or more data tables.





NOTE

When synchronizing visualizations with different data tables, it is necessary for these data tables to have all the column names used on the synchronized variables.

A special case is when a Calculated Column is used on a synchronized variable with synchronization across different data tables. For each data table, aside from having a calculated column of the same name, ensure that they also have the same identity GUID. This can only be achieved by creating the first data table, then the calculated column, and then duplicating the entire data table. From that point, any required changes can be made in the duplicated data table, in terms of data connector settings, data source change, etc., all the while preserving the calculated column.


5. Click on the *Main* drop-down list and select the main visualization.





Delete a main visualization by clicking


6. To define the shared variables of a main visualization, click its **Settings** icon. The corresponding *Properties* pane displays. Click the **Sync** tab.



It is indicated at the top section of the tab that this visualization will be the *Synchronization Main* and will be the basis for the shared and visible variables across the selected data table(s).

Check the Synchronized Variables boxes of the variables that will be shared by the main visualization to its dependents.

For the child visualizations, the main visualization to which it will be synchronized into is indicated as well. For example "Synchronized by visualization.HorizontalBarGraph1".



7. Click the **Save** icon to save the changes.



Viewing the dashboard on the *Open Workbook in View Mode*, only the main visualization will have the enabled shelves.

Also, when a new value is selected in a synchronized variable, the dependent visualizations will be automatically updated.

Morphing Visualizations


You can morph a visualization by simply selecting the required resultant visualization from the available listing. When used in combination with the <u>copy</u> and <u>paste</u> functionality, dashboards can be quickly created.

Steps:

1. On the *Dashboard and Workbook Settings* pane, click the **Dashboard** tab and then the button. The *Morph* pane displays.



2. Select the visualization to morph from the drop-down list.



The list of visualizations is enabled.



3. Select another visualization on the list.

The visualization is changed to the new one.

NOTE

When morphing between visualizations with the same variables, there is no further configuration required. For example, from a Horizontal Bar Graph to a Vertical Bar Graph.

However, when morphing between visualizations with different variables, the new visualization will need to be configured to include columns for empty variables. For example, when converting from a Pie Chart to a Scatter Plot, the X and Y axis must be defined.

Breakdown


You can define hierarchical structures called breakdowns for each visualization. The hierarchy may be flat (single level) or multi-level. You can also define <u>multiple breakdowns</u> for each visualization so you can readily <u>select</u> the one most appropriate for the analysis task at hand.

The breakdown consists of up to three components:

- Rows which cross tab the visualization into rows.
- Columns which cross tab the visualization into columns.
- Hierarchy which displays the hierarchy within the visualization.

Not all visualizations support all three. If no breakdown is defined, a single aggregated data point will be shown in the visualization.


If enabled, the *Breakdown* shelf appears at the top left of each visualization.




The example above shows that there are no columns added yet as a breakdown (Empty state) with the <u>X variable</u> default values (0.00 to 1.00).

Adding Columns to the Breakdown


A Bar Graph without a breakdown will show a single bar.




Note that in this sample visualization, there is a column (Mcap (USD)) dragged and dropped to the X variable.



To add items to the breakdown, you can drag text columns from the *Data Table* pane to the *Items* pill or drop area under the **Breakdown** tab.




For example:




Note that the other controls where you can drop the dragged Text column are highlighted as well (X, Color, Details, Filters, Columns, Rows).


After dragging a data column to a breakdown, this will break apart the aggregated data into separate bars and the column is added under the *Items* drop area of the **Breakdown** tab and *Breakdown* section of the visualization. Also, the dragged column will replace the *Empty* state name.



You can opt to drag more columns into the current breakdown.




This will produce a multi-level hierarchy and the new column is added to the breakdown.





If the column has been dropped into the incorrect position, simply click and drag the column to the correct position in the visualization.





The visible detail level of the multi-level hierarchy can be adjusted by clicking on the breakdown column itself. This will grey out the hierarchy level.





Clicking on the breakdown column will update the display to show the level of detail again.

On the Visualization Settings pane, you can also perform the following:


- Modify the breakdown columns
- □ Sort the visualization for each <u>level of the breakdown</u>
- □ Sort the visualization based on the <u>breakdown column values</u>
- ☐ Add more breakdowns
- □ Select the breakdown to use
- Delete a breakdown column

Adding Parameterized Columns to the Breakdown


In this section, we will add the following <u>parameterized columns</u> to the breakdown:

Parameter	Value
Region	Europe
Country	BE


A Bar Graph without a breakdown (Empty) will show a single bar.




Note that in this sample visualization, there is a column (Mcap (USD)) dragged and dropped to the Yvariable.




Drag the **Region** field from the *Data Table* pane to the *Items* pill of drop area under the **Breakdown** tab. The value of the parameterized column is used in the breakdown (i.e., **Europe**).



Drag the **Country** field from the *Data Table* pane to the *Items* pill of drop area under the **Breakdown** tab. This will produce a multi-level hierarchy and the new parameterized column (i.e., **BE**) is added to the breakdown.




Drag the **Industry** field from the *Data Table* pane to the *Items* pill of drop area under the **Breakdown** tab. This will produce a multi-level hierarchy and the new column with its values is added to the breakdown. The first two levels will display the parameterized values **Europe** and **BE**.




Modifying the Columns of the Breakdown

If the dragged column is incorrect, instead of deleting, you can just select another column in the Items drop-down list.




The breakdown settings are modified along with the visualization.




Sorting the Visualization for Each Level of the Breakdown

You can sort visualizations based on the filled variables, plus alphabetically on the breakdown title.


For example, here are the available sorting methods for the Bar Graph – Horizontal visualization:






□ Sorting by Title (Default)

Sorting based on the breakdown column name values, in ascending order.



Sorting by Height


Sorting based on the height (X) variable values (eg., Mcap(USD).



This type of sorting is most useful in the following visualizations:

- Bar Graphs
- Treemaps (to produce a Heat Map)
- Stack Graphs
- Horizon Graphs
- Sorting by Color

Sorting based on the color variable values (e.g., 1 Month Change % (USD)).



Sorting the Visualization Based on the Breakdown Column Values

Sort the visualization in an **Ascending** or **Descending** or order by clicking on a breakdown level **Sort** icon.


Adding Breakdowns

You can define several breakdowns for a visualization.


Steps:

1. Under the Breakdown tab, click New Breakdown







A new **Empty** breakdown definition is added under the **Breakdown** tab with the **View** icon turned on. The visualization also shows a single bar.



2. To add more breakdown levels, drag text columns to the *Items* pill or drop area.



After dragging a data column to a breakdown, this will break apart the aggregated data into separate bars and the column is added under the *Items* drop area of the **Breakdown** tab and *Breakdown* section of the visualization. Also, the dragged column will replace the *Empty* state name.



You can have as many levels in the breakdown as you like, although best practice is to limit the hierarchy to five or fewer levels.

3. Click the Save icon on the toolbar.

When saved, the notification is displayed.

Selecting Other Breakdowns


To select the breakdown to use on the visualization, you can either double-click on an instance or click the **View** icon to turn it on . Note that if there are several breakdowns in a visualization, you must select one to use.

Deleting Breakdowns

Select a breakdown under the **Breakdown** tab of the *Visualization Settings* pane and click ...

Level of Details

Under the **Breakdown** tab, you can also define the *Level of Details* feature. This setting determines the automatic adjustment of the visible detail when drilling into a hierarchical visualization and restricts how many levels of visible detail can be displayed.



Manual

All levels of the breakdown can be shown.



For the example above, there are five breakdown levels:

Type > Super Region > Region > Store > Area



Drilling into the value of the lowest level (**Ambient**) will grey out the topmost level (**Type**) displaying only its value (**Chilled**). Furthermore, the visible details will only display the second to fifth levels (Super Region, Region, Store, and Area):



Then drilling into the first Ambient value for the North Super Region level:




Will grey out the second level (**Super Region**) displaying only its value (**North**). Furthermore, the visible details will only display the third to fifth levels (Region, Store, and Area):



To continue, drilling into the **Cold & Frozen** value for the **North East** Region level:




Will grey out the third level (**Region**) displaying only its value (**North East**). Furthermore, the visible details will only display the fourth to fifth levels (**Store** and **Area**):



One Level

Only one level will be shown. Initially, the only visible detail will be the topmost level (Type) and the rest of the levels will be greyed out.




Drilling into an area automatically shows the values of the next level (i.e., Super Region).




Two Levels

Displays two levels of visible detail.




Drilling into an area automatically shows the next two levels of detail.




Three Levels

Displays three levels of visible detail.



Drilling into an area automatically shows the next three levels of detail.



Four Levels

Displays four levels of visible detail.



Drilling into an area automatically shows the next four levels of detail.




Five Levels

Displays five levels of visible detail.



Drilling into an area automatically shows the next five levels of detail.



Cross Tabbing

A cross Tab is the division of a single visualization into smaller multiple visualizations across either on rows, columns or both. Each smaller child visualization displays the relevant portion of the data set. It can also be called trellising, or small multiples.

The purpose of a cross tab is to allow comparison across portions of the data set.

Cross tabbing is available in the following visualizations:


Bar Graph	Numeric Stacked Needle
Box Plot	OHLC Graph
Bullet Graph	Order Book
Candle Stick	Pareto Chart
Categorical Line Graph	Pie Chart
Circle Pack	Price Band
Donut Chart	Scatter Plot
Donut Gauge	Spread Graph
Dot Plot	Stacked Needle Graph
Funnel Chart	Stack Graph

- □ Grouped Needle Graph
- Heat Matrix
- Line Graph
- Needle Graph
- □ Numeric Needle Graph
- □ Numeric Line Graph


- Ticker Tile
- □ Treemap
- Time Combination
- Timeseries Scatter Plot
- Waterfall Chart

Steps:


1. Select a visualization that supports cross tabbing like a Bar Graph.



- 2. To add columns or rows, you can do the following:
 - Drag text fields from the Data Table pane to the Columns or Rows pill or on the drop area under the Breakdown tab




For example:



• Select from the **Rows** or **Columns** buttons on the visualization


This example is selecting from the **Columns** \Box button.



To search for a particular column, enter into the *Search Columns* box. You can also enter one or more characters into the *Search Columns* box and the suggested list of columns that matched the entries will be displayed.


Once dropped or selected, the visualization will be cross tabbed, producing a series of smaller visualizations for each item within the column dropped.

On both instances, the new column is added under the Breakdown tab and on the visualization.




Cross tabs can be across rows, across columns, or across both where two separate cross tabbing dimensions have been selected.


Dropping a text column onto the Columns section trellis the visualization horizontally:



While dropping a column onto the Rows section trellis the visualization vertically:



And finally dropping columns onto both *Rows* and *Columns* produces a series of smaller trellised visuals. Each showing the specified subset of the overall dataset.



AXES

Visualizations have different axes properties, and they can be categorized into:


- Cross Tab Axes
- Visualizations Axes
- □ <u>Table Visualization Axis</u>

NOTE

Axis definition is not available in the following visualizations: Map Plot, Network Graph, Surface Plot, Surface Plot 3D, Record Graph, Shapes, Timeseries Surface Plot, and Horizon Graph.

Cross Tab Axes


Visualizations that support cross tabbing, include the following settings for both the X and Y axes.



Setting	Description
Leaf Bar Thickness	The thickness of the leaf or lowest level of data. The default value is 80 .
Leaf Label Angle	The Label angle of the leaf or lowest level of data of the crosstab axis. Default is 0 , accepts values between -90 and +90 .

Inner Bar Thickness	The width or height allocated for the non-leaf components of the crosstab axis in pixels. Default is 80 .
Inner Label Angle	The angle of the non-leaf labels. Default is 0 , accepts values between - 90 and +90 .
Min Interval Length	The minimal interval in pixels between cross tabbed visualizations. Default is 100 .
Max Interval Length	The maximum interval in pixels between cross tabbed visualizations. Default is 400 .
Word Wrap	Determines whether to wrap the crosstab axis text.

Visualizations Axes





The X and Y axes of visualizations may include the following settings when accessed from the *Breakdown* section:

Setting	Description
Leaf Bar Thickness	The thickness of the leaf or lowest level of data.
Leaf Label Angle	The Label angle of the leaf or lowest level of data of the crosstab axis. Default is 0 , accepts values between -90 and +90 .
Inner Bar Thickness	The width or height allocated for the non-leaf components of the crosstab axis in pixels. Default is 80 .

Inner Label Angle	The angle of the non-leaf labels. Default is 0 , accepts values between - 90 and +90 .
Min Interval Length	The minimal interval in pixels between cross tabbed visualizations. Default is 20 .
Max Interval Length	The maximum interval in pixels between cross tabbed visualizations. Default is 400 .
Word Wrap	Determines whether to wrap the visualization axis text.

Some visualizations may also include the following X and Y axes settings:






Setting	Description
Scale	Determines whether the scale of the axis is Linear, Log, or Power.
	• Linear – a change between two values is based on addition e.g., 30, 60, 90, 120, 180, etc.
	 Log - a change between two values is perceived based on the ratio of the two values or based on multiplication.
	Once selected, the <i>Base</i> control displays with the value of the common base for the logarithmic scale (i.e., 10).

	You can opt to ent NOTE: Value canr Power – Works ac SIGN (MEASURE formula. Works like values and every v	er a new Base value the not be lower than 2. cording to the **LOG10 (MAX (1, A) the the Log scale except it value between -1 and 1 is alues between -100 and	BS (MEASURE))) can handle negative s set to 0.
Inverted	Determines whether th (for Horizontal) is inver		ertical) or X or Width axis
Show Title		abel. n opt to enter a custom 7 the visualization variable	
Axis Bar Thickness	The margin in pixels fo	r the axis. If set to zero, t	the axis is removed.
Preferred Tick Space	The preferred space in pixels between the minor grid lines across the axis.		
Minor Grid Line	How minor grid lines are drawn across the axis. Allowed values: None Dotted Dashed Solid		
Major Grid Line	How major grid lines are drawn across the axis. Allowed values: None Dotted Dashed Solid		
Tick Format	Set to From Variable to use the format string that is on the current variable displayed in the axis. Set to Metric Prefix to format the Tick labels in the numeric axes using the metric prefixes.		
Tickmarks	Click + to add and s Tickmarks Value Label Enter the Value and the Click + to add more	t 0 e Label.	

Table Visualization Axis

The Y axis of the Table visualization includes the following settings:



Setting	Description
Leaf Bar Thickness	The thickness of the leaf or lowest level of data. Default is 80.
Leaf Label Angle	The Label angle of the leaf or lowest level of data of the crosstab axis. Default is 0 , accepts values between -90 and +90 .
Inner Bar Thickness	The width or height allocated for the non-leaf components of the Table axis in pixels. Default is 80 .
Inner Label Angle	The angle of the non-leaf labels. Default is 0 , accepts values between - 90 and +90 .
Row Height	Defines the height of table rows in pixels. For tables created in versions before 2021.1 the configured "Minimum Interval Length" is used. Default is 30 .
Word Wrap	Determines whether to wrap the visualization axis text.


Show All Column Levels	Determines whether the space in the text axis should be allocated to all hierarchy levels, whether visible or not.
Show Column Labels	Determines whether column labels are visible or not. Enabled by default.
Show Grid Lines	Determines whether grid lines are visible or not.
Show Zebra Stripes	Determines whether to display alternating row colors (like zebra stripes) in the table.
Foreground	Foreground color of the Y-axis.
Background	Background color of the Y-axis.

VISUALIZATION STATIC FILTER


You can define a filter to a visualization based on a specific subset of the available data.

Steps:


1. Click on a visualization to display its *Properties* pane.



2. To add to the filter, drag text columns from the Data Table pane to the Filter drop area.




3. The column is added and the Visualization Settings pane changes to display the Filter properties.




Initially, there are no values added for the filter column.

4. Click on the filter column. The pane changes again.



5. Enter the Value.




The visualization is updated based on the filter column values.

6. You can opt to select a set dashboard parameter from the *Parameter* drop-down list.




This will overwrite the entered filter values.




NOTE The selected parameter must have values that are available on the filter column.

7. Drag and drop other text columns to add more filters.



- 8. Repeat steps 4 to 6 to define its value.
- 9. Click the **Save** icon on the toolbar.




Modifying Visualization Static Filter


If the column that was dragged and dropped to the Filter drop area is incorrect, you can modify it and its value.


Steps:

1. Click on a filter column.



2. Click on the Column drop-down list and select another column.






The visualization now displays a blank graph.



For this example, since the values of the dashboard parameter is not applicable to the new filter column, you can either select **No Parameter** or the applicable parameter in the list.



For this example, select **No Parameter** since the available dashboard parameters (Region and Area) are not applicable to the new filter column (Store).


3. Enter the Value.




The visualization is updated based on the filter column values.

Deleting Visualization Static Filter

Select a visualization static filter on the list and click the **Delete** button.



The filter is deleted.



RANK FILTERING

Rank filtering only uses the leaf item of the breakdown when creating the ranking. Consequently, this makes the number of items consistent, regardless of the hierarchy. Note that this behavior also applies to crosstabs.

Rank Filter is available in all non-time series visualizations that use the <u>Size</u> or <u>Height</u> variable:

Bar Graph
Bullet Graph - Horizontal & Vertical
Categorical Line Graph
Circle Pack
Dot Plot
Donut Chart
Donut Gauge
Funnel Chart
Heat Map
Map Plot
Network Graph
Pareto Chart
Pie Chart
Scatter Plot
Treemap
Waterfall Chart

It is also available in the Record and Table visualizations.

This section discusses the steps and guidelines to set the rank filtering using this sample data table.

Sample Data Table 1: SuperMarket


Region	Area	Туре	Amount Sold	Revenue
South West	Ambient	Store Cupboard	4,885.00	550,697.00
South West	Ambient	Home Products	2,314.00	323,094.00
South West	Ambient	Savoury	840.00	67,702.00
South West	Ambient	Confectionary	429.00	33,219.00
South West	Ambient	Tobacco	1,975.00	712,467.00
South West	Ambient	Soft Drinks	619.00	56,493.00
South West	Ambient	Chilled	415.00	22,825.00
South West	Cold & Frozen	Frozen	2,084.00	357,953.00
South West	Cold & Frozen	Chilled	9,478.00	1,059,714.00
South West	Cold & Frozen	Frozen Ice Creams	1,169.00	148,791.00
South West	Alcohol	Alcohol	2,916.00	1,170,043.00
Wales	Ambient	Store Cupboard	3,151.00	352,862.00

Wales	Ambient	Home Products	1,450.00	191,889.00
Wales	Ambient	Savoury	487.00	39,249.00
Wales	Ambient	Confectionary	150.00	8,870.00
Wales	Ambient	Soft Drinks	337.00	29,761.00
Wales	Ambient	Tobacco	1,267.00	454,652.00
Wales	Ambient	Chilled	321.00	17,655.00
Wales	Cold & Frozen	Frozen	1,332.00	226,840.00
Wales	Cold & Frozen	Chilled	6,316.00	702,994.00

Other settings on the Treemap visualization:


Breakdown	Size	Color
Type, Area, Region	Amount Sold	Revenue

Sample visualization: Treemap before the rank filter




Steps:

Click on a snapshot visualization and then click the Filters drop area on the Visualization Settings pane.
 The visualization filter properties are displayed.



Tap the Rank Filter Enabled slider to turn it on.
 The Rank Filter Mode drop-down list is enabled.



- 3. Select either of the Rank Filter Mode:
 - By Height/Size

Allows the visualization to be ranked based on the Size or Height variable.

By Sorting

Allows the visualization to be ranked based on the top values of the Size or Height variable.

- 4. Select either of the Rank Filter Scope:
 - Overall

For the flat rank, including all the existing leaf nodes.

Group

For the per inner node rank of leaf nodes under the same inner node.

5. Enter the value of the Limits.

Default values are -1,5,10,100,1000,10000.


For example, the values are set to -1,10,100,1000.

These limits can be selected either:


• in the *Limit* drop-down list in the visualization




on the Filter Settings pane




- 6. Select the ranking *Direction* that can be selected either:
 - in the Direction drop-down list in the visualization




• on the Filter Settings pane




Example 1: Selecting the **Height/Size** mode, **Overall** scope, **Top** direction, **10** as the limit, and **Amount Sold** as the *Size* variable.




Example 2: Selecting the **Height/Size** mode, **Group** scope, **Top** direction, **10** as the limit, and **Amount Sold** as the *Size* variable.



Example 3: Selecting the **Height/Size** mode, **Overall** scope, **Bottom** direction, **10** as the limit, and **Amount Sold** as the *Size* variable.




Example 4: Selecting the **Height/Size** mode, **Group** scope, **Bottom** direction, **10** as the limit, and **Amount Sold** as the *Size* variable.



7. Tap the **Fixed in Presentation Mode** slider to turn it on.

This disables the drop-down lists in the visualization. Only the labels of the options are displayed:



8. Click the Save icon.


When saved, the saved! notification is displayed.

Rank Filtering for the Table Visualization

For the Table visualization, the rank filter only uses the leaf item of the breakdown when creating the ranking. Consequently, this makes the number of items consistent, regardless of the hierarchy.


Steps:

Click on a Table visualization and then click the Filters drop area on the Visualization Settings pane.
 The visualization filter properties are displayed.



2. Tap the Rank Filter Enabled slider to turn it on.

This enables the Rank Filter Mode drop-down list and the Rank Filter Mode (set to By Sorting by default)



The Direction is set to Bottom by default.

- 3. Select either of the Rank Filter Scope:
 - Overal

For the flat rank, including all of the existing leaf nodes.

Group

For the per inner node rank of leaf nodes under the same inner node.

4. Enter the value of the Limits.

Default values are -1,5,10,100,1000,10000.


For example, the values are set to -1,10,100,1000.

These limits can be selected either:

• in the Limit drop-down list in the visualization



• on the Filter Settings pane




The data set will be limited to display the top/bottom n based on the sorting of the data. When a column is clicked for sorting, the data set will be limited accordingly.


Example 1: Selecting the **Overall** scope, **10** as the limit, and the breakdown fields are based on the sorting made on the first visual member, **Amount Sold (Bottom)**.



Example 2: Selecting the **Group** scope, **10** as the limit, and the breakdown fields are based on the sorting made on the first visual member, **Amount Sold**.



Example 3: Selecting the **Group** scope, **10** as the limit, and the breakdown fields are based on the sorting made on the second visual member, **Revenue (Top)**.



5. Tap the **Fixed in presentation mode** slider to turn it on.

This disables the drop-down lists in the visualization. Only the labels of the options are displayed.



6. Click the **Save** icon.

When saved, the Saved! notification is displayed.

SELECT VARIABLES

Variables are the columns of data used by visualizations. For example, if you have a database of sales information broken down by product, you might associate the total amount of sales for a given with the *Size* variable in a Treemap. You could also associate the difference between this year's sales and last year's sales to the *Color* variable for the same Treemap. This simple configuration will let you see at a glance which products are bringing in the most revenue and which products are increasing and decreasing in sales.

Each visualization uses a different set of variables, depending on the capabilities of the visualization:

Snapshot Visualizations

Visualization	Variables
Bar Graph – Vertical	Y, Color, Details, Style
Bar Graph - Horizontal	X, Color, Details, Style
Box Plot	Y (BoxPlot), Color, Details, Style
Bullet Graph - Vertical	Y, Reference Y, X, Color, Details, Style
Bullet Graph - Horizontal	X, Reference X, Y, Color, Details, Style
Categorical Line Graph	Y, Color, Details, Style
Circle Pack	Size, Color, Details, Style
Donut Chart	Size, Color, Details, Style
Donut Gauge	Size, Color, Details, Style
Dot Plot – Vertical	Y, Color, Opacity, Shape, Details, Style
Dot Plot – Horizontal	X, Color, Opacity, Shape, Details, Style
Funnel Chart	Size, Color, Details, Style
Heat Matrix	Color, Icons, Details, Style
Map Plot	Size, Color, Longitude, Latitude, Details, Style
Network Graph	Size, Color, Details, Style
Numeric Line Graph	X, Y, Color, Opacity, Details, Style
Numeric Line Graph – Vertical	X, Y, Color, Opacity, Details, Style
Numeric Needle Graph	X, Y, Size, Color, Opacity, Details, Style
Numeric Needle Graph – Horizontal	X, Y, Size, Color, Opacity, Details, Style
Numeric Stacked Needles	X, Y, Size, Color, Opacity, Details, Style
Numeric Stacked Needles – Horizontal	X, Y, Size, Color, Opacity, Details, Style
Pareto Chart	Left Y, Right Y, Color, Reference Color, Details, Style
Pie Chart	Size, Color, Details, Style
Record	Records, Color, Shape, Icons, Details, Style

Scatter Plot 3D	Z, X, Y, Size, Color, Opacity, Shape, Details, Style
Scatter Plot	X, Y, Size, Color, Opacity, Shape, Ref Lines, Details, Style
Shapes	Color, Shapes, Details, Style
Surface Plot	X, Y, Color, Details, Style
Surface Plot 3D	Z, X, Y, Color, Details, Style
Table	Records, Color, Shape, Icons, Details, Style
Ticker Tile	Color, Price, Change, Details, Style
Treemap	Size, Color, Icons, Details, Style
Waterfall Chart	Y, Color, Details, Style

Time Series Visualizations

Visualization	Variables
Candle Stick Graph	Y, Time Axis, Color, Ref Lines, Details, Style
Stacked / Grouped Needle Graph	Y, Time Axis, Color, Opacity, Ref Lines, Details, Style
Horizon Graph	Y, Time Axis, Details, Style
Line Graph	Y, Time Axis, Color, Opacity, Ref Lines, Details, Style
Needle Graph	Y, Time Axis, Color, Opacity, Ref Lines, Details, Style
OHLC Graph	Y (OHLC), Time Axis, Color, Ref Lines, Details, Style
Order Book	Y, Time Axis, Size, Color, Ref Lines, Details, Style
Price Band	Y, Time Axis, Color, Opacity, Ref Lines, Details, Style
Spread Graph	Y, Time Axis, Opacity, Ref Lines, Details, Style
Stack Graph	Y, Time Axis, Color, Ref Lines, Details, Style
Timeseries Scatter Plot	Y, Time Axis, Size, Color, Opacity, Shape, Ref Lines, Details, Style
Timeseries Surface Plot	Y, Time Axis, Color, Details, Style

Combination Visualizations


Visualization	Variables
Numeric Combination	Visualizations, X, Size, Color, Opacity, Shape, Ref Lines, Details, Style
Text Combination	Visualizations, <u>Text Axis</u> , <u>Size</u> , <u>Color</u> , <u>Opacity</u> , <u>Shape</u> , <u>Ref Lines</u> , <u>Details</u> , <u>Style</u>
Time Combination	Visualizations, <u>Time Axis</u> , <u>Size</u> , <u>Color</u> , <u>Opacity</u> , <u>Shape</u> , <u>Ref Lines</u> , <u>Details</u> , <u>Style</u>

Variable Constant State

Most of the variables (Size, X & Y, Z, Latitude & Longitude, Price, Change, Opacity) have a **Constant** state by default. When enabled, the constant state can be used as value for the variable.


Steps:

1. On the Visualization Settings pane, click Yvariable.



Initially, the constant state is disabled.

2. Click the Constant<Variable> value to expand its settings.



- 3. Tap the slider to turn on **Enabled**. *Empty* currently displays as the associated value of the Y variable.
- 4. Set the Value and Format as required.

Associating Columns to the Variables


You can associate columns of data from the data table in the *Design* Toolbox with the variables available for the visualizations in your dashboard.




Steps:

- 1. In the *Data Table* pane, select the column you want to associate with a variable.
- 2. Drag the column to the variable you want to use.


In this example, we are dragging and dropping the **Mcap(local)** data column to the *Size* variable drop area in a Treemap, with the **Industry** column added as the breakdown.




3. Drop the column to the Size variable drop area.



The column is displayed under the *Size* variable list and on the *Size* variable on the visualization. The Treemap also changes to reflect the values of the **Mcap(local)** column as the *Size* variable.




By default, the name of the variable is the dragged column, and the aggregate is Sum.




4. You can drag more data columns onto the same variable. This produces a list of options that the user can select from.

In our example, we have added the **RecScore** data column to the same *Size* variable for the Treemap.



The user will be able to quickly select between two different views of the data. In one view, the Treemap will associate *Size* with **Mcap (local)** and with **RecScore** in the second view.

Deleting Variables from a Visualization




VARIABLES CONFIGURATION

Size Variable Configuration

The Size variable is available in Circle Pack, Donut Chart, Donut Gauge, Funnel Chart, Map Plot, Network Graph, Numeric Needle Graph, Numeric Stacked Needle, Pie Chart, Scatter Plot, Scatter Plot 3D, Treemap, Time Combination, Time Series Scatter Plot visualizations.

Steps:

1. On the *Visualization Settings* pane, click the *Size* variable. To associate other columns from the data table, drag and drop them to the *Size* variable drop area. Select one to display the corresponding configuration pane.



2. Enter the label of the Size variable in the Variable Title field.

You can <u>parameterize the variable title</u> to support dynamic schema in the dashboards.

- 3. You can also change the column to the be used as the Size variable from the Column drop-down list.
- 4. Specify an aggregation method in the Aggregate field.


The default is Sum.

The Size variable also supports several other aggregate types:

If you set the aggregation method to **Cumulative Sum** or **Cumulative Sum by Max**, the *Sort By* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the sorting column for the aggregate.




Cumulative Sum By Max is, in practice, Cumulative Sum with a setting to use Max as the sort by aggregation.




• If you set the aggregation method to **Intercept** or **Slope**, the *Y Variable* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the Y-axis variable column for the aggregate.




• If you set the aggregation method to **Percent of Parent Reference**, **Percent of Total Reference**, or **Ratio of Sums**, the *Reference Column* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the reference column for the aggregate.




• If you set the aggregation method to **Percent of Total Change**, the *Previous Values Column* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the previous column for the aggregate.




• If you set the aggregation method to **Percentile**, the *Percentile* field is displayed. Specify the value that can be used to calculate the value of the selected percentile.



If you set the aggregation method to Weighted Harmonic Mean, Weighted Mean, Weighted Population Variance, Weighted Stdev, Weighted Stdevp, Weighted Sum, or Weighted Variance, the Weight Column drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the weight column for the aggregate.



- 5. The <u>Format</u> field lets you specify the format that numbers will be displayed in. Panopticon uses the same formatting rules as Excel.
- 6. Select the Divide By value to divide a number:
 - •
 - 1000 (by a thousand)
 - 10000
 - 1000000 (by a million)
 - 1000000000 (by a billion)



7. Click the Save icon on the toolbar.


When saved, the

notification is displayed.

X & Y Variables Configuration


The X and/or Y variables are available in Bar Graph, Box Plot, Bullet Graph, Categorical Line Graph, Dot Plot, Numeric Line Graph, Numeric Needle Graph, Numeric Stacked Needle, Scatter Plot, Scatter Plot 3D, Surface Plot, Surface Plot 3D, Waterfall Chart, Candle Stick Graph, Stacked /Grouped Needle Graph, Horizon Graph, Line Graph, Needle Graph, OHLC Graph, Order Book, Pareto Chart, Price Band, Spread Graph, Stack Graph, Timeseries Scatter Plot, Timeseries Surface Plot visualizations, Numeric Combination, Horizontal Combination, Vertical Combination.

The configuration pane for X & Y Variables is the same as for the Size variable.



Z Variable Configuration

The Z variable is available in the <u>3D Surface Plot</u> and <u>3D Scatter Plot</u> visualizations and is used to set the height. The configuration pane for the Z variable is the same as for the <u>Size variable</u>.



Latitude & Longitude Variables Configuration

The Longitude and Latitude variables are available in the Map Plot visualization. These coordinates are used to locate a place on Earth's surface.

The configuration pane for Lat and Long Variables is the same as for the Size variable.

NOTE

Default aggregation for the Latitude and Longitude variables are:

- Mean for numeric columns.
- Calculation for calculated columns.
- External if data table contains external aggregates for the column.

Price Variable Configuration

The Price variable is available in the <u>Ticker Tile</u> visualization.

The configuration pane for the Price variable is the same as for the Size variable.

Change Variable Configuration

The Change variable is available in the <u>Ticker Tile</u> visualization.


The configuration pane for the Change variable is the same as for the Size variable.

Opacity Variable Configuration

The Opacity variable is available in the <u>Dot Plot, Grouped Needle, Line Graph, Map Plot, Needle Graph, Numeric Line Graph, Numeric Needle Graph, Numeric Stacked Needle, Price Band Graph, Scatter Plot, Scatter Plot 3D, Spread Graph, Stacked Needle, Timeseries Scatter Plot, and Timeseries Scatter Plot in the <u>Combination Graph</u> visualizations.</u>


Steps:

1. On the Visualization Settings pane, click the Opacity variable.



You can set the Constant Opacity, if needed.

2. Click the **Constant Opacity** to expand its settings.



NOTE

Constant Opacity has a minimum of 0 to maximum of 1 value, and a step of 0.01. The **Up** and **Down** buttons have been removed in previous changes to numeric input component, but the mouse wheel can still be used to scroll between values.


3. Tap the **Enabled** slider to turn it on. *Empty* currently displays as the associated value of the *Opacity* variable.



You can opt to modify the following properties:

Property	Description
Opacity Value	Opacity value of the Opacity variable. The two nearest valid values are 0% and 100%.
Format	Format how numbers will be displayed.

4. To associate other columns from the data table, drag and drop them to the *Opacity* variable drop area. Select one to display the corresponding configuration pane.



5. Enter the label of the *Opacity* variable in the *Variable Title* field.

You can <u>parameterize the variable title</u> to support dynamic schema in the dashboards.

- 6. You can also change the column to the be used as the *Opacity* variable from the *Column* drop-down list.
- 7. Specify the aggregation method in the Aggregate field.


The default is Sum.

The *Opacity* variable also supports several other aggregate types:


• If you set the aggregation method to **Cumulative Sum** or **Cumulative Sum by Max**, the *Sort By* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the sorting column for the aggregate.




Cumulative Sum By Max is, in practice, Cumulative Sum with a setting to use Max as the sort by aggregation.




• If you set the aggregation method to **Intercept** or **Slope**, the Y *Variable* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the Y-axis variable column for the aggregate.



• If you set the aggregation method to **Percent of Parent Reference**, **Percent of Total Reference**, or **Ratio of Sums**, the *Reference Column* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the reference column for the aggregate.




• If you set the aggregation method to **Percent of Total Change**, the *Previous Values Column* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the previous column for the aggregate.



• If you set the aggregation method to **Percentile**, the *Percentile* field is displayed. Specify the value that can be used to calculate the value of the selected percentile.




If you set the aggregation method to Weighted Harmonic Mean, Weighted Mean, Weighted Population Variance, Weighted Stdev, Weighted Stdevp, Weighted Sum, or Weighted Variance, the Weight Column drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the weight column for the aggregate.




- 8. The <u>Format</u> field lets you specify the format that numbers will be displayed in. Panopticon uses the same formatting rules as Excel.
- 9. Select the Divide By value to divide a number:
 - 1
 - 1000 (by a thousand)
 - 10000
 - 1000000 (by a million)
 - 1000000000 (by a billion)
- 10. The visible range for the *Opacity* variable can either be calculated dynamically (the default, enabled **Dynamic**).




Or set between predefined limits by clicking **Fixed**. This reveals the *Min* and *Max* text boxes and populates them with default values taken from the data set.



11. Enter the Min Opacity (default 0%) and Max Opacity (default 100%) values.



The *Opacity* variable takes any numeric column and maps the values to their corresponding Opacity values. Consequently, it calculates the values' relative position in the domain of the column, and maps that to the same relative position for the domain of the Opacity values.




12. Click the **Save** icon on the toolbar.

BoxPlot Variable Configuration


The BoxPlot variable is available in the Box Plot visualization.

Steps:

1. On the *Visualization Settings* pane, click the *Y (BoxPlot)* variable. Initially, the variable has no value.



2. To associate other columns from the data table, drag and drop them to the *BoxPlot* variable drop area. Select one to display the corresponding configuration pane.



3. Enter the label of the BoxPlot variable in the Variable Title field.


You can <u>parameterize the variable title</u> to support dynamic schema in the dashboards.

4. The associated column is displayed in *Set All Columns* and all the five sub variables are automatically populated with this column: *First Column*, *Second Column*, *Third Column*, *Fourth Column*, and *Fifth Column*.


This allows for automatically drawing a boxplot based on a single column. The variable also allows for changing each column of each sub variables, which can be used in case the values are precalculated.

5. The percentile values of the member variables are configurable. Each percentile can be set to any value between **0** to **100**. The values default to **0** (Min), **25** (First Quartile), **50** (Median), **75** (Third Quartile), **100** (Max), respectively.

The percentile aggregate is calculated with inclusive median.




- 6. The <u>Format</u> field lets you specify the format that numbers will be displayed in. Panopticon uses the same formatting rules as Excel.
- 7. Select the Divide By value to divide a number:
 - , -
 - 1000 (by a thousand)
 - 10000
 - 1000000 (by a million)
 - 1000000000 (by a billion)
- 8. The visible range for the BoxPlot variable can either be calculated dynamically (the default, enabled **Dynamic**).



Check the **Always Include Zero** box to let the axis scale start at zero and grow to any number that may show up in the data.


Or set between predefined limits by clicking **Fixed**. This reveals the *Min* and *Max* text boxes and populates them with default values taken from the data set.



When saved, the Saved! notification is displayed.


Shape Variable Configuration

The Shape variable is available in the <u>Dot Plot</u>, <u>Map Plot</u>, <u>Scatter Plot</u>, <u>Scatter Plot 3D</u>, <u>Time Combination</u>, and <u>Timeseries Scatter Plot</u> visualizations.




Steps:

1. On the Visualization Settings pane, click the Shape variable.




You can opt to set the settings of the **Single Shape** variable state.


2. Click the **Single Shape** value to expand its settings.




3. Tap the **Enabled** slider to turn it on. [*Empty*] currently displays as the associated value of the *Shape* variable with the *Selected Shape* set to **FilledCircle**.



You can opt to modify the Shape Palette settings:




And then the corresponding Selected Shape:



NOTE

There is a default shape palette with a set of geometric symbols, and a shape palette named **Arial** with capital letters A-Z. You can add your own custom shape palettes from SVG files in the Theme-editor of Panopticon Real Time. The SVG files added to a palette must follow the same rules as custom SVG files used with the *Shapes* visualization.

4. To associate other columns from the data table, drag and drop them to the *Shape* variable drop area. Select one to display the corresponding configuration pane.




5. Enter the label of the Shape variable in the Title field.

You can <u>parameterize the variable title</u> to support dynamic schema in the dashboards.

- 6. You can also change the column to the be used as the Shape variable from the Column drop-down list.
- 7. Select the Shape Palette.

- 8. Click Recalculate Mapping to recalculate the mapping of the selected column values to the shapes.
- 9. For columns that are not mapped to a shape, select the *Default Shape* to be used.
- 10. Checking the Automatic Mapping box enables the Modes drop-down list:




- 11. You can either assign the shape assignment when new data is dynamically loaded into the visualization:
 - By Size

The shape assignment is based on the <u>Size</u> variable.

Alphabetically

The shape assignment is done alphabetically.

12. Click the **Save** icon on the toolbar.



Reference Variable Configuration

The Reference variable is available in the **Bullet** Graph visualization.


The configuration pane for the Reference variable is the same as for the <u>Size</u> variable.

Spread Variable Configuration

The Spread (Y) variable is available in the **Spread Graph** visualization.

Steps:

1. On the *Visualization Settings* pane, click the *Spread* variable. To associate other columns from the data table, drag and drop them to the *Spread* variable drop area. Select one to display the corresponding configuration pane.



2. Enter the label of the Spread variable in the Variable Title field.

You can <u>parameterize the variable title</u> to support dynamic schema in the dashboards.

- 3. You can also change the column to the be used as the Shape variable from the Value Column drop-down list.
- 4. Select the *Reference Column*. The difference with the *Value Column* will be the basis if the variability or spread of the data is positive or negative.

For example:


Value Column	Reference Column	Spread
-7.2%	-19.9%	12.7 (Positive)
-8.1%	-6.5%	-1.6% (Negative)

5. You can also specify an aggregation method in the *Aggregate* field.

The default is Sum.

The Spread variable also supports a number of other aggregate types:

• If you set the aggregation method to **Cumulative Sum** or **Cumulative Sum by Max**, the *Sort By* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the sorting column for the aggregate.




Cumulative Sum By Max is, in practice, Cumulative Sum with a setting to use Max as the sort by aggregation.




• If you set the aggregation method to **Intercept** or **Slope**, the Y *Variable* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the Y-axis variable column for the aggregate.




• If you set the aggregation method to **Percent of Parent Reference**, **Percent of Total Reference**, or **Ratio of Sums**, the *Reference Column* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the reference column for the aggregate.




• If you set the aggregation method to **Percent of Total Change**, the *Previous Values Column* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the previous column for the aggregate.



• If you set the aggregation method to **Percentile**, the *Percentile* field is displayed. Specify the value that can be used to calculate the value of the selected percentile.



If you set the aggregation method to Weighted Harmonic Mean, Weighted Mean, Weighted Population Variance, Weighted Stdev, Weighted Stdevp, Weighted Sum, or Weighted Variance, the Weight Column drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the weight column for the aggregate.




- 6. The <u>Format</u> field lets you to specify the format that numbers will be displayed in Panopticon uses the same formatting as Excel.
- 7. Select the *Divide By* value to divide a number:
 - 1
 - 1000 (by a thousand)
 - 10000
 - 1000000 (by a million)
 - 1000000000 (by a billion)
- 8. The visible range for the Spread variable can either be calculated dynamically (the default, enabled **Dynamic**).



Check the **Always Include Zero** box to let the axis scale start at zero and grow to any number that may show up in the data.

Or set between predefined limits by clicking **Fixed**. This reveals the *Min* and *Max* text boxes and populates them with default values taken from the data set.

notification is displayed.



Panopticon Web Authoring Guide


When saved, the

OHLC Variable Configuration

This configuration pane for OHLC variable is used by both the OHLC Graph and the Candle Stick Graph.

Steps:

1. On the *Visualization Settings* pane, click the *Y* (*OHLC*) variable. To associate other columns from the data table, drag and drop them to the *OHLC* variable drop area. Select one to display the corresponding configuration pane.



2. Enter the label of the OHLC variable in the Variable Title field.


You can <u>parameterize the variable title</u> to support dynamic schema in the dashboards.

- 3. Unlike other variables, the OHLC requires four input columns (*Open, High, Low & Close*). These are selectable from list boxes once the **Close** column has been dragged onto the OHLC variable slot.
- 4. You can also specify an aggregation method in the Aggregate field.

The default is Sum.

The OHLC variable also supports a number of other aggregate types:

• If you set the aggregation method to **Cumulative Sum** or **Cumulative Sum by Max**, the *Sort By* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the sorting column for the aggregate.




Cumulative Sum By Max is, in practice, Cumulative Sum with a setting to use Max as the sort by aggregation.




• If you set the aggregation method to **Intercept** or **Slope**, the Y Variable drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the Y-axis variable column for the aggregate.



• If you set the aggregation method to **Percent of Parent Reference**, **Percent of Total Reference**, or **Ratio of Sums**, the *Reference Column* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the reference column for the aggregate.




• If you set the aggregation method to **Percent of Total Change**, the *Previous Values Column* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the previous column for the aggregate.



• If you set the aggregation method to **Percentile**, the *Percentile* field is displayed. Specify the value that can be used to calculate the value of the selected percentile.



If you set the aggregation method to **Weighted Harmonic Mean, Weighted Mean, Weighted Population Variance, Weighted Stdev, Weighted Stdevp, Weighted Sum,** or **Weighted Variance**, the *Weight Column* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the weight column for the aggregate.




- 5. The <u>Format</u> field lets you specify the format that numbers will be displayed in. Panopticon uses the same formatting rules as Excel.
- 6. Select the Divide By value to divide a number:
 - 1
 - 1000 (by a thousand)
 - 10000
 - 1000000 (by a million)
 - 1000000000 (by a billion)
- 7. The visible range for the OHLC variable can either be calculated dynamically (the default, enabled **Dynamic**).




Check the **Always Include Zero** box to let the axis scale start at zero and grow to any number that may show up in the data.

Or set between predefined limits by clicking **Fixed**. This reveals the *Min* and *Max* text boxes and populates them with default values taken from the data set.



Reference Lines Variable Configuration

You can add a horizontal or vertical line to your chart (for this example, Scatter Plot) to indicate key values, important aggregates, or dates, etc. Adding the Y column to a Reference Lines variable can produce this visualization:




For this sample, after adding the same column used for the Y-axis (3 Month Change % (USD)) as a Reference Line, all of the values on the Scatter plot are then taken and sorted horizontally along the X-axis, then a line is drawn between the values.

The Reference Line variable is available in the <u>Table</u> and all the time series visualizations (except in the Horizon Graph and Timeseries Surface Plot).


Steps:

1. To associate columns from the data table, drag and drop them to the *Reference Lines* variable drop area. Select one to display the corresponding configuration pane.




- You can opt to change the column to the be used as the Reference Lines variable from the Reference drop-down list.
- 3. Specify the Line Width. Default is 1.


- 4. Specify the *Dot radius* (in pixels) of each data point. Default is **0**.
- 5. Select the *Line Interpolation*: **Linear, Stepped,** or **Smooth**.
- 6. Tap the **In Front** slider to display the lines in front of the scatter points.
- 7. Tap the Visible slider to enable the reference line of added columns. This is enabled by default.
- 8. Tap the **Interactive** slider to apply the interactive parameters of the column.
- 9. Enable:
 - Interpolate Time Gaps
 - Interpolate Na Value Gaps
- 10. Select the Dash Pattern: Dotted, Dashed, or Solid.
- 11. The Main Variable field displays the selected column that will be used as the main variable of the reference line.
- 12. Set the line color of an added column either by:
 - clicking the corresponding *Color* box to display the *Color* dialog to:




- select the color, or
- click to enter the values
 for RGB



for HSL



for the Hex color code




• or enter the Hex color code




+ Constant Reference Line

13. Click

A new constant reference line is added under the Reference Lines list.



This value (e.g., 100) can be used as point of reference as compared to the column values added in the Y-axis. You can also perform steps 2 to 13 to the added constants.



Color Variable Configuration

You can associate either numeric or text columns with the Color variable.

All the static and time series visualizations have the *Color* variable except in the <u>Spread</u> and <u>Horizon</u> graphs.

The configuration pane of the *Reference Color* variable in the <u>Pareto Chart</u> visualization is the same as what is discussed in this section.

Color Variable Configuration for Text Columns Using the Palette Color Source

The configuration pane for the *Color* variable changes depending on the column data type.


When a text column is added to the *Color* variable, the configuration pane displays the color associated with each categorical item, as specified with a default color palette (e.g., **Twenty Eight Colors**).

Note that since there are only 23 categorical items assigned to the colors of the selected palette, the remaining color palettes are left blank.


To use the #RGB Color Source, see Color Variable Configuration for Text Columns Using the RGB Color Source.

Steps:


1. On the *Visualization Settings* pane, click the *Color* variable. To associate other columns from the data table, drag and drop them to the *Color* variable drop area. Select one to display the corresponding configuration pane.




- 2. Enter the label of the Color variable in the Variable Title field.
 - You can parameterize the variable title to support dynamic schema in the dashboards.
- 3. You can also change the column to the be used as the Color variable from the Column drop-down list.
- 4. Select the **Palette** Color Source.
- Click the Palette drop-down list to display and select from the available ones. By default, Twenty Eight Colors is selected.



The number of categorical items for a visualization will depend on the selected palette. For example, if you select **Seven Standard Colors**, the list of categorical items will be reduced to seven.




To modify the color palettes, click to expand the *Palette* section.



See Color Palettes for more information.

- 6. Click Recalculate Colors to re-retrieve the categorical items and match them to the color palette.
- 7. Select the General Colors that will be used for the Color variable.
- 8. Checking the Automatic Mapping box enables the Modes drop-down list:



- 9. You can either assign the categorical color assignment when new data is dynamically loaded into the visualization:
 - By Size

The color assignment is based on the <u>Size</u> variable.

Alphabetically

The color assignment is done alphabetically.

NOTE

- This would occur as a result of navigation action defining a parameterized data set to be displayed in the visualization.
- The following visualizations will now use the selected <u>Height</u> variable:
 - o Bar Graph (Horizontal and Vertical)
 - o Bullet Graph (Horizontal and Vertical)
 - Dot Plot (Horizontal and Vertical)
 - o Line Graph
 - o Numeric Line Graph
 - Needle Graph
 - o Order Book Graph
 - Pareto Chart
- The following visualizations are using the selected <u>Size</u> variable:
 - Circle Pack
 - Map Plot
 - Network Graph
 - o Pie Chart
 - o Scatter Plot
 - Stack Graph
 - Timeseries Scatter Plot
 - o Treemap

The rest of the visualizations will perform as before.

10. Click the Save



icon on the toolbar.

When saved, the



notification is displayed.

Color Variable Configuration for Text Columns Using the #RGB Color Source

Aside from assigning the categorical items to the colors of the selected palette, the **color names** (i.e., red, green, blue, etc.) or **Hex Codes** (i.e., #FFFFFF, #000000, etc.) in a column of the data table can be used.

For example, the data table has the following columns:

А	В	BrowserColors	ColorCodes	Mix
а	10.00	red	#70db8c	red
a1	11.00	green	#70dbd4	#70dbd4
a2	12.00	pink	#9437bf	70dbd4
a3	14.00	purple	#70dbd4	ff70dbd4
a4	13.00	blue	#707cdb	Orange
a5	15.00	orange	#c9db70	Orange
a6	16.00	yellow	#db4132	#db4132

The values of the *BrowserColors*, *ColorCode*, and *Mix* columns can be used as colors (background or text) for a column in the visualization.


NOTE

Color names are case-insensitive. Some color names consist of two or three words, and they must never be entered with spaces. For example, a correct value is 'DarkOliveGreen'.


The 140 color names supported by all modern browsers can be used: https://www.w3schools.com/colors/colors_names.asp.

Steps:

1. To associate other columns from the data table, drag and drop them to the *Color* variable drop area. Select one to display the corresponding configuration pane.




Note that the values of the *BrowserColumns* column do not match the associated color palette. To use the color names, select the **#RGB****Color Source.**




- 2. Select the General Colors that will be used for the Color variable.
- 3. Select the *Mapping Column* that will be used when new data is dynamically loaded into the visualization. For this sample table visualization:




If you want to use the colors in the *BrowserColors* column as background for the *B* column, you can do so by selecting **B** under the *Records* pane list.



In the Color drop-down list, select BrowserColors.



The values of BrowserColors column are applied as the background color of the B column.




4. Click the **Save** Save icon on the toolbar.

When saved, the Saved! notification is displayed.

Color Variable Configuration for Numeric Columns


When you add a numeric column to a *Color* variable, the configuration pane displays a set of options similar to the pane for the <u>Size</u> variable. This allows you to define the data display <u>format</u> and aggregation method:



Other configuration options for numeric color variables include:


Range

The Min and Max text boxes are populated default values from the data set.



□ Automatic Limits/Range Calculation

Disables the Range option and supports either:



• Zero Center range calculation



Mean Center range calculation




Divide By


Divide By 1

Enter the *Divide By* value then click \checkmark to divide fixed and automatic ranges.


For example, for this range:



When the Divide By is 10000, then the range values will be:





Another example for the Automatic Range:





When the *Divide by* is **1000000**, then the automatic range values will be:





Palette

The sequential and diverging color palettes that are used in numeric color variables in visualizations


General Colors

The general colors to be used for visualizations.


Continuous/Stepped Colors

The color palette can either be a continuous color gradient or a stepped color gradient.

You can define this setting using the appropriate radio button.



Select the number of steps in the gradient in the Steps list box.




Reversed Colors

You can reverse the color palette for cases where a high number indicates poor performance. For example, if your data shows high risk as a high number, it may be more useful to display high risk using **Red** rather than Blue.




Distinct Outlier Colors

When outliers are of particular interest, you can highlight outliers using the Distinct Outlier Colors function.



□ Highlighted Outlier Colors

Where only the outliers are important, the central color range is grayed and only the *Distinct Outlier Colors* are highlighted in the visualization.




Panopticon supports two types of Numeric Color Palettes: Sequential and Diverging.

Sequential Color Palettes

Sequential Palettes use a two-color gradient between a minimum and a maximum value. Numeric column containing only positive values default to a Sequential Palette using the **White-Blue** color palette.


In this case the range *Mid* point is disabled, and the *Min* and *Max* points are populated with defaults from the data set.



Diverging Color Palettes


Diverging Palettes use a three-color gradient between a minimum, middle and a maximum value. Numeric columns containing both positive and negative values default to the Diverging Palette with the **Red White Blue** color palette selected.


Diverging Palettes use the **Range Midpoint**. The *Min*, *Mid* and *Max* points are populated with defaults from the data set.




General Colors and Shared Single Configuration

For the <u>Table</u>, <u>Record Graph</u>, <u>Time Combination</u>, <u>Numeric Combination</u> and <u>Text Combination</u> visualizations, instead of associating data table columns to the *Color* variable, you can modify the default *General Colors* and *Shared Single* settings.








Steps:

- 1. Click the **Color** button.
- 2. Click General Colors to expand.



- 3. Select the <u>General Colors</u> such as the axis, background, border, and focus colors, that will be used in the visualization.
- 4. Click Shared Single to expand.

These are the single colors that will be shared in a workbook for:


- Records in Table and Record visualizations for the background, text, or shape
- Visual members in Combination visualizations for the background or text

By default, the color is set to




5. To edit the color palettes, click the *Palette* drop-down list and *Edit Color Palettes* ...

The available light and medium single colors are displayed. Note that they are all included and cannot be deleted.




- 6. You may opt to uncheck any of the Include boxes to exclude them in the single color palette options.
- 7. Click on a single color option to set it as the palette.



8. You can also opt to click:





9. Click the Save


Icons Variable Configuration

You can drag and drop numeric and text columns onto the *lcons* variable. The options available in the configuration pane will depend on the type of data in the column. You can also assign multiple icons for each single source column.


The Heat Matrix, Treemap, and Table visualizations have the Icons variable.

Steps:

To associate columns from the data table, drag and drop them to the Icons variable drop area. Select a numeric column to display the corresponding configuration pane.



This displays the configuration pane.



- 2. Enter the label of the *Icons* variable in the *Variable Title* field.
- 3. You can also change the column to the be used as the Icons variable from the Column drop-down list.
- 4. Specify an aggregation method in the Aggregate field.

The default is Sum.

The *lcons* variable also supports several other aggregate types:


• If you set the aggregation method to **Cumulative Sum** or **Cumulative Sum by Max**, the *Sort By* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the sorting column for the aggregate.



Cumulative Sum By Max is, in practice, Cumulative Sum with a setting to use Max as the sort by aggregation.




• If you set the aggregation method to **Intercept** or **Slope**, the Y Variable drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the Y-axis variable column for the aggregate.



• If you set the aggregation method to **Percent of Parent Reference**, **Percent of Total Reference**, or **Ratio of Sums**, the *Reference Column* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the reference column for the aggregate.



If you set the aggregation method to **Percent of Total Change**, the *Previous Values Column* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the previous column for the aggregate.



• If you set the aggregation method to **Percentile**, the *Percentile* field is displayed. Specify the value that can be used to calculate the value of the selected percentile.




If you set the aggregation method to **Weighted Harmonic Mean, Weighted Mean, Weighted Population Variance, Weighted Stdev, Weighted Stdevp, Weighted Sum,** or **Weighted Variance**, the *Weight Column* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the weight column for the aggregate.




- 5. The *Format* field lets you specify the format that numbers will be displayed in. Panopticon uses the same formatting rules as Excel.
- 6. Select the Divide By value to divide a number:
 - •
 - 1000 (by a thousand)
 - 10000
 - 1000000 (by a million)
 - 1000000000 (by a billion)
- 7. Click the **Add Icon** ⁺ button to complete the task.


Clicking the Add Icon button with a numeric column displays a new section where you can specify:



- 8. Enter the Label of the new icon.
- 9. Specify the numeric range (*Min* and *Max*) to display the icon. Leaving the Min and Max fields empty implies no limit.
- 10. Select the *Icon* from the drop-down list.




- 11. You can also opt to select an **External Image**. Click **Choose File** to display the *Open* dialog and select the icon that will be used.
- 12. To add more icons, click the **Add Icon** + and repeat steps 8 to 11.
- 13. Click the **Save** icon on the toolbar.




You can add Icons based on text columns in a similar way.

Steps:


1. To associate columns from the data table, drag and drop them to the *Icons* variable drop area. Select a text column to display the corresponding configuration pane.




This displays the configuration pane.



- 2. Enter the label of the *Icons* variable in the *Variable Title* field.
- 3. You can also change the column to the be used as the *lcons* variable from the *Column* drop-down list.
- Click the Add Icon button to complete the task.
 Clicking the Add Icon button with a numeric column displays a new section where you can specify:




- 5. Enter the Label of the new icon.
- 6. The *Raw Pattern* field lets you specify a text string. When a node in the visualization matches the text string, the corresponding icon is displayed. Leaving the *Raw Pattern* field empty creates a match on non-empty strings.
- 7. Select the *Icon* from the drop-down list.



8. You can also opt to select an **External Image**. Click **Choose File** and select the icon that will be used.

9. To add more icons, click the **Add Icon** $^+$ and repeat steps 5 to 8.




Records Variable Configuration

The *Records* variable is available in the <u>Record Graph</u> and <u>Table</u> visualizations.

Steps:

1. To associate columns from the data table, drag and drop them to the *Records* variable drop area. Select a text column to display the corresponding configuration pane.

The name of the dragged column and its aggregate (e.g., Text Unique) are displayed as the header.



- 2. You can opt to change the column to the be used as the Record variable from the Column drop-down list.
- 3. Select the text aggregation method from the *Aggregate* field: **Count Distinct**, **Text Unique** (default), or **Text Concat Distinct**.
- 4. Enter the label of the Record variable in the Variable Title field.
- 5. Select the column that will be used as the *Color* in the *Apply Color To* field.
- 6. Set how the color variable is displayed in the Apply Color To drop-down: Background, Text, or Text.

Sample 1: If 1 Day Change % (USD) column is selected and the Apply Color To is set to Background, then the visualization will be:

Name	Auckland	Contact Energy Ltd.	Fletcher Building Ltd.	Sky City	Telecom Corp. of New
	International Airport			Entertainment Group	Zealand Ltd.
	Ltd.			Ltd.	

Sample 2: If Industry column is selected and the Apply Color To is set to Text, then the visualization will be:


Name	Auckland	Contact Energy Ltd.	Fletcher Building Ltd.	Sky City	Telecom Corp. of New
	International Airport			Entertainment Group	Zealand Ltd.
	Ltd.			Ltd.	

Sample 3. If Industry column is selected and the Apply Color To is set to Shape, then the visualization will be:




Displaying the shape is a useful visual cue in a record graph. Users will be able to build a legend that will display each unique combination of shape and color, along with the values from the columns used for the shape and color.

When selecting **Shape** as the Apply Color To value, ensure to select the Shape value in the drop-down list.



Click the *lcons* drop-down and check the boxes of the <u>columns with icons</u> that will be assigned for this particular column.




8. Click the **Save** icon on the toolbar.

When saved, the Saved! notification is displayed.

For numeric records, follow the steps below.

Steps:

1. Select a numeric column to display the corresponding configuration pane.



- 2. You can opt to change the column to the be used as the Records variable from the Column drop-down list.
- 3. Specify an aggregation method in the Aggregate field.

The default is **Sum**.

The Records variable also supports several other aggregate types.

• If you set the aggregation method to **Cumulative Sum** or **Cumulative Sum by Max**, the *Sort By* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the sorting column for the aggregate.

Aggregate	Cumulative Sum 🔻	ڻ
Sort By	Mcap(USD)	~


Cumulative Sum By Max is, in practice, Cumulative Sum with a setting to use Max as the sort by aggregation.




If you set the aggregation method to **Intercept** or **Slope**, the *Y Variable* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the Y-axis variable column for the aggregate.



• If you set the aggregation method to **Percent of Parent Reference**, **Percent of Total Reference**, or **Ratio of Sums**, the *Reference Column* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the reference column for the aggregate.



• If you set the aggregation method to **Percent of Total Change**, the *Previous Values Column* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the previous column for the aggregate.



• If you set the aggregation method to **Percentile**, the *Percentile* field is displayed. Specify the value that can be used to calculate the value of the selected percentile.



If you set the aggregation method to **Weighted Harmonic Mean, Weighted Mean, Weighted Population Variance, Weighted Stdev, Weighted Stdevp, Weighted Sum,** or **Weighted Variance**, the *Weight Column* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the weight column for the aggregate.




- 4. The <u>Format</u> field lets you specify the format that numbers will be displayed in. Panopticon uses the same formatting rules as Excel.
- 5. Select the Divide By value to divide a number:
 - •
 - 1000 (by a thousand)
 - 10000
 - 1000000 (by a million)
 - 1000000000 (by a billion)
- 6. Enter the label of the Record variable in the Variable Title field.
- 7. Select the column that will be used as the Color in the Apply Color To field.
- 8. Sets how the color variable is displayed in the Apply Color To drop-down: Background or Text.

Sample 1: If 1 Day Change % (USD) column is selected and the Apply Color To is set to Background, then the visualization will be:




Displaying the shape is a useful visual cue in a record graph. Users will be able to build a legend that will display each unique combination of shape and color, along with the values from the columns used for the shape and color.

When selecting **Shape** as the Apply Color To value, ensure to select the Shape value in the drop-down list.



9. Click the Icons drop-down and check the boxes of the <u>columns with icons</u> that will be assigned for this particular column.



Details Variable Configuration

The *Details* variable controls the information that appears on the pop-up when hovering over a specific item within a visualization. It also controls the information available for export from the visualization.


You can also control whether the following items are displayed or hidden in the Details pop-up:

- Other visualization variables, including Size, Height, X, Y, Color, and Icon variables
- ☐ Time (Current Time period for a Time Series visualization)
- Additional variables specifically added to appear in the Details pop-up


Steps:

1. Click on the **Details** button of a visualization. The *Details Settings* pane displays along with the available variables of the visualization.


Sample 1: Scatter Plot visualization has HeightX, HeightY, Size, Color, Opacity, Shape, and Reference Lines variables under the *Details* pane.



Sample 2: Bar Graph – Vertical visualization has HeightY and Color variables under the *Details* pane.




Sample 3: Time Combination visualization has Visuals and Time variables under the Details pane.



- 2. Select the Title Style: Title, Visible Path, or Full Path.
- 3. By default, **Popup Visible** is enabled to display the *Details* pop-up. Tap the slider to turn it off.
- 4. Tap the **Hide Null Values** slider to turn it on.
- 5. Select the Selection in Popup:
 - On

The Details pop-up of the selection in the visualization is displayed.



Off
 The selection in the *Details* pop-up is turned off.




Inherit

The selection option in the *Details* pop-up is inherited from the workbook properties.


6. You can also drag and drop numeric columns from the *Data Table* pane to the **Details** or on the *Details* pane.



The column is added under the *Details* pane.



7. Click on the column to display the configuration pane.



8. Enter the label of the *Details* variable in the *Variable Title* field.

You can <u>parameterize the variable title</u> to support dynamic schema in the dashboards.


- 9. You can opt to change the column to the be used from the Column drop-down list.
- 10. Specify an aggregation method in the Aggregate field.

The default is Sum.


• If you set the aggregation method to **Cumulative Sum** or **Cumulative Sum by Max**, the *Sort By* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the sorting column for the aggregate.




Cumulative Sum By Max is, in practice, Cumulative Sum with a setting to use Max as the sort by aggregation.




• If you set the aggregation method to **Intercept** or **Slope**, the *Y Variable* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the Y-axis variable column for the aggregate.




• If you set the aggregation method to **Percent of Parent Reference**, **Percent of Total Reference**, or **Ratio of Sums**, the *Reference Column* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the reference column for the aggregate.




• If you set the aggregation method to **Percent of Total Change**, the *Previous Values Column* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the previous column for the aggregate.



• If you set the aggregation method to **Percentile**, the *Percentile* field is displayed. Specify the value that can be used to calculate the value of the selected percentile.




If you set the aggregation method to Weighted Harmonic Mean, Weighted Mean, Weighted Population Variance, Weighted Stdev, Weighted Stdevp, Weighted Sum, or Weighted Variance, the Weight Column drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the weight column for the aggregate.




- 11. The *Format* field lets you specify the format that numbers will be displayed in. Panopticon uses the same formatting rules as Excel.
- 12. Select the Divide By value to divide a number:
 - 1
 - 1000 (by a thousand)
 - 10000
 - 1000000 (by a million)
 - 1000000000 (by a billion)
- 13. You can also drag and drop text columns from the *Data Table* pane to the **Details** button or on the *Details* pane.

The column is added under the Details pane.





14. Click on the column to display the configuration pane.



- 15. Enter the label of the Details variable in the Variable Title field.
 - You can parameterize the variable title to support dynamic schema in the dashboards.
- 16. You can also change the column to the be used from the Column drop-down list.
- 17. Select the text aggregation method from the *Aggregate* field: **Count Distinct**, **Text Unique** (default), or **Text Concat Distinct**.
- 18. The Format field lets you specify the format that the text will be displayed in. Panopticon uses the same formatting rules as Excel.
- 19. By default, all of the variables are set to be **Visible** on the *Details* pop-up.


For example, when the *Height* variable column is **Revenue** and set to **Visible**, the value of *Revenue* is displayed in the *Details* pop-up.







Tap the Visible slider to turn it off so the variable detail will not be displayed.






20. Tap the **Append Separator** slider to display the separator of the values.







21. For time series visualizations, you can set the current time period that will be displayed on the *Details* pop-up. Otherwise, skip to step 22.



Set the Variable Title and Format of the time.

For example:





22. Click the **Save** icon on the toolbar.

When saved, the Saved! notification is displayed.


Details Variable Configuration for Visualizations with Records or Visuals Variable

In addition to the *Details* variable configuration discussed in the <u>previous</u> section, you can set the records variable (for Table and Records visualizations) or visuals variable (for Time Combination, Numeric Combination and Text Combination visualizations) that will be displayed on the *Details* pop-up.


Steps:

 Click on the **Details** button of a visualization. The *Details Settings* pane displays along with the available variables of the visualization.

Sample 1: Table visualization has Records and Icons variables under the *Details* pane.




Sample 2: Time Combination visualization has Visuals and Time variables under the *Details* pane.



2. Expand the Visuals or Records variables.


Sample 3: Table visualization with three records added.




Clicking on an item on the visualization will display the values of the three records on the Details pop-up.



Sample 4: Time Combination visualization with six visualization members added.




Clicking on an item on the visualization will display the values of the six visualization members along with the Time variable on the *Details* pop-up.



3. Click the corresponding drop down and check the boxes of the records or visualization members that will be displayed on the *Details* pop-up.


Sample 5: Two records are selected for the Table visualization.



Clicking on an item on the visualization will only display two records on the Details pop-up..



Sample 6: Three visualization members are selected for the Time Combination visualization.



Clicking on an item on the visualization will only display the three visualization members along with the Time variable on the *Details* pop-up.



4. Click the **Save** icon on the toolbar.




Time Axis Variable Configuration

All of the time series visualizations have the *Time Axis* variable. There is no need to drag and drop columns to this variable.

Steps:


1. Click on the **Time Axis** variable drop area of a time series visualization. The *Time Axis Settings* pane displays.



Visualizations supporting time axes include the following settings:

Setting	Description
Axis Bar Thickness	The margin in pixels for the time axis. The time axis is hidden if this is set to zero . Default is 25 .
Preferred Tick Space	The preferred space in pixels between minor grid lines across the axis. Default is 100 .
Style	Defines that the time-based axis is displayed across two rows, with the start and end points displayed on the bottom row.
	When Relative is selected, the time forwards and backwards from a set time (i.e., midnight will be shown as 00:00 on the axis) will be displayed. The prior hours/days from midnight at the start of day are negative and the future hours/days are positive.
	For example:
	Last midnight is 00:00

	 Noon yesterday is -12:00 (-12 hours) Noon today is 12:00 (+12 hours) The axis values can have the following tick mark labels: -12.00, -6.00, 0:00, 6.00, 12:00 		
End Points	 Determines whether to display end points. Allowed values: Automatic – automatically displays the end points. None – end points are not displayed. Custom – allows the selection of the Date/Time format of end points. 		
Tick Points	Determines whether to display tick points. Allowed values: Automatic – automatically displays the tick points. None – tick points are not displayed. Custom – allows the selection of the Date/Time format of tick points.		
Align to Time Window	Align with the time window set in the <i>Time Filter Box</i> . Enabled by default when creating a new time series visualization.		
Zero Grid Line	For the Relative Style , set how a major X axis grid line is drawn:		
Snapshot Grid Line	Determines whether a grid line is drawn showing the snapshot location. Allowed values: None Dotted Dashed Solid When the Snapshot Grid Line is rendered, the Set Snapshot Here option will be available in the visualization context menu in the web client.		
Minor Grid Line	Determines whether minor grid lines are drawn across the axis. Allowed values: None Dotted Dashed Solid		
Visible Periods	Determines whether: a standard calendar time axis is shown (Calendar). weekends are hidden (Work Week). weekends and closed market hours are hidden (Work Hours). The settings pane changes to allow the addition and setting of the work hours.		
	Visible Periods Work Hours ▼		
	Work Hours Open Close +		
	09:30 16:00		
	 Open – Defines what time the market opens. Close – Defines what time the market closes. 		



2. Click the **Save** icon on the toolbar.


When saved, the notification is displayed.

Text Axis Variable Configuration for the Text Combination Graph

The Text Axis Combination graph has a time axis variable that you can configure. There is no need to drag and drop columns to this variable.

Steps:

1. Click on the **Text Axis** variable drop area of the Text Combination graph. The *Text Axis Settings* pane displays.



2. Define or select the value of the following settings:

Setting	Description
Leaf Bar Thickness	The thickness of the leaf or lowest level of data. The default value is 40 .
Leaf Label Angle	The Label angle of the leaf or lowest level of data of the crosstab axis. Default is 0 , accepts values between -90 and +90 .
Inner Bar Thickness	The width or height allocated for the non-leaf components of the Table axis in pixels. The default value is 40 .
Inner Label Angle	The angle of the non-leaf labels. Default is 0 , accepts values between -90 and +90 .
Min Interval Length	The minimal interval in pixels between cross tabbed visualizations. Enabled by default and the value is set to 20 .
Max Interval Length	The maximum interval in pixels between cross tabbed visualizations. Tap the slider to enable. The default value is 400 .
Word Wrap	Determines whether to wrap the visualization axis text.

3. Click the Save icon on the toolbar.

When saved, the notification is displayed.


Style Variable Configuration for Visualizations

The Style variable allows setting the style of the visualization and its title.


Steps:

On the Visualization Settings pane, click the Style variable to display the style settings you can configure.
 Initially, the **Default** style will be based on the default visualization style that is set for the selected theme of the workbook.

For the **Light** theme example:



For the **Dark** theme example:




2. You may opt to modify the colors of the following properties:

Property	Description
Foreground	Foreground color of the visualization and title.
Background	Background color of the visualization and title.
Border	Border color of the visualization.


- 3. Select the visualization and title Font.
- 4. Specify the visualization and title Font Size.
- 5. You may set to **Bold** and **Italic**.
- 6. Specify the Border Size of the visualization.
- 7. Select the visualization title Alignment: Left, Middle, or Center.
- + Update Style →
 - Click and select any of the following options:
 - Set current as default Save the changes and set it as the default.
 - Create custom style Save the changes and set it as a custom style.

The Style pane updates to display the Title control.



- Enter the custom style Title.
- If there are additional changes made, click **Update Current Style** in the *Update Style* drop-down.

The new custom style is added in the Workbook > Theme > Custom Styles list.



If published, the custom style configuration of the visualization will be added to the Global custom styles list and can be applied to other visualizations.

- Reset to default Revert to the original default settings.
- 9. Click the **Save** icon on the toolbar.

 When saved, the notification is displayed.

Supported Parameterized Variable Titles


This section discusses the list of variable titles that can be parameterized. For example, you can use a dashboard parameter reference instead of a hardcoded string as the title for the visualization variables.

Variable	Supported Parameterized Title
Size	~
X	✓
Υ	✓
Z	✓
Latitude	✓
Longitude	✓
Price	✓
Change	✓

Opacity	✓
Box Plot	✓
Shape	✓
Reference	✓
Visuals	✓
Spread	✓
OHLC	✓
Color	✓
Records	✓
Details	✓
Icons	X
Reference Line	X
Time Axis	X
Text Axis	X

TABLE VISUALIZATION

The Table visualization warrants a separate explanation; given it can display mini visualizations in each table cell, which are called micro-charts, and unlike other visualizations can display many data variables.



Each row of the Table is defined by the hierarchy, added to the <u>breakdown</u>. If there are too many rows, a vertical scroll bar will be displayed.




Dragging columns from the *Data Table* pane to the *Records* variable drop area creates the columns of the table. If there are too many columns, a horizontal scroll bar will be displayed:



Color and lcons are added as with other visualizations.

Aside from being displayed as Text, visual numeric columns can also be configured to these visualizations:



Static numeric data:


- □ Dot
- □ Bar
- Bullet

Time series numeric data:

- Needle
- □ Line

Records Variable Configuration for the Table Visualization


The configuration of the records added to the table visualization will depend on how the numeric or text columns will be displayed:




Steps:

1. Click on a numeric column under the Records variable list.


This displays the configuration pane.



- 2. You can opt to change the column to the be used as the *Records* variable from the *Column* drop-down list.
- 3. Select how the column values will be displayed:
 - Text



This visualization type displays the following configuration settings:




• Specify to what the color variable selected will be applied to:



Background

Applies the color to the background.






Text

Applies the color to the text.







Shape


Displaying the shape is a useful visual cue in a table. Users will be able to build a legend that will display each unique combination of shape and color, along with the values from the columns used for the shape and color.

When selecting **Shape** as the *Apply Color To* value, ensure to select the *Shape* value in the drop-down list.






Select the Value Alignment



By default, **By Data Type** is selected. This means, for text values, it is aligned to the left. For numeric or Data/Time data type, the value is aligned to the right.


- Tap the **Show Value Label** slider to display the column values.
- Click the *lcons* drop-down and check the boxes of the <u>columns with icons</u> that will be assigned for this
 particular column.



Horizontal <u>Dot Plot</u>



This visualization type displays the following configuration settings:



- Set the Dot Radius. Default is 5.
- Select the Shape that will be applied to the dot plot.



Select whether the <u>Scale</u> of the axis is Linear, Log10, or Power.




- Check the *Inverted* box. The dot plots on the x-axis is inverted.
- Select whether Tick Mark Format will be Metric Prefix or From Variable.



- Enter the Preferred Tick Space. Default is 20.
- Horizontal <u>Bar Graph</u>



This visualization type displays the following configuration settings:




- Tap the Show Bar Values slider to display the bar values.
- Set wether the <u>Scale</u> will be **Linear** or **Power**.
- Check the *Inverted* box. The bar graph on the x-axis is inverted.
- Select whether Tick Mark Format will be Metric Prefix or From Variable.



- Enter the Preferred Tick Space. Default is 20.
- Horizontal <u>Bullet Graph</u>



This visualization type displays the following configuration settings:



- Enter the Max Bullet Thickness. Default is 15.
- Set wether the <u>Scale</u> will be Linear or Power.
- Check the *Inverted* box. The bullet graph on the x-axis is inverted.


Select whether Tick Mark Format will be Metric Prefix or From Variable.



- Enter the Preferred Tick Space. Default is 20.
- Needle Graph (time series data)




This visualization type displays the following configuration settings:



• Enter the Needle Width. Default is 1.


- Tap the Set Width to Time Slice slider for the needle width to be extended to the width of the time slice.
- Tap the Show Borders slider to display the borders.
- Set wether the <u>Scale</u> will be Linear or Power.
- Check the *Inverted* box. The needle graph on the x-axis is inverted.
- Set the <u>Snapshot Grid Line</u>.



- Enter the Preferred Tick Space. Default is 20.
- Set the End Points.
 - Automatic automatically displays the end points.
 - None end points are not displayed.
 - Custom allows the selection of the Date/Time format of end points.
- Set the Tick Points.
 - Automatic automatically displays the tick points.
 - None tick points are not displayed.
 - Custom allows the selection of the Date/Time format of tick points.
- Enable Align to Time Window to align with the time window of the Time Filter Box.
- Line Graph (time series data)



This visualization type displays the following configuration settings:



- Enter the Line Width. Default is 1.
- Enter the Dot Radius of each data point.
- Enter the Line Opacity which is the level of color transparency/opacity. Default is 255.
- Select the whether the *Line Interpolation* will be **Linear**, **Steeped**, or **Smooth**.



- Check the **Time Gaps** box for the time axis gaps to be interpolated.
- Check the Na Value Gaps box for the Na value gaps to be interpolated.
- Tap the Shade Area Below Line slider to apply the opacity shades between the lines and the zero Y grid line.
- Select wherer the Dash Pattern will be Solid, Dashed, or Dotted.



- Set wether the <u>Scale</u> will be Linear or Power.
- Select the *Inverted* checkbox. The line graph on the X axis is inverted.
- Set the <u>Snapshot Grid Line</u>.

- Enter the Preferred Tick Space. Default is 100.
- Set the End Points.
 - Automatic automatically displays the end points.
 - None end points are not displayed.
 - Custom allows the selection of the Date/Time format of end points.
- Set the Tick Points.
 - Automatic automatically displays the tick points.
 - None tick points are not displayed.
 - Custom allows the selection of the Date/Time format of tick points.
- Enable Align to Time Window to align with the time window of the <u>Time Filter Box</u>.
- 4. Select the aggregation method in the Aggregate field.

The default is **Sum**.

• If you set the aggregation method to Intercept, Slope, Weighted Mean, Weighted Harmonic Mean, Percent of Total Reference, Weighted Sum, Percent of Parent Reference, Percent of Total Change, or Cumulative Sum by Max, the Weight Column drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the weight column for the aggregate.



• If you set the aggregation method to **Percentile**, the *Percentile* field is displayed. Specify the value that can be used to calculate the value of the selected percentile.



- 5. The <u>Format</u> field lets you specify the format that numbers will be displayed in. Panopticon uses the same formatting rules as Excel.
- 6. Select the Divide By value to divide a number:
 - •
 - 1000 (by a thousand)
 - 10000
 - 1000000 (by a million)
 - 1000000000 (by a billion)
- 7. Enter the Title of the column.
- 8. Select the Color variable that will be used for the column:




- None
- Shared Single
- Custom Single
- Column added to the *Color* variable (e.g., **Exchange**)
- 9. You can also opt to group columns in the table visualization.
- 10. Click the **Save** icon on the toolbar.

 When saved, the save icon on the toolbar.


You can add text records in a similar way.

Steps:

Click on a text column under the *Records* variable list.
 This displays the configuration pane.



- 2. You can opt to change the column to the be used as the Records variable from the Column drop-down list.
- 3. By default, text colums are displayed as Text. Select the text aggregation method from the *Aggregate* field: **Count Distinct**, **Text Unique**, or **Text Concat Distinct**.



The default is **Text Unique**.

For Count Distinct, select the Format.



- 4. Enter the *Title* of the column.
- 5. Select the *Color* variable that will be used for the column:



- None
- Shared Single
- Custom Single


Apply Color To

Column added to the Color variable (e.g., Exchange)


Background

6. Specify to what the color variable selected will be applied to:





Text






Shape

Displaying the shape is a useful visual cue in a table. Also, with support for using the shape palettes as icons in the visual table, users will be able to build a legend that will display each unique combination of shape and color, along with the values from the columns used for shape and color.

When selecting **Shape** as the Apply Color To value, ensure to select the Shape value in the drop-down list.




7. Select the Value Alignment.



By default, **By Data Type** is selected. This means, for text values, it is aligned to the left. For numeric or Data/Time data type, the value is aligned to the right.

- 8. Tap the **Show Value Label** slider to display the column values.
- 9. Click the *lcons* drop-down and check the boxes of the <u>columns with icons</u> that will be assigned for this particular column.




- 10. Tap the Word Wrap slider to wrap the text of the column values.
- 11. You can also opt to group columns in the Table visualization.

Grouping Colums in the Table Visualization

Visual members of a Table visualization can be grouped into sections.

Steps:

- 1. Open or create a Table visualization and add columns to the *Records* variable.
- 2. Click the **Records** variable drop area to display the available visual.



NOTE

The inclusion of columns in a group will be based on their sequence in the *Visual Members* list.

For example, the following groups will be created:

First group: Close(local) and Mcap(USD)


Second group: 1 Day Change % (USD), 1 Week Change % (USD), and 2 Week Change %

Third group: 1 Month Change % (USD), 2 Month Change % (USD), and 3 Month Change % (USD)


Forex and Symbol will not be included in any group.

3. For the groupings, click the following columns, check the **Last in Group** box, enter the *Column Group Title*, and click :


• First group: Mcap(USD)




Second group: 2 Week Change %



• Third group: 3 Month Change % (USD)



The groupings are applied to the Table visualization.



AGGREGATION METHODS

Panopticon supports a wide range of aggregation methods. These methods are mathematical computations applied to a set of values. Values may include a group of numbers or numeric field values and variables. The following aggregation methods are available for most variables:

Aggregation Method	Description
Abs	The sum of absolutes of the selection.
Abs Sum	The absolute of the sum of the selection.
Combinations	Returns how many distinct combinations of breakdown column values there are below each node in the hierarchy
Count	The count of the number of rows in the selection.
Count Distinct	Creates numeric aggregated variables based on the distinct count of Text columns.
Count Non Zero	The count of non-zero values.
Cumulative Sum	The cumulative sum based on the currently applied sort order for each leaf node.
Cumulative Sum By Max	The cumulative sum of the sum of the value across siblings ordered by the max of the weight column.
Do Not Aggregate	Returns the value of a single row, otherwise null.
External	Allows aggregates to be supplied from source data. The external aggregate configuration can be supplied explicitly, defined by the user, or implicitly from the data plug-in.
Harmonic Mean	The harmonic mean of the selection.
Intercept	The intercept of the least-squares line.
Level	The level in the hierarchy for the node or numbered from the leaf.

<u>Max</u>	The maximum value from the selection.			
Mean	The mean of the selection.			
Min	The minimum value from the selection.			
Neg	The sum of the negative values in the selection.			
<u>Percentile</u>	The selected percentile.			
Percent of Parent	For each member item (child node) of a breakdown group (parent node), the percentage share of its value in relation to the parent group value, where the parent group value is calculated as the sum of all group member (child node) values: [single child node value] / [sum of all child node values in the group] The aggregate value is calculated as a ratio between 0 and 1 and will be presented as a percentage value by applying a percent format string in the aggregation settings.			
Count Distinct Percent of Parent	Count Distinct expressed as a percentage share of the Count Distinct at the parent node level.			
Percent of Total	For each group and for each group member at all levels of the breakdown hierarchy, the percentage share of its value in relation to the total data set value, where the total is calculated as the sum across all rows in the dataset. This aggregate is similar to Percent of Parent, with the difference that the denominator or reference is ALWAYS based on the complete dataset:			
	[single node value] / [sum of all rows in the dataset] The aggregate value is calculated as a ratio between 0 and 1 and will be presented as a percentage value by applying a percent format string in the aggregation settings.			
Count Distinct Percent of Total	Count Distinct expressed as a percentage share of the Count Distinct in the total data table.			
Percent of Total Change	This aggregate should be understood as "Change in (Percent of Total)", not as "Percent of (Total Change)". It is the result of calculating Percent of Total on two different columns, and then calculating the difference between them. The result is presented as the difference in <i>percentage units</i> , n.b.			
	This aggregate is typically used for comparing Percent of Total based on current values, to Percent of Total based on previous values. Therefore, the column specified as "Previous Values Column" in the settings, should be the column containing previous values.			
	The aggregate value is calculated as a ratio between 0 and 1 and will be presented as a percentage value by applying a percent format string in the aggregation settings. Optionally, you can emphasize that the value is a percentage units by customizing the format unit, for example: 0.00%'-units'.			
Percent of Parent Reference	This aggregate works like Percent of Parent, with the difference that a value from one column is compared to a parent level sum of values from another column, which is set as the "Reference column":			
	[single child node value from a column] / [sum of all child node values from the reference column in the group]			
	While Percent of Parent will always summarize to 100% at the group (parent) level, this is not the case with Percent of Parent Reference, which can summarize to any number, depending on the differences between the Values and the Reference Values.			
	The aggregate value is calculated as a ratio between 0 and 1 and will be presented as a percentage value by applying a percent format string in the aggregation settings.			

Percent of Total Reference	This aggregate works like Percent of Total, with the difference that a value from one column is compared to a total data set level sum of values <i>from another column</i> , which is set as the "Reference column":
	[single node value from a column] / [sum of all rows from the reference column in the dataset]
	While Percent of Total will always summarize to 100% across the whole data set, this is not the case with Percent of Total Reference, which can summarize to any number, depending on the differences between the Values and the Reference Values .
	The aggregate value is calculated as a ratio between 0 and 1 and will be presented as a percentage value by applying a percent format string in the aggregation settings.
Pos	The sum of the positive values in the selection
<u>Product</u>	The product of the selection.
Ratio of Sums	The comparison between the sum of a selected measure divided by the sum of the selected reference measure.
Sibling Rank	The numeric rank of siblings within a hierarchy branch.
Slope	The slope of the least-squares line.
Stdev	The standard deviation of the selection.
Stdevp	The population standard deviation of the selection.
Sum	The sum of the selection.
<u>Unique</u>	Used with numeric values and will display a number in case all the values in a group are the same, otherwise it will show empty/null. This aggregation can be used as an indicator of a logical test: "if the numeric values in this group and in any subgroups are identical, then show the numeric value, or else show nothing".
Text Concat Distinct	Aggregates text fields to display all possible text values in a comma delimited list.
Text Unique	Aggregates text fields to display distinct values.
Weighted Harmonic Mean	The weighted harmonic mean of the selection, based on a specified weighting column.
Weighted Mean	The weighted mean of the selection, based on a specified weighting column.
Weighted Sum	The sum of the product of the selected field and the weight field.

Abs

The sum of absolute values of the selection.

This method returns the sum of the absolute values of each item in a set of numbers.

The absolute value of a number refers to the number without its sign.

Adding each item of a set of numbers will produce its total or sum.

Sample 1

Given a list of arbitrary numbers:

Arbitrary	
	3
	2
	1
	0
	-1
	-2
	-3
	0
	0
	0

A list of positive and negative numbers

Steps:

1. Compute for the absolute value of each item.

Arbitrary	
	3
	2
	1
	0
	1
	2
	3
	0
	0
	0

The list of absolute values.

2. Compute the sum of the absolute numbers.

$$3 + 2 + 1 + 0 + 1 + 2 + 3 + 0 + 0 + 0 = 12$$

Sample 2

Assuming that the same list of numbers has multiple groupings or breakdowns as shown below.

Grouping	Arbitrary
1	3
1	2
1	1
1	0
2	-1
2	-2
2	-3
3	0
3	0
3	0

The list of values with groupings.

Steps:

1. Compute for the absolute values of each item based on the Grouping defined.

Grouping		Arbitrary	
	1		3
	1		2
	1		1
	1		0
	2		1
	2		2
	2		3
	3		0
	3		0
	3		0

The list of absolute values with groupings.

2. Compute the sum of the absolute numbers based on the grouping.

Grouping	Arbitrary
1	6
2	6
3	0

The final result.

Computation Details:

Group 1: 3 + 2 + 1 + 0 = 6

Group 2: 1 + 2 + 3 = 6

Group 3: 0 + 0 + 0 = 0

Sample 3

Given the following sample fields:

Number	Arbitrary	Negative Values	Positive Values	One	Binary	Currency	Decimal
1	3	-1	1	1	0	\$1.00	1.01
2	2	-2	2		1	\$10.00	2.02
3	1	-3	3		0	\$100.00	3.03
4	0	-4	4		1	\$1,000.00	4.04
5	-1	-5	5		0	\$10,000.00	5.05
6	-2	-6	6		1	-\$1.00	6.06
7	-3	-7	7		0	-\$10.00	7.07
8	0	-8	8			-\$100.00	8.08
9	0	-9	9			-\$1,000.00	9.09
10	0	-10	0			\$0.00	0.00

Sample fields.

Abs Results:

1	Number	Arbitrary	Negative Values	Positive Values	One	Binary	Currency	Decimal
	55	12	55	45	1	3	12,222.00	45.45

The results per field.


Abs Sum

The absolute of the sum of the selection.

This method returns the absolute value of the sum of each item in a set of numbers.

Sample 1

Given a list of arbitrary numbers:



A list of positive and negative numbers

Steps:

1. Compute for the sum of the values.



The sum of all values.

2. Compute the absolute of zero, which equals zero.

Sample 2

Assuming that the same list of numbers has multiple groupings or breakdowns as shown below:

Grouping	Arbitrary
1	3
1	2
1	1
1	0
2	-1
2	-2

2	-3
3	0
3	0
3	0

The list of values with grouping.

Steps:

1. Compute the sum of the numbers based on the grouping.

Grouping		Arbitrary
	1	6
	2	-6
	3	0

The sum of values per grouping.

Computation Details:

Group 1: 3 + 2 + 1 + 0 = 6

Group 2: -1 + -2 + -3 = -6

Group 3: 0 + 0 + 0 = 0

2. Compute the absolute value of the summed-up numbers above.

Grouping		Arbitrary
	1	6
	2	6
	3	0

Final result.

Sample 3

Given the following sample fields:

Number	Arbitrary	Negative Values	Positive Values	One	Binary	Currency	Decimal
1	3	-1	1	1	0	\$1.00	1.01
2	2	-2	2		1	\$10.00	2.02
3	1	-3	3		0	\$100.00	3.03
4	0	-4	4		1	\$1,000.00	4.04
5	-1	-5	5		0	\$10,000.00	5.05
6	-2	-6	6		1	-\$1.00	6.06

7	-3	-7	7	0	-\$10.00	7.07
8	0	-8	8		-\$100.00	8.08
9	0	-9	9		-\$1,000.00	9.09
10	0	-10	0		\$0.00	0.00

Sample fields.

AbsSum Results:

Number	Arbitrary	Negative Values	Positive Values	One	Binary	Currency	Decimal
55	0	55	45	1	3	10,000.00	45.45

The results per field.

Combinations

Returns how many distinct combinations of breakdown column values there are below each node in the hierarchy. Given this data table:

Region	Country	1 Day Change % (USD)	Mcap Rank	1 Month Change % (USD)
Europe	AT	-7.4%	32	71.31%
Europe	AT	-6.56%	68	51.07%
Europe	AT	-2.78%	66	-17.28%
Asia Pacific	AU	-0.72%	57	22.35%
Asia Pacific	AU	3.28%	72	13.99%
Europe	BE	-4.94%	45	49.33%
Europe	BE	-9.23%	48	78.89%
Europe	BE	4.19%	28	22.68%
Europe	BE	-2.63%	51	22.60%
North America	CA	-5.19%	25	13.82
North America	CA	12.19%	41	19.11%
North America	CA	1.20%	16	17.14%

Sample 1

Below is the defined breakdown in a Table visualization:



Adding 1 Day Change % (USD) column to the *Records* variable will produce the following table with the aggregate set to **Sum** (default):

		1 Day Change % (USD)
Asia Pacific	AU	0.03
Europe	AT	-0.17
	BE	-0.13
North America	CA	0.08

Changing the aggregate of 1 Day Change % (USD) to **Count** will display how many instances of 1 Day Change % (USD) (rows from the data table) there are in each country:

		1 Day Change % (USD)
Asia Pacific	AU	2
Europe	AT	3
	BE	4
North America	CA	3

Adding Mcap Rank to the Records variable will result to the following table with the aggregate set to Sum (default):

		1 Day Change % (USD)	Mcap Rank
Asia Pacific	AU	2	129
Europe	AT	3	166
	BE	4	172
North America	CA	3	82

Changing the aggregate of Mcap Rank to **Combinations** will display how many countries (rows in fully expanded visual table) there are.

		1 Day Change % (USD)	Mcap Rank
Asia Pacific	AU	2	1
Europe	AT	3	1
	BE	4	1
North America	CA	3	1

Changing the visible depth in the breakdown to **Region** should show:

	1 Day Change % (USD)	Mcap Rank
Asia Pacific	2	1
Europe	7	2
North America	3	1

Asia Pacific has 1 (AU), Europe has 2 (AT and BE), and North America has 1 (CA).

Count

The count of the number of rows in the selection. Returns the number of items in a set of numbers.

Sample 1

Given a list of arbitrary numbers:

Arbitrary	
	3
	2
	1
	0
	-1
	-2
	-3
	0
	0
	0

A list of positive and negative numbers

The field has 10 rows and therefore the count is equal to 10.

Sample 2

Assuming that the same list of numbers has multiple groupings or breakdowns as below:

Grouping		Arbitrary
	1	3
	1	2
	1	1
	1	0
	2	-1
	2	-2
	2	-3
	3	0
	3	0

3 0

A list of values based on a grouping

Computing for the Count based on the Grouping field yields the following results:

Grouping		Arbitrary
	1	4
	2	3
	3	3

The final result

Sample 3

Given the following sample fields:

Number	Arbitrary	Negative Values	Positive Values	One	Binary	Currency	Decimal
1	3	-1	1	1	0	\$1.00	1.01
2	2	-2	2		1	\$10.00	2.02
3	1	-3	3		0	\$100.00	3.03
4	0	-4	4		1	\$1,000.00	4.04
5	-1	-5	5		0	\$10,000.00	5.05
6	-2	-6	6		1	-\$1.00	6.06
7	-3	-7	7		0	-\$10.00	7.07
8	0	-8	8			-\$100.00	8.08
9	0	-9	9			-\$1,000.00	9.09
10	0	-10	0			\$0.00	0.00

Final results.

Count Distinct

Creates numeric aggregated variables based on the distinct count of text columns.

Given this data table:

Country	Industry	Product	Company	1 Day Change % (USD)	Mcap(USD)
AT	Financials	Charleston	Raiffeisen International Bank- Holding AG	-0.07	3439883100
AT	Financials	Soflyy	Raiffeisen International Bank- Holding AG	-0.07	1371987780

AT	Basic Materials	Digital 2TB	Raiffeisen International Bank- Holding AG	-0.03	1412883878
AT	Industrials	Charleston	Wienerberger AG	-0.04	660942066
AU	Basic Materials	Charleston	BHP Billiton Ltd.	-0.06	74380605994
AU	Basic Materials	Soflyy	Lihir Gold Ltd.	0.02	5377974426
AU	Basic Materials	Soflyy	BHP Billiton Ltd.	-0.02	2104618718
BE	Financials	Digital 2TB	KBC Group N.V.	-0.05	2369136539
BE	Financials	Charleston	Dexia S.A.	-0.09	2272408744
BE	Basic Materials	Soflyy	KBC Group N.V.	0.04	4151907147
BE	Basic Materials	Digital 2TB	Umicore S.A.	-0.03	2078266946
CA	Consumer Goods	Canbio HD	Magna International Inc. CI A	-0.05	2981991456
CA	Financials	Wraith Tri	Canadian Imperial Bank of Commerce	-0.03	13960011146

Country, Industry, Product, and Company are text columns while 1 Day Change % (USD) and Mcap(USD) are numeric columns.


Sample 1

Below is the defined breakdown in a Table visualization:

This Table visualization is showing the grouping of the columns based on the breakdown hierarchy with Product, Company, 1 Day Change % (USD), and Mcap(USD) as Visual Members and with the corresponding aggregates:

Column	Aggregate
Product	TextUnique
Company	TextUnique
1 Day Change % (USD)	Sum
Mcap(USD)	Sum


By default, the aggregates of Product and Company are both set to **TextUnique**.



The Table visualization now displays the distinct text values of Product and Company for the breakdown columns, Country and Industry.

		Product	Company	1 Day Chang % (USD)	ge Mcap(USD)
AT	Basic Materials	Digital 2B	Raiffeisen International Bank-Holding AG	-0.03	1412883878
	Financials		Raiffeisen International Bank-Holding AG	-0.14	4811879880
	Industrials	Charleston	Wienerberger AG	-0.04	660942066
AU	Basic Materials			-0.06	81863199138
BE	Basic Materials			0.02	6230174093
	Financials			-0.14	4641545283
CA	Consumer Goods	Canbio HD	Magna International Inc. Cl A	-0.05	2981991456
	Financials	Wraith Tri	Canadian Imperial Bank of Commerce	-0.03	13960011146

To display the Product column as a distinct count, click **Show as Distinct Count**. The dialog changes to show numeric properties with *Aggregate* set to **CountDistinct**:




The values of the Product column display in the Table as:

		Product	Company	1 Day CI % (USD)	
AT	Basic Materials	1.00	Raiffeisen International Bank-Holding AG	-0.03	1412883878
	Financials	2.00	Raiffeisen International Bank-Holding AG	-0.14	4811879880
	Industrials	1.00	Wienerberger AG	-0.04	660942066
AU	Basic Materials	2.00		-0.06	81863199138
BE	Basic Materials	2.00		0.02	6230174093
	Financials	2.00		-0.14	4641545283
CA	Consumer Goods	1.00	Magna International Inc.	-0.05	2981991456
	Financials	1.00	Canadian Imperial Bank of Commerce	-0.03	13960011146

For example, for the Country AT and Industry Financials, it shows that there are **2** Product distinct counts for the breakdown columns which are: **Charleston and Soflyy**

While for the Country AU and Industry Basic Materials, there are **2** Product distinct counts for the breakdown columns which are also: **Charleston and Soflyy**

You can also opt display the Company column as a distinct count by clicking **Show as Distinct Count**. The dialog changes to show numeric properties with *Aggregate* set to **CountDistinct**:




The values of the Company column display in the Table as:

		Product	Company	1 Day Change % (USD)	e Mcap(USD)
AT	Basic Materials	1.00	1.00	-0.03	1412883878
	Financials	2.00	1.00	-0.14	4811879880
	Industrials	1.00	1.00	-0.04	660942066
AU	Basic Materials	2.00	2.00	-0.06	81863199138
BE	Basic Materials	2.00	2.00	0.02	6230174093
	Financials	2.00	2.00	-0.14	4641545283
CA	Consumer Goods	1.00	1.00	-0.05	2981991456
	Financials	1.00	1.00	-0.03	13960011146

Note that for the Country AT and Industry Financials, there are **2** Product distinct counts but only **1** Company distinct count which is **Raiffeisen International Bank-Holding AG.**

This aggregation method is initially implemented for the following:

□ Ticker Tile, Bar, Dot, and Bullet visualizations




For example:




☐ Height, Size, and Details variables

For the Details variable, dragging a text column to the *Details* shelf drop area creates a text details member.



To show as distinct count, select **Count Distinct** as the aggregate.



Count Non Zero

The count of the number of non-zero rows in the selection. Returns the number of items in a set of numbers.

Sample 1

Arbitrary	
	3
	2
	1
	0
	-1
	-2
	-3
	0
	0
	0

A list of positive and negative numbers

The field has 10 rows but the number of non-zero values is 6.

Sample 2

Given the following sample fields:

Number	Arbitrary	Negative Values	Positive Values	One	Binary	Currency	Decimal
1	3	-1	1	1	0	\$1.00	1.01
2	2	-2	2		1	\$10.00	2.02

3	1	-3	3	0	\$100.00	3.03
4	0	-4	4	1	\$1,000.00	4.04
5	-1	-5	5	0	\$10,000.00	5.05
6	-2	-6	6	1	-\$1.00	6.06
7	-3	-7	7	0	-\$10.00	7.07
8	0	-8	8		-\$100.00	8.08
9	0	-9	9		-\$1,000.00	9.09
10	0	-10	0		\$0.00	0.00

Sample fields.

Count Results:

Number	Arbitrary	Negative Values	Positive Values	One	Binary	Currency	Decimal
10	6	10	9	1	3	9	9

Final results.

Cumulative Sum

Returns the cumulative sum based on the currently applied sort order for each leaf nodes, any inner nodes return a null value.

Sample

Below is a table showing **Day** and Amount fields, with **Balance** as the new aggregate column (CumulativeSum) based on **Amount** as the **source** column and Day as the **sorting** column.

The **Key** column serves as the breakdown.

Key	Day	Amount	Balance
А	5	\$2.00	\$5.50
В	2	\$3.00	\$7.00
С	7	-\$1.00	\$9.50
D	3	-\$5.00	\$2.00
E	1	\$4.00	\$4.00
F	4	\$1.50	\$3.50
G	6	\$5.00	\$10.50
Н	10	\$1.00	\$12.50
1	8	-\$2.00	\$7.50
J	9	\$4.00	\$11.50

In the example, you get one row in the visualization per row in the data source since every source row has a unique key. If not, multiple rows roll into each visualization row, and then the CumulativeSum will first sort them on the sums of the **Day** column, then accumulate the sums of the **Amount** column.

To get the correct CumulativeSum values in the **Balance** column, click the **Up/Down** button of the **Day** column to sort the fields in ascending order.

Result

Based on the ascending sort order of the **Day** column and the cumulative sum of the **Amount** column, the results will be:

Key	Day	Amount	Balance
Е	1	\$4.00	\$4.00
В	2	\$3.00	\$7.00
D	3	-\$5.00	\$2.00
F	4	\$1.50	\$3.50
Α	5	\$2.00	\$5.50
G	6	\$5.00	\$10.50
С	7	-\$1.00	\$9.50
1	8	-\$2.00	\$7.50
J	9	\$4.00	\$11.50
Н	10	\$1.00	\$12.50

Computation details:

Day 1: \$4.00	Day 6: $$5.50 + $5.00 = 10.50
Day 2: \$4.00.00 + \$3.00 = \$7.00	Day 7: \$10.50 + -\$1.00 = \$9.50
Day 3: \$7.00 + -\$5.00 = \$2.00	Day 8: \$9.50 + -\$2.00 = \$7.50
Day 4: \$2.00 + \$1.50 = \$3.50	Day 9: \$7.50 + \$4.00 = \$11.50
Day 5: \$3.50 + \$2.00 = \$5.50	Day 10: \$11.50 + \$1.00 = \$12.50

Cumulative Sum By Max

The cumulative sum of the sum of the value across siblings ordered by the max of the weight column.

Sample

Given this table showing Key, Date, Value, Day, and RowPerDay fields.

Key	Date	Value	Day	RowsPerDay
А	2018-01-01	1	1	3
В	2018-01-01	2	1	3
С	2018-01-01	4	1	3
D	2018-01-02	4	2	1
Е	2018-01-03	5	3	4


F	2018-01-03	6	3	4
G	2018-01-03	7	3	4
Н	2018-01-03	8	3	4

Provide a weight column that when summed gives the order of the nodes. For example, create a new calculated column based on this expression:

AverageDay = [Day]/[RowsPerDay]

Make **Value-CumSumByMax** as the new aggregate column (CumulativeSumByMax) based on **Value** as the source column and AverageDay as the weight column.

The Date - Day column serves as the breakdown.



Result

The nodes are sorted on the max of the weight column, and then the sum of the value column is accumulated across.

Date - Day	AverageDay	Day	RowsPerDay	Value	Value-CumSumByMax
1	0.33	3	9	7.00	7.00
2	2.00	2	1	4.00	37.00
3	0.75	12	16	26.00	33.00

Computation details:

Day 1: 7.00

Day 2: 7.00 + 4.00 + 26.00 = 37.00

Day 3: 7.00 + 26.00 = 33.00

Do Not Aggregate

Returns the value of a single row, otherwise null.

This method can be used to display a source table.

Below is a source table showing two fields Number and Arbitrary, with Aggregation set to DoNotAggregate and grouped by the Row field. This means Row is also the Breakdown field.

Row	Number	Arbitrary
Α	1	3
В	2	2
С	3	1
D	4	0
Е	5	-1
F	6	-2
G	7	-3
Н	8	0
1	9	0
J	10	0

Sample table

If there are multiple items or rows without any grouping, then the value of the method is just n/a.

Harmonic Mean

The harmonic mean gives equal weight to each data point, meaning that extreme outlier values will not impact the Harmonic Mean as much as it would an Arithmetic Mean.

Typically, it is appropriate for situations when the average of rates is desired. The Harmonic mean H of the positive real numbers x1, x2, ..., xn > 0 is defined to be:

$$H = \frac{n}{\frac{1}{x_1} + \frac{1}{x_2} + \dots + \frac{1}{x_n}} = \frac{n}{\sum_{i=1}^n \frac{1}{x_i}} = \frac{n \cdot \prod_{j=1}^n x_j}{\sum_{i=1}^n \frac{\prod_{j=1}^n x_j}{x_i}}.$$

Sample 1:

As a simple example, the Harmonic mean of 1, 2, and 4 is

$$\frac{3}{\frac{1}{1}+\frac{1}{2}+\frac{1}{4}} = \frac{1}{\frac{1}{3}(\frac{1}{1}+\frac{1}{2}+\frac{1}{4})} = \frac{12}{7} \, . \\ \text{or 1.7143}$$

Sample 2:

Another example based on the number of hours worked per week:

The table shows the average working hours per week per employee (a rate). Each employee was only required to work 2000 hours but their working hours differs per week:

Employee	Total Hours Worked	Average Working Hours Per Week	Work Weeks
Joy	2000	50	40
Thomas	2000	45	44.4444
Erick	2000	35	57.142857
John	2000	40	50

Employee working hours per week

The total number of working hours by all four employees is 8000 hours. The total number of work weeks is 191.59 weeks. The calculation to compute for the Harmonic mean is:

$$4/(1/50 + 1/45 + 1/35 + 1/40) = 41.7564$$
 hours

A simple check of dividing 8000 hours by 41.76 will equal 191.59 which is the total number of weeks the employees worked.

Intercept

The intercept of the least-squares line.

The formula:

Intercept =
$$\left[\sum (x^2)\sum (y) - \sum (x)\sum (xy)\right]/\left[n\sum (x^2) - \sum (x)^2\right]$$

Sample 1:

Given the set of X and Y values where X and Y can represent any correlated values below:

X	Υ
1	2
2	4
3	6

4	8
5	10
6	12
7	14
8	16
9	18
10	20

Sample table of correlated values

Steps:

1. Solve the parts of the formula.

```
Intercept = [\sum (x^2)\sum (y) - \sum (x)\sum (xy)]/[n\sum (x^2) - \sum (x)^2]
n =count of items, equal to 10
```

in -count of items, equal to 10

 $\sum (x^2)$ = get the square of all x items and sum up the values. To square a number also means to multiply the number by itself.

$$1x1 + 2x2 + 3x3 + 4x4 + 5x5 + 6x6 + 7x7 + 8x8 + 9x9 + 10x10 = 385$$

 $\sum (y) = \text{sum of y items} = 110$

 $\sum (x) = \text{sum of } x \text{ items} = 55$

 $\sum (xy)$ = multiply all x and y items and get the sum = 770

$$1x2 + 2x4 + 3x6 + 4x8 + 5x10 + 6x12 + 7x14 + 8x16 + 9x18 + 10x20 = 770$$

 $\sum (x)^2$ = get the sum of all items in x and get the square = 55 * 55 or 3025

2. Substitute the known values in the formula and compute for the intercept:

$$Intercept = [385(110) - 55(770)/[10(385) - 3025]$$

Intercept = [42350 - 42350]/[3850 - 3025]

Intercept = [0]/825]

Intercept = 0

Level

Returns the level in the hierarchy for the node or numbered from the leaf.

Given this data table:

Industry	Supersector	Symbol	3 Month Change %
Financials	Banks	ERST.VI	-0.21
Basic Materials	Basic Resources	VOES.VI	-0.35
Industrials	Construction & Materials	WBSV.VI	-0.50
Health Care	Health Care	ICEL.VI	0.06
Industrials	Industrial Goods & Services	ANDR.VI	0.28

Financials	Insurance	VIGR.VI	-0.10
Oil & Gas	Oil & Gas	OMVV.VI	0.35
Telecommunications	Telecommunications	TELA.VI	0.11
Utilities	Utilities	VERB.VI	-0.12
Financials	Real Estate	ATRV.VI	-0.12
Financials	Banks	BEN.AX	-0.26
Financials	Banks	SUN.AX	-0.28
Financials	Banks	NAB.AX	-0.04
Financials	Banks	ANZ.AX	-0.11
Financials	Banks	CBA.AX	0.03
Basic Materials	Basic Resources	BSL.AX	0.15

Sample 1

Below is the defined breakdown in a Table visualization:




The Levels will be:

Column	Level
Symbol	0
Supersector	1
Industry	2
Root	3

This Table visualization is showing the grouping of the columns based on the breakdown hierarchy with 3 Month Change %'s aggregate set to Sum.




Changing the aggregate to **Level** and the format to **#,##0.00** will produce this table since the *Visible Depth* is set until Symbol:






Sample 2


Clicking on Supersector will make the Symbol breakdown column invisible:



Sample 3

Collapsing columns in the table can also change the Level values:






Sample 4

Clicking to the Root in the breakdown hierarchy:




The Level aggregate can also be used when creating calculated columns.


1. On the Data Table Editor layout page, click Calculated Columns and select Calculated.



The Numeric Calculated Column pane displays.



2. Build the expression with the *Level* aggregate.



For example: 12.0 + [3 Month Change %:level]

When all of the levels are visible in the breakdown (Sample 1), the results will be:

Industry	Supersector	Symbol	3 Month Change %	LevelCalc
Basic Materials	Basic Resources	BSL.AX	0	12.0
		VOES.VI	0	12.0
Financials	Banks	ANZ.AX	0	12.0
		BEN.AX	0	12.0
		CBA.AX	0	12.0
		ERST.VI	0	12.0
		NAB.AX	0	12.0
		SUN.AX	0	12.0
	Insurance	VIGR.VI	0	12.0
	Real Estate	ATRV.VI	0	12.0
Health Care	Health Care	ICEL.VI	0	12.0

Industrials	Construction & Materials	WBSV.VI	0	12.0
	Industrial Goods & Services	ANDR.VI	0	12.0
Oil & Gas	Oil & Gas	OMVV.VI	0	12.0
Telecommunications	Telecommunications	TELA.VI	0	12.0
Utilities	Utilities	VERB.VI	0	12.0

Collapsing columns in the table (similar with Sample 3 above) will result to:



Max

The maximum value from the selection.

Returns the maximum value in a given set of numbers.

Sample 1

Given the following sample fields:

Number	Arbitrary	Negative Values	Positive Values	One	Binary	Currency	Decimal
1	3	-1	1	1	0	\$1.00	1.01
2	2	-2	2		1	\$10.00	2.02
3	1	-3	3		0	\$100.00	3.03
4	0	-4	4		1	\$1,000.00	4.04
5	-1	-5	5		0	\$10,000.00	5.05
6	-2	-6	6		1	-\$1.00	6.06
7	-3	-7	7		0	-\$10.00	7.07
8	0	-8	8			-\$100.00	8.08

國 /

9	0	-9	9		-\$1,000.00	9.09
10	0	-10	0		\$0.00	0.00

Sample fields.

The maximum value for each field in the table:

Number	Arbitrary	Negative Values	Positive Values	One	Binary	Currency	Decimal
10	3	-1	9	1	1	10,000.00	9.09

The results per field.

Mean

The mean of the selection.

Returns the average of a given set of numbers.

The mean is the sum of all the values in a set of numbers, divided by the number of values.

Sample 1:

Given a list of arbitrary numbers:

Arbitrary	
	3
	2
	1
	0
	-1
	-2
	-3
	0
	0
	0

A list of positive and negative numbers

Steps:

1. Compute the sum of the values.

$$3 + 2 + 1 + 0 + -1 + -2 + -3 + 0 + 0 = 0$$

2. Divide it by the number of values.

0/10 = 0

Sample 2

Assuming that the same list of numbers has multiple groupings or breakdowns as shown below:

Grouping	Arbitrary
1	3
1	2
1	1
1	0
2	-1
2	-2
2	-3
3	0
3	0
3	0

Groupings of numbers

Computing for the mean of the Arbitrary field based on the Grouping field will result in the table below:

Grouping	Arbitrary
1	2
2	-2
3	0

The resulting table

Computation details:

Group 1: 3 + 2 + 1 + 0 = 6/4 = 1.5

Group 2: -1 + -2 + -3 = -6/3 = -2

Group 3: 0 + 0 + 0 = 0/3 = 0

Sample 3

Given the following sample fields:

Number	Arbitrary	Negative Values	Positive Values	One	Binary	Currency	Decimal
1	3	-1	1	1	0	\$1.00	1.01
2	2	-2	2		1	\$10.00	2.02
3	1	-3	3		0	\$100.00	3.03
4	0	-4	4		1	\$1,000.00	4.04
5	-1	-5	5		0	\$10,000.00	5.05

6	-2	-6	6	1	-\$1.00	6.06
7	-3	-7	7	0	-\$10.00	7.07
8	0	-8	8		-\$100.00	8.08
9	0	-9	9		-\$1,000.00	9.09
10	0	-10	0		\$0.00	0.00

Sample fields.

Mean Results:

Number	Arbitrary	Negative Values	Positive Values	One	Binary	Currency	Decimal
6	0	-6	5	1	0	1000.00	4.55

The results per field.

Min

The minimum value from the selection.

Returns the minimum value in each set of numbers.

Sample 1

Given the following sample fields:

Number	Arbitrary	Negative Values	Positive Values	One	Binary	Currency	Decimal
1	3	-1	1	1	0	\$1.00	1.01
2	2	-2	2		1	\$10.00	2.02
3	1	-3	3		0	\$100.00	3.03
4	0	-4	4		1	\$1,000.00	4.04
5	-1	-5	5		0	\$10,000.00	5.05
6	-2	-6	6		1	-\$1.00	6.06
7	-3	-7	7		0	-\$10.00	7.07
8	0	-8	8			-\$100.00	8.08
9	0	-9	9			-\$1,000.00	9.09
10	0	-10	0			\$0.00	0.00

Sample fields.

The minimum value for each field in the table:

Number	Arbitrary	Negative Values	Positive Values	One	Binary	Currency	Decimal
1	-3	-10	0	1	0	\$0.00	0.00

The results per field.

Neg

The sum of the negative values in the selection. If a value is positive or zero, the value n/a is returned.

Sample 1

Given a list of arbitrary numbers:

Arbitrary	
	3
	2
	1
	0
	-1
	-2
	-3
	0
	0
	0

A list of positive and negative numbers

Steps:

1. Select which values are negative.

Arbitrary	
	n/a
	n/a
	n/a
	n/a
	-1
	-2
	-3
	n/a
	n/a

n/a

Negative numbers in the list

2. Add the negative values -1 + -2 + -3 = -6.

Sample 2

Given the following sample fields:

Number	Arbitrary	Negative Values	Positive Values	One	Binary	Currency	Decimal
1	3	-1	1	1	0	\$1.00	1.01
2	2	-2	2		1	\$10.00	2.02
3	1	-3	3		0	\$100.00	3.03
4	0	-4	4		1	\$1,000.00	4.04
5	-1	-5	5		0	\$10,000.00	5.05
6	-2	-6	6		1	-\$1.00	6.06
7	-3	-7	7		0	-\$10.00	7.07
8	0	-8	8			-\$100.00	8.08
9	0	-9	9			-\$1,000.00	9.09
10	0	-10	0			\$0.00	0.00

Sample fields.

The Neg value for each field in the table:

Number	Arbitrary	Negative Values	Positive Values	One	Binary	Currency	Decimal
n/a	-6	-55	n/a	n/a	n/a	\$-1,111.00	n/a

The results per field.

Percentile

The selected percentile.

Percentile (^{U}P) is the value of the P-th percentile of an ascending ordered data set containing N elements with values $v_1 \leq v_2 \leq \ldots \leq v_N$.

There are two steps to compute for Percentile.

Steps:

1. Calculate the rank:

$$n = \frac{P}{100}(N-1) + 1$$

The rank is then split into its integer component \emph{k} and decimal component \emph{d} , such that n=k+d.

2. Use the formula below to calculate v_P as:

$$v_P = \begin{cases} v_1, & \text{for } k = 0 \\ v_N, & \text{for } k = N \\ v_k + d(v_{k+1} - v_k), & \text{for } 0 < k < N \end{cases}$$

Sample 1

Consider the ordered list of values 15, 20, 35, 40, 50. What is the 40th percentile of this list?

Steps:

1. Calculate the rank of the 40th percentile as follows.

$$n = \frac{40}{100}(5-1) + 1 = 2.6$$

Thus, n=2.6, which gives us k=2 and d=0.6.

2. Calculate the value of the 40th percentile.

$$v_k + d(v_{k+1} - v_k) = v_2 + 0.6(v_3 - v_2) = 20 + 0.6(35 - 20) = 29$$

Thus, the value of the 40th percentile of the ordered list 15, 20, 35, 40, 50 is 29.

Sample 2

Consider the ordered list 1,2,3,4. What is the 75th percentile of this list?

Steps:

1. Calculate the rank of the 75th percentile as follows.

$$N = 75/100(4-1) + 1 = 3.25$$

Thus, n=3.25, which gives us k=3 and d=0.25.

2. Calculate the value of the 75th percentile.

$$v_k + d(v_{k+1} - v_k) = v_3 + 0.25(v_4 - v_3) = 3 + 0.25(4 - 3) = 3.25$$

Thus, the value of the 75th percentile of the ordered list 1,2,3,4 is 3.25.

Sample 3

Given the following sample fields:

Number	Arbitrary	Negative Values	Positive Values	One	Binary	Currency	Decimal
1	3	-1	1	1	0	\$1.00	1.01
2	2	-2	2		1	\$10.00	2.02
3	1	-3	3		0	\$100.00	3.03

4	0	-4	4	1	\$1,000.00	4.04
5	-1	-5	5	0	\$10,000.00	5.05
6	-2	-6	6	1	-\$1.00	6.06
7	-3	-7	7	0	-\$10.00	7.07
8	0	-8	8		-\$100.00	8.08
9	0	-9	9		-\$1,000.00	9.09
10	0	-10	0		\$0.00	0.00

Sample fields.

The 50th Percentile value for each field in the table:

5.50	0.00	-5.50	4.50	1.00	0.00	0.50	4.55
5.50	0.00	-5.50	4.50	1.00	0.00	0.50	4.55

The results per field.

Percent of Parent

For each member item (child node) of a breakdown group (parent node), the percentage share of its value in relation to the parent group value, where the parent group value is calculated as the sum of all group member (child node) values:

[single child node value] / [sum of all child node values in the group]

The aggregate value is calculated as a ratio between 0 and 1 and will be presented as a percentage value by applying a percent format string in the aggregation settings.

Sample

Group (Parent)	Member (Child)	Values	Group Sum	Percent of Parent
G1	Α	20	100	0.20
G1	В	30	100	0.30
G1	С	50	100	0.50
G2	D	1.5	5	0.30
G2	E	1.5	5	0.30
G2	F	2	5	0.40
G3	G	7	20	0.35
G3	Н	9	20	0.45
G3	1	4	20	0.20

Count Distinct Percent of Parent and Count Distinct Percent of Total

Count Distinct Percent of Parent is the Count Distinct expressed as a percentage share of the Count Distinct as the parent node level. While **Count Distinct Percent of Total** is the Count Distinct expressed as a percentage share of the Count Distinct in the total data table.

Sample dataset:

Auto Key	Row Count	CustomerID	Product Downloaded	Product Family	Product Vendor	Timestamp
1	1	c1	Prod X	Fam A	Boogle	03/04/2022
2	1	c1	Prod Y	Fam A	Boogle	02/04/2022
3	1	c1	Prod Z	Fam B	Boogle	29/04/2022
4	1	c2	Prod X	Fam A	Boogle	04/04/2022
5	1	c2	Prod Y	Fam A	Boogle	04/04/2022
6	1	c2	Prod Z	Fam B	Boogle	18/04/2022
7	1	с3	Prod X	Fam A	Boogle	10/04/2022
8	1	c3	Prod Y	Fam A	Boogle	11/04/2022
9	1	c3	Prod Z	Fam B	Boogle	01/04/2022
10	1	c4	Prod Z	Fam B	Boogle	01/04/2022
11	1	c91	Prod X	Fam A	Boogle	15/03/2022
12	1	c91	Prod X	Fam A	Boogle	15/04/2022
13	1	c91	Prod X	Fam A	Boogle	15/05/2022s
14	1	c91	Prod X	Fam A	Boogle	15/06/2022
15	1	c91	Prod X	Fam A	Boogle	16/06/2022
16	1	c92	Prod Y	Fam A	Boogle	01/05/2022
17	1	c92	Prod Z	Fam B	Boogle	01/05/2022
18	1	c92	Prod Y	Fam A	Boogle	06/05/2022
19	1	c92	Prod Z	Fam B	Boogle	03/06/2022
20	1	c92	Prod Z	Fam B	Boogle	06/06/2022

This dataset contains information about software product downloads.

Count	Details
1	Product vendor
2	Product families
3	Products
6	Customers
3	Month and Year time periods
20	Unique download occasions

Below is the defined breakdown in a Table visualization:

Month and Year | Product Family | Product Downloaded | CustomerID |

The added columns have the following aggregations:

Column	Aggregate	
Row Count	Sum	
CustomerID	Count Distinct	
CustomerID	Count Distinct Percent of Parent	
Customer ID	Count Distinct Percent of Total	

By counting the rows in the dataset, we can count how many different download occasions we have.

By doing Count Distinct on CustomerID, we find out how many unique customers there are, regardless of how many times each customer did a download.



For Count Distinct Percent of Parent, we can determine how large was the portion that was downloaded by all Customers during May 2022. Based on the visualization, it's 33% (one-third, 2 out of 6).

For Count Distinct Percent of Total, we can determine the portion of Product Z that was downloaded by all Customers in April 2022. Based on the visualization, it's 67% (two-thirds, 4 out of 6).

Percent of Total

For each group and for each group member at all levels of the breakdown hierarchy, the percentage share of its value in relation to the total data set value, where the total is calculated as the sum across all rows in the dataset. This aggregate is like Percent of Parent, with the difference that the denominator or reference is ALWAYS based on the complete dataset:

[single node value] / [sum of all rows in the dataset]

The aggregate value is calculated as a ratio between 0 and 1 and will be presented as a percentage value by applying a percent format string in the aggregation settings.

Sample 1

Group (Parent)	Member (Child)	Value	Total Sum	Percent of Total
G1	Α	20	125	0.16
G1	В	30	125	0.24
G1	С	50	125	0.40
G2	D	1.5	125	0.012
G2	Е	1.5	125	0.012
G2	F	2	125	0.016
G3	G	7	125	0.056
G3	Н	9	125	0.072
G3	I	4	125	0.032

Sample 1 Aggregated to Group Level

Group (Parent)	Group Value	Total Sum	Percent of Total
G1	100	125	0.80
G2	5	125	0.04
G3	20	125	0.16

Percent of Total Change

This aggregate should be understood as "Change in (Percent of Total)", not as "Percent of (Total Change)". It is the result of calculating Percent of Total on two different columns, and then calculating the difference between them. The result is presented as the difference in *percentage units*, n.b.

This aggregate is typically used for comparing Percent of Total based on current values, to Percent of Total based on previous values. Therefore, the column specified as "Previous Values Column" in the settings, should be the column containing previous values.

The aggregate value is calculated as a ratio between 0 and 1 and will be presented as a percentage value by applying a percent format string in the aggregation settings. Optionally, you can emphasize that the value is a percentage units by customizing the format unit, for example: 0.00%'-units'.

Sample

ID	Current value	Previous value	Total of current	Total of previous	Percent of Total (current)	Percent of Total (previous)	Percent of Total Change
Α	25	25	100	125	0.25	0.20	+0.05
В	45	65	100	125	0.45	0.52	-0.07
С	30	35	100	125	0.30	0.28	+0.02

Percent of Parent Reference

This aggregate works like <u>Percent of Parent</u>, with the difference that a value from one column is compared to a parent level sum of values *from another column*, which is set as the "Reference column":

[single child node value from a column] / [sum of all child node values from the *reference column* in the group]

While Percent of Parent will always summarize to 100% at the group (parent) level, this is not the case with Percent of Parent Reference, which can summarize to any number, depending on the differences between the **Values** and the **Reference Values**.

The aggregate value is calculated as a ratio between 0 and 1 and will be presented as a percentage value by applying a percent format string in the aggregation settings.

Sample

Group (Parent)	Member (Child)	Value	Weight value	Group Sum of Weight value	Percent of Parent Reference
G1	Α	10	20	100	0.10
G1	В	15	30	100	0.15
G1	С	25	50	100	0.25
G2	D	1	1.5	5	0.20
G2	E	3	1.5	5	0.60
G2	F	2	2	5	0.40
G3	G	14	7	20	0.70
G3	Н	18	9	20	0.90
G3	1	8	4	20	0.40

Percent of Total Reference

This aggregate works like <u>Percent of Total</u>, with the difference that a value from one column is compared to a total data set level sum of values *from another column*, which is set as the "Reference column":

[single node value from a column] / [sum of all rows from the reference column in the dataset]

While Percent of Total will always summarize to 100% across the whole data set, this is not the case with Percent of Total Reference, which can summarize to any number, depending on the differences between the **Values** and the **Reference Values**.

The aggregate value is calculated as a ratio between 0 and 1 and will be presented as a percentage value by applying a percent format string in the aggregation settings.

Sample 1

Group (Parent)	Member (Child)	Value	Weight value	Total Sum of Weight value	Percent of Total Reference
G1	Α	10	20	125	0.08
G1	В	15	30	125	0.12
G1	С	25	50	125	0.20
G2	D	1	1.5	125	0.008
G2	Е	3	1.5	125	0.024
G2	F	2	2	125	0.016
G3	G	14	7	125	0.112
G3	Н	18	9	125	0.144
G3	1	8	4	125	0.064

Sample 1 Aggregated to Group Level

Group (Parent)	Member (Child)	Value	Weight value		Percent of Total Reference
G1		50	100	125	0.40
G2		6	5	125	0.048
G3		40	20	125	0.32

Pos

The sum of the positive values in the selection. If a value is negative or zero, the value n/a is returned.

Sample 1:

Given a list of arbitrary numbers:

Arbitrary	
	3
	2
	1
	0
	-1
	-2
	-3
	0
	0
	0

A list of positive and negative numbers

Steps:

1. Select which values are positive.

Arbitrary	
	3
	2
	1
	n/a

Negative numbers in the list

2. Add the values 3 + 2 + 1 = 6

Sample 2

Given the following sample fields:

Number	Arbitrary	Negative Values	Positive Values	One	Binary	Currency	Decimal
1	3	-1	1	1	0	\$1.00	1.01
2	2	-2	2		1	\$10.00	2.02
3	1	-3	3		0	\$100.00	3.03
4	0	-4	4		1	\$1,000.00	4.04
5	-1	-5	5		0	\$10,000.00	5.05
6	-2	-6	6		1	-\$1.00	6.06
7	-3	-7	7		0	-\$10.00	7.07
8	0	-8	8			-\$100.00	8.08
9	0	-9	9			-\$1,000.00	9.09
10	0	-10	0			\$0.00	0.00

Sample fields.

The Pos value for each field in the table:

55	6	n/a	45	1	3	\$11,111.00	45.45

The results per field.

Product

The product of the selection. Returns the result of multiplying the items in a set of numbers.

Sample 1

Given a list of arbitrary numbers:

Arbitrary	
	1
	2
	3
	4
	5
	6
	7
	8
	9
	10

A list of numbers

The Product of the table above is $1 \times 2 \times 3 \times 4 \times 5 \times 6 \times 7 \times 8 \times 9 \times 10 = 3,628,800$

Sample 2

Given the following sample fields:

Number	Arbitrary	Negative Values	Positive Values	One	Binary	Currency	Decimal
1	3	-1	1	1	0	\$1.00	1.01
2	2	-2	2		1	\$10.00	2.02
3	1	-3	3		0	\$100.00	3.03
4	0	-4	4		1	\$1,000.00	4.04
5	-1	-5	5		0	\$10,000.00	5.05
6	-2	-6	6		1	-\$1.00	6.06
7	-3	-7	7		0	-\$10.00	7.07
8	0	-8	8			-\$100.00	8.08
9	0	-9	9			-\$1,000.00	9.09
10	0	-10	0			\$0.00	0.00

Sample fields.

The Product for each field:

Number	Arbitrary	Negative Values	Positive Values	One	Binary	Currency	Decimal
3,628,800	0	3,628,800	0	1	0	\$0.00	0

The results per field.

Ratio of Sums

The comparison between the sum of a selected measure divided by the sum of the selected reference measure.

The formula:

Ratio of Sums = sum(selected measure) / sum(selected reference measure)

Sample

Given the sample data:


Region	Store	Actual	Target
North	Α	\$1,300	\$2,000
North	В	\$750	\$1,000
North	С	\$2,100	\$3,000
South	D	\$4,700	\$4,000
South	Е	\$2,000	\$2,000

Sample fields

Creating a Table visualization with Breakdowns Region and Store with subtotals and grand totals produces:

Region	Store	Actual	Target
North	Α	\$1,300	\$2,000
	В	\$750	\$1,000
	С	\$2,100	\$3,000
North Total		\$4,150	\$6,000
South	D	\$4,700	\$4,000
	E	\$2,000	\$2,000
South Total		\$6,700	\$6,000
Grand Total		\$10,850	\$12,000

Setting the *Column* to **Actual** and the *Reference Column* to **Target** with the format set to **0.00%** results to the following Ratio of Sums values:



Region	Store	Actual	Target	Ratio of Sums
North	А	\$1,300	\$2,000	65.00%
	В	\$750	\$1,000	75.00%
	С	\$2,100	\$3,000	70.00%
North Total	North Total		\$6,000	69.17%
South	D	\$4,700	\$4,000	117.50%
	Е	\$2,000	\$2,000	100.00%
South Total		\$6,700	\$6,000	111.67%
Grand Total		\$10,850	\$12,000	90.42%

The results per row

Computation details:

North A: \$1,300 / \$2,000 = 65.00% South D: \$4,700 / \$4,000 = 117.50%North B: \$750 / \$1,000 = 75.00% South E: \$2,000 / \$2,000 = 100.00%North C: \$2,100 / \$3,000 = 70.00% South Total: \$6,700 / \$6,000 = 111.67%North Total: \$4,150 / \$6,000 = 69.17% Grand Total: \$10,850 / \$12,000 = 90.42%

Collapsing the North region results to the following Ratio of Sums values:

Region	Store	Actual	Target	Ratio of Sums
North Total		\$4,150	\$6,000	69.17%
South	D	\$4,700	\$4,000	117.50%
	Е	\$2,000	\$2,000	100.00%
South Total		\$6,700	\$6,000	111.67%
Grand Total		\$10,850	\$12,000	90.42%

The results per row

The rest of the computation details are the same except for the collapsed North region:

North =
$$(\$1,300 + \$750 + \$2,100) / (\$2,000 + \$1,000 + \$3,000) = 69.17\%$$

Or

North = \$4,150 / \$6,000 = 69.17%

Collapsing the South region results to the following Ratio values:

Region	Actual	Target	Ratio of Sums
North	\$4,150	\$6,000	69.17%
South	\$6,700	\$6,000	111.67%
Grand Total	\$10,850	\$12,000	90.42%

The results per row

The computation details for the collapsed South region:

South = (\$4,700 + \$2,000) / (\$4,000 + \$2,000) = 111.67%

Or

South = \$6,700 / \$6,000 = 111.67%

Sibling Rank

The numeric rank of siblings within a hierarchy branch.

Returns the rank of a number in a list of numbers. The rank of a number is its size relative to other values in a list. If you were to sort the list, the rank of the number would be its position.

Sample 1:

Given a list of numbers, find each number's Sibling Rank:

Number	
	1
	2
	3
	4
	5
	6
	7
	8
	9
	10

List of numbers.

Steps:

1. Sort the numbers in descending order.

Number	
	10
	9
	8
	7
	6
	5
	4
	3
	2
	1

Sorted numbers in descending order.

- 2. The highest number automatically gets the first position with the sibling rank = 1
- 3. Assign the position as the value of the Sibling Rank

The second highest number equal to 9 gets the second position or sibling rank = 2

The third highest number equal to 8 gets the third position or sibling rank = 3

Repeat this process until there is only one item left.

4. The lowest number automatically gets the last position equal to the number of items or Sibling Rank = 10.

Sample 2:

Given a set of numbers V to Z, the Sibling Ranks are as shown below:

V	w	Х	Υ	z	Sibling Rank V	Sibling Rank W	Sibling Rank X	Sibling Rank Y	Sibling Rank Z
1	1	1	1	10	10	10	10	10	1
2	2	2	2	9	8	9	9	9	2
2	3	3	3	8	8	8	8	8	3
4	5	4	4	7	7	6	7	7	4
5	5	5	5	6	6	6	6	6	5
6	6	6	6	5	5	5	5	5	6
7	7	7	7	4	4	4	2	4	7
8	8	7	8	3	2	2	2	3	8
8	8	7	9	2	2	2	2	2	9
10	10	10	10	1	1	1	1	1	10

The first five fields from the left to the right are the sample fields, and the last five fields are the results.

In the case where duplicate items exists in the list. The duplicate items will have the same rank, and the rank will be the position of the first occurrence of the duplicated items. The position where the next duplicate entries fall will no longer be used as a rank and will be skipped.

In the above example, column V has duplicate entries for the numbers 8 and 2. The resulting column Sibling Rank V shows item 8 has a sibling rank of 2, and position 3 was skipped as a rank. Item 2 has a rank of 8, and position 9 was also skipped as a rank.

Slope

The slope of the least-squares line.

The formula:

Slope =
$$[n\sum (xy) - \sum (x)\sum (y)]/[n\sum (x^2) - \sum (x)^2]$$

Sample 1

Given the set of ${\bf X}$ and ${\bf Y}$ values where ${\bf X}$ and ${\bf Y}$ can represent any correlated values below:

V	W
1	2
2	4
3	6
4	8
5	10
6	12
7	14
8	16
9	18
10	20

Sample table

Steps:

1. Solve the parts of the formula:

Slope =
$$\sum (xy) - \sum (x)\sum (y)]/[n\sum (x^2) - \sum (x)^2$$

n =count of items, equal to 10
 $\sum (xy)$ = multiply all x and y items and get the sum = 770
 $1x2 + 2x4 + 3x6 + 4x8 + 5x10 + 6x12 + 7x14 + 8x16 + 9x18 + 10x20 = 770$
 $\sum (x)$ = sum of x items = 55

 $\sum (y) = \text{sum of y items} = 33$

 $\sum (x^2)$ = get the square of all x items and sum up the values. To square a number also means to multiply the number by itself.

$$1x1 + 2x2 + 3x3 + 4x4 + 5x5 + 6x6 + 7x7 + 8x8 + 9x9 + 10x10 = 385$$

 $\sum (x)^2 = \text{get the sum of all items in x and get the square} = 55 * 55 \text{ or } 3025$

2. Substitute the known values in the formula and computed for the Slope:

Slope =
$$[n\sum(xy) - \sum(x)\sum(y)]/[n\sum(x^2) - \sum(x)^2]$$

Slope = $[10(770) - 55(110)]/[10(385) - 3025]$
Slope = $[7700 - 6050]/3850-3025]$
Slope = $1650/825$
Slope = 2

Stdev

The Standard Deviation of the selection.

The Standard Deviation is a measure of how spread-out numbers are in a set. The deviation just means how far from the normal.

Stdev is used when the group of numbers being evaluated is only a partial sampling of the whole population.

The formula:

$$s = \sqrt{\frac{1}{N-1} \sum_{i=1}^{N} (x_i - \overline{x})^2}$$

Where \overline{x} is the mean computed by getting the sum of all the items and dividing them by the number of items minus one.

Sample 1

Given a set of numbers like 12, 6, 12.

Steps:

1. Compute the mean of the sample.

Mean = (Sum of items/n), where n is the number of items

12+6+12/3=10

2. Square the difference between each point and the mean

 $(12-10)^2 = 4$

 $(6-10)^2 = 16$

(12-10)^2 =4

3. Calculate the average of the results in step 2 above

4+16+4/3-1=24/2

4. Compute the square root of the result in step 4.

 $\sqrt{12}$ or 3.4641

Sample 2:

Given the following sample fields:

Number	Arbitrary	Negative Values	Positive Values	One	Binary	Currency	Decimal
1	3	-1	1	1	0	\$1.00	1.01
2	2	-2	2		1	\$10.00	2.02
3	1	-3	3		0	\$100.00	3.03
4	0	-4	4		1	\$1,000.00	4.04
5	-1	-5	5		0	\$10,000.00	5.05
6	-2	-6	6		1	-\$1.00	6.06
7	-3	-7	7		0	-\$10.00	7.07
8	0	-8	8			-\$100.00	8.08
9	0	-9	9			-\$1,000.00	9.09
10	0	-10	0			\$0.00	0.00

Sample fields.

The Stdev for each field:

Number	Arbitrary	Negative Values	Positive Values	One	Binary	Currency	Decimal
3.0277	1.7638	3.0277	3.0277	0	.5345	\$3,197.5720	3.0579

The results per field.

Stdevp

The Population Standard Deviation of the selection.

The Stdevp deals with the complete population whereas Stdev deals with a population sample only.

The formula:

$$\sigma = \sqrt{\frac{1}{N} \sum_{i=1}^{N} (x_i - \mu)^2}$$

Sample 1:

Population: A set of data that is all inclusive.

Populations are often very large. For simplicity, imagine the following as an example:

12,6,12

Compute the Stdevp:

Steps:

1. Determine the mean of the sample

12+6+12/3=10

2. Square the difference between each item and the mean

 $(12-10)^2 = 4$

 $(6-10)^2 = 16$

 $(12-10)^2 = 4$

3. Calculate the average

4+16+4/3=24/3

4. Calculate the square root

 $\sqrt{8}$ or 2.8284

Sample 2

Given the following sample fields:

Number	Arbitrary	Negative Values	Positive Values	One	Binary	Currency	Decimal
1	3	-1	1	1	0	\$1.00	1.01
2	2	-2	2		1	\$10.00	2.02
3	1	-3	3		0	\$100.00	3.03
4	0	-4	4		1	\$1,000.00	4.04
5	-1	-5	5		0	\$10,000.00	5.05
6	-2	-6	6		1	-\$1.00	6.06
7	-3	-7	7		0	-\$10.00	7.07
8	0	-8	8			-\$100.00	8.08

9	0	-9	9		-\$1,000.00	9.09
10	0	-10	0		\$0.00	0.00

Sample fields.

The Stdevp for each field:

Number	Arbitrary	Negative Values	Positive Values	One	Binary	Currency	Decimal
2.8723	1.6733	2.8723	2.8723	0	0.4949	\$3,033.4832	2.9010

The results per field.

Sum

The sum or total of the selection.

Computed by adding all the items in a set of numbers.

Sample 1

Given a list of arbitrary numbers:

Arbitrary	
	1
	2
	3
	4
	5
	6
	7
	8
	9
	10

A list of numbers

The Sum of the table above is 1 + 2 + 3 + 4 + 5 + 6 + 7 + 8 + 9 + 10 = 55

Sample 2

Given the following sample fields:

Number	Arbitrary	Negative Values	Positive Values	One	Binary	Currency	Decimal
1	3	-1	1	1	0	\$1.00	1.01
2	2	-2	2		1	\$10.00	2.02
3	1	-3	3		0	\$100.00	3.03

4	0	-4	4	1	\$1,000.00	4.04
5	-1	-5	5	0	\$10,000.00	5.05
6	-2	-6	6	1	-\$1.00	6.06
7	-3	-7	7	0	-\$10.00	7.07
8	0	-8	8		-\$100.00	8.08
9	0	-9	9		-\$1,000.00	9.09
10	0	-10	0		\$0.00	0.00

Sample fields.

The Product for each field:

Number	Arbitrary	Negative Values	Positive Values	One	Binary	Currency	Decimal
3,628,800	0	3,628,800	0	1	0	\$0.00	0

The results per field.

Unique

The Unique aggregation is used with numeric values and will display a number in case all the values in a group are the same, otherwise it will show empty/null. This aggregation can be used as an indicator of a logical test: "if the numeric values in this group and in any subgroups are identical, then show the numeric value, or else show nothing".

Sample 1

Group1	Group2	same_value_all	same_value_in_group	mixed_value
root	а	7	3	2
root	а	7	3	1
root	а	7	3	4
root	b	7	6	5
root	b	7	6	4
root	b	7	6	7

The Unique for each field with Group1 as breakdown item:

Group1	Group2	same_value_all	same_value_in_group	mixed_value
		7		

The Unique for each field with Group1 and Group2 as breakdown items:

Group1	Group2	same_value_all	same_value_in_group	mixed_value
		7	3	
		7	6	

Text Unique and Text Concat Distinct

The Text Unique aggregates text fields to distinct values while Text Concat Distinct aggregates text fields to display all possible text values in a comma delimited list.

Given this data table:

Country	Industry	Company	1 Day Change % (USD)	Mcap(USD)
AT	Financials	Erste Group Bank AG	-0.07	3439883100
AT	Financials	Raiffeisen International Bank-Holding AG	-0.07	1371987780
AT	Basic Materials	voestalpine AG	-0.03	1412883878
AT	Industrials	Wienerberger AG	-0.04	660942066
AU	Basic Materials	BHP Billiton Ltd.	-0.06	74380605994
AU	Basic Materials	Lihir Gold Ltd.	0.02	5377974426
AU	Basic Materials	Fortescue Metals Group Ltd.	-0.02	2104618718
BE	Financials	KBC Group N.V.	-0.05	2369136539
BE	Basic Materials	Solvay S.A.	0.04	4151907147
BE	Basic Materials	Umicore S.A.	-0.03	2078266946
CA	Consumer Goods	Magna International Inc. CI	-0.05	2981991456
CA	Financials	Canadian Imperial Bank of Commerce	-0.03	13960011146

The Country, Industry, and Company are text columns while 1 Day Change % (USD) and Mcap(USD) are numeric columns.

Sample 1


Below is the defined breakdown in a Table visualization:



This Table visualization is showing the grouping of the columns based on the breakdown hierarchy with Company, 1 Day Change % (USD), and Mcap(USD) as Visual Members and with the corresponding aggregates:

Column	Aggregate
Company	Text Unique
1 Day Change % (USD)	Sum
Mcap(USD)	Sum


By default, the aggregate of Company is set to Text Unique.



The Table visualization now displays the distinct text values of a Company for the breakdown columns, Country and Industry.

		Company	1 Day Change % (USD)	Mcap(USD)
AT	Basic Materials	voestalpine AG	-0.03	1412883878
	Financials		-0.14	4811879880
	Industrials	Wienerberger AG	-0.04	660942066
AU	Basic Materials		-0.06	81863199138
BE	Basic Materials		0.02	6230174093
	Financials		-0.05	2369136539
CA	Consumer Goods	Magna International Inc. CI A	-0.05	2981991456
	Financials	Canadian Imperial Bank of Commerce	-0.03	13960011146

If the aggregate for the Company column is changed to **Text Concat Distinct**, all the text values for the corresponding breakdown columns are displayed in a comma delimited list:



		Company	1 Day Change % (USD)	Mcap(USD)
AT	Basic Materials	voestalpine AG	-0.03	1412883878
	Financials	Erste Group Bank AG, Raiffeisen International Bank-Holding AG	-0.14	4811879880
	Industrials	Wienerberger AG	-0.04	660942066
AU	Basic Materials	BHP Billiton Ltd., Lihir Gold Ltd., Fortescue Metals Group Ltd.	-0.06	81863199138
BE	Basic Materials	Solvay S.A., Umicore S.A.	0.02	6230174093
	Financials	KBC Group N.V.	-0.05	2369136539
CA	Consumer Goods	Magna International Inc. CI A	-0.05	2981991456
	Financials	Canadian Imperial Bank of Commerce	-0.03	13960011146

You can opt to display a text column as a distinct count. Refer to **Count Distinct** for more information.

Weighted Harmonic Mean

The weighted harmonic mean of the selection based on a specified weighting column.

Weighted Harmonic Mean is calculated the same way as the Harmonic Mean. The Harmonic Mean is defined as a special case where all of the weights are equal to 1 and is equivalent to any weighted harmonic mean where all weights are equal.

The formula:

If a set of weights $w_1, ..., w_n$ is associated to the dataset $x_1, ..., x_n$, the weighted harmonic mean is defined by

$$\frac{\sum_{i=1}^{n} w_i}{\sum_{i=1}^{n} \frac{w_i}{x_i}}$$

Sample 1:

As a simple example, the Weighted Harmonic Mean of 1, 2, and 4 given the weights 5, 6, 7 respectively is:

$$18/(5/1 + 6/2 + 7/4) = 18/9.75 = 1.8462$$

Weighted Mean

The weighted mean of the selection based on a specified weighting column.

It is a mean where some values contribute more than others.

Weighted means can help with decisions where some considerations are more important than others.

The formula:

Weighted Mean =
$$\frac{\Sigma wx}{\Sigma w}$$

In other words: multiply each weight w by its matching value x, sum that all up, and divide by the sum of weights.

Sample 1:

Sam wants to buy a new camera, and decides on the following rating system:

- Image Quality 50%
- Battery Life 30%
- Zoom Range 20%

Based on reviews the Cony camera gets 8 (out of 10) for Image Quality, 6 for Battery Life and 7 for Zoom Range

The Sanon camera gets 9 for Image Quality, 4 for Battery Life and 6 for Zoom Range

Which camera is best?

Cony: $(50/100) \times 8 + (30/100) \times 6 + (20/100) \times 7 = 4 + 1.8 + 1.4 = 7.2$

Sanon: $(50/100) \times 9 + (30/100) \times 4 + (20/100) \times 6 = 4.5 + 1.2 + 1.2 = 6.9$

Sam decides to buy the Cony.

Sample 2:

A Company sells Mango products with the following Revenue breakdown for the current year:

Products	Revenue
Mango Tarts	45,000
Mango Juice	297,000
Dried Mangoes	975,000
Total	1,317,000

The revenue values per product.

The Company posted an increase in revenue from the previous year with the following Percentage Change:

Products	Revenue Percentage Change
Mango Tarts	50%
Mango Juice	10%
Dried Mangoes	30%

Revenue percentage change values.

Compute for the all-over revenue change percent:

 $((50/100) \times 45,000 + (10/100) \times 297,000 + (30/100) \times 975,000) / 1,317,000$

or

(22,500 + 29,700 + 292,500) / 1,317,000 = .26 or 26%

Weighted Sample Standard Deviation and Weighted Sample Variance

The formula used for calculation of the weighted sample Standard Deviation ("Weighted Stdev") and weighted sample Variance ("Weighted Variance") is the following, defined by NIST.gov, National Institute of Standards and Technology:

$$s^2 \ = \frac{\sum_{i=1}^N w_i (x_i - \bar{x}^*)^2}{\frac{(M-1)}{M} \sum_{i=1}^N w_i},$$

Where:

N is the number of observations.

M is the number of nonzero weights.

 $oldsymbol{w_i}$ are the weights.

 $oldsymbol{x_i}$ are the observations.

 $ar{x}^*$ is the weighted mean.

Example with sample data:

Value	6	7	8	9	10	11	12	23
Weight	1	1	1	1	1	1	1	100

Mean	Weighted Mean	Sample Standard Deviation	Weighted sample Standard Deviation		Weighted sample Variance
10.75	22.08	5.34	3.74	28.50	13.99

Weighted Population Standard Deviation and Weighted Population Variance

The formula used for *weighted population variance* is a straight extension of the *population variance*. The population variance formula is:

 $var_p = sum((x_i - \mu)^2) / N$, where $\mu = sum(x_i) / N$

The weighted population variance formula is the above with some extension:

 $wvar_p = sum(w_i * (x_i - \mu')^2) / sum(w_i), where \mu' = sum(w_i * x_i) / sum(w_i)$

Example with sample data:

Value	6	7	8	9	10	11	12	23
Weight	1	1	1	1	1	1	1	100

Mean	Weighted Mean	Population Standard Deviation	Weighted population Standard Deviation		Weighted population Variance
10.75	22.08	4.99	3.50	24.94	12.25

Weighted Sum

The sum of the product of the selected field and the weight field.

The Formula:

WeightedSum = $\sum (x w)$ where x are the items and w are weights

Sample 1:

Given the weights .20, .15, .40 and .25 compute the weighted sum of the following numbers: 25, 20, 15, 30.

Computation:

WeightedSum = $25 \times 0.20 + 20 \times 0.15 + 15 \times 0.40 + 30 \times 0.25 = 21.50$

Sample 2:

Alex wants to buy a new camera, and has the following preferences based on a scale of 1 to 10, and 10 being the highest:

■ Image Quality: 8

Battery Life: 8

■ Zoom Range: 5

Based on reviews the Cony camera gets 7 (out of 10) for Image Quality, 5 for Battery Life and 6 for Zoom Range

The Sanon camera gets 6 for Image Quality, 5 for Battery Life and 7 for Zoom Range

Which camera is best?

Cony: $8 \times 7 + 8 \times 5 + 5 \times 6 = 56 + 40 + 30 = 126$

Sanon: $8 \times 6 + 8 \times 5 + 5 \times 7 = 48 + 40 + 35 = 123$

Alex decides to buy the Cony.

NOTE

Weighted columns such as Weighted Mean, Weighted Harmonic Mean, and Weighted Sum have the Weight drop-down list enabled.

SNAPSHOT VISUALIZATION SETTINGS

Each visualization has specific settings controlling the display. For more information on what is the most appropriate visualization to use, refer to Panopticon Visualizations.

Bar Graph Settings

Bar Graphs are probably the best-known visualization for quantitative data.

You can display Panopticon Bar Graphs either horizontally or vertically. These graphs are available in three variants:


- Standard
- Grouped
- Stacked

In each case, you can sort the layout of the bar graph according to your requirements, and, with hierarchical data, the graph represents the netted position at each aggregated depth level.

The bar graph settings pane is displayed after clicking the **Options**




button.




Setting	Description
Bar Mode	Specifies the mode of the bar graph, which can be Standard , Stacked , or Grouped .
Bar Width Ratio (%)	Defines the ratio of the width within the bars. Default is .75.
Show Borders	Determines whether borders are drawn around bars or stacks within bars.
Show Labels	Determines whether labels are drawn inside the bars or not.
Show Values	Determines whether values are displayed on each bar or not.
Adaptive Mode	Automatically swaps to the Standard mode when displaying the top items within a hierarchy.
Value Margin	The width of the margin of the Values from the border.

Other visualization-specific properties can be set by clicking on either:

□ <u>Y-Axis</u> variable drop area then selecting the **Y-Axis** tab (for Vertical Bar Graphs) or





Box Plot Settings

Box Plots are designed to display numeric distributions.


The plot draws the Minimum, 25th Percentile, Median, 75th Percentile, and Maximum of the specified measure by category.

This can be provided as a single measure, where Panopticon performs the aggregation.

Or as separate measures for each component of the box plot, where the data source performs the aggregation.


The box plot settings pane is displayed after clicking the **Options**





Setting	Description
Paint Mode	The no fill color. Possible values: Fill or Border .
Box Width Ratio	Defines the ratio between boxes and the space within each box. Default is 0.5 .
Show Borders	Determines whether borders are drawn around the box. Disabled when the <i>Paint Mode</i> is set to Border .
Show Whiskers	Determines whether to display lines extending vertically from the boxes, indicating variability outside the upper and lower quartiles.

Other visualization-specific properties can be set by clicking on the **Y-Axis** variable drop area and then selecting the <u>Y-Axis</u> tab:



Bullet Graph Settings

Bullet Graphs were designed by Stephen Few to remove unnecessary clutter and instead focus on visualizing metrics like Key Performance Indicators (KPI).


Research has shown that bullet graphs are easier to interpret in less time than the radial gauges or speedometers often seen in BI dashboards.






Other visualization-specific properties can be set by clicking on either:


Y-Axis variable drop area then selecting the Y-Axis tab (for Vertical Bullet Graphs) or




X-Axis variable drop area then selecting the X-Axis tab (for Horizontal Bullet Graphs)





Furthermore, there is the X-axis setting (for Vertical Bullet Graphs) or Y-Axis setting (for Horizontal Bullet Graphs):







Setting	Description
Margin	The margin in pixels for the axis. If set to zero, the axis is removed.










Categorical Line Graph Settings

Line Graphs are easy to understand and are a great way to communicate important time-based trends, clustering, relative performance and outliers.

However, on occasion the axis is not time, but instead categorical. In this case a categorical line graph is used.


The categorical line graph settings pane is displayed after clicking the **Options**





Setting	Description
Dots Radius	Specifies the radius of each dot in pixels.
Show Borders	Determines whether a border is drawn around each dot.
Line Width	The line width.

Other visualization-specific properties can be set by clicking on the $\underline{\text{Y-Axis}}$ variable drop area and then selecting the $\underline{\text{Y-Axis}}$ tab:



Circle Pack Settings

Circle Packs represent hierarchical data sets, showing both each level in the hierarchy and how they interact with each other. They are consequently used for identifying patterns of performance, and outliers within peer groups.


They are represented by a colorful mosaic of enclosed circles based on your data. The size of a circle reflects its importance. The color conveys urgency or variance.

Circle Packs can also be cross tabbed and offer an alternative to the <u>Heat Matrix</u>, with the added benefit of having both a size (typically relating to importance), and a color variable (typically related to performance variance).

Most people can learn to understand the information presented in a Circle Pack in under a minute – even if that Circle Pack is showing data representing an underlying data set of thousands of records.

A recommended alternative to the Circle Pack is the <u>Treemap</u>, which can display a larger number of data points, and is easier to compare constituent data points.

The circle pack settings pane is displayed after clicking the **Options** button.



Setting	Description
Show Borders	Determines whether a border is drawn around each circle.
Show Labels	Determines whether labels are displayed within each circle.
Show Outer Circle	Determines whether to display the outer circle.

Donut Chart Settings


Donut Charts are a derivative of the pie chart and are used in the same manner for displaying contributions to a total.

Panopticon can produce standard Donut Charts in which the donut slice represents a numeric variable that is proportional to the total size of the donut. The color variable can represent either a category or another numeric variable.

Donut Charts can be flat, showing a single set of slices. They can also be hierarchical and display multiple levels of data in a variant called a Multilevel Donut Chart.

A recommended alternative to the Donut Chart is the <u>Treemap</u>, which can display a larger number of data points, and is easier to compare constituent data points.

The donut chart settings pane is displayed after clicking the **Options** button.



Setting	Description
Show Borders	Determines whether a border is drawn around each leaf.
Show Labels	Determines whether labels are displayed within each leaf.

Donut Gauge Settings

Donut Gauge charts display percentage of total based metrics like Key Performance Indicators (KPI), and support values between 0 and 100%.

They remove unnecessary clutter and instead focus on best displaying the metric and provide an alternative to the Bullet graph.

Panopticon can produce standard Donut Gauge Charts in which the slice angle represents a percentage.

The color variable can represent either a category or another numeric variable.

Donut Gauge Charts can be individual, or displayed in cross tabs, highlighting differences between items.

An alternative visualization to the Donut Gauge to highlight differences between items and contribution to the total may be the Treemap.

The donut gauge chart settings pane is displayed after clicking the Options



Show Borders Slice Thickness 0.25

Setting	Description
Slice Thickness (%)	Specifies the thickness of the donut slice.
Show Borders	Determines whether a border is drawn around each donut.

Dot Plot Settings

Dot Plots have two primary use cases:

- A more effective alternative to a Bar Graph
- A distribution display similar to a Scatter Plot


Dot Plots are an effective alternative to Bar Graphs, particularly in cases where the data being analyzed contains many similar numeric values.

In comparison with the Bar Graph, Dot Plots do not use a zero baseline and are less cluttered. This makes it easier to add additional data variables to the visualization.

The dot plot settings pane is displayed after clicking the Options




button.




Setting	Description
Dot Radius	Specifies the radius of each dot in pixels.
Show Borders	Determines whether a border is drawn around each dot.
Show Grid Lines	Determines whether grid lines are drawn through each dot.
Show Connecting Lines	Determines whether a line is drawn between the dots category constituents. Allows a categorical line graph to be displayed.
Line Width	Specifies the width in pixels of the line if enabled.

Other visualization-specific properties can be set by clicking on either:

□ <u>Y-Axis</u> variable drop area then selecting the **Y-Axis** tab (for Vertical Dot Plots) or



 \square X-Axis variable drop area then selecting the X-Axis tab (for Horizontal Dot Plots)



Funnel Chart Settings

Funnel Charts are a type of Bar Graph, often used to represent stages in a sales process or order fulfillment process and can show the amount of potential revenue for each stage.


This type of chart can be useful in identifying potential problems in an organization's sales process.

Color can be used to represent either a Stage in the process, or the change in performance for that stage against a prior period.

Alternatives to the Funnel Chart would be a simple Bar Graph, or a Stacked Bar Graph.

The funnel chart settings pane is displayed after clicking the **Options**





Setting	Description
Bar Thickness Ratio	Specifies the thickness ratio of the bars and spaces between bars.
Bar Width Padding	Specifies the width padding between the bar and the border.
Show Borders	Determines if a border is drawn around each bar.
Show Values on Bars	Determines if values are displayed in bars.

Heat Matrix Settings

A Heat Matrix is similar to both the Heat Map and <u>Treemap</u> in that it displays many different data items and represents the value for each item using colors. However, unlike its cousins, the Heat Matrix has a defined structure where two data attributes define each axis, thus producing a correlation matrix. Within the Heat Matrix, each column and row represent a unique attribute, and the point where two items intersect represents a unique combination of the two attributes.


* Options

button.

The matrix can display labels within each intersecting tile or simply display color.

Our Heat Matrix data visualization helps our clients identify correlations within their data sets using an intuitive graphical display.

The heat matrix settings pane is displayed after clicking the **Options**



Setting	Description
Apply Color To	Sets how the color variable is displayed: Background or Text.
Show Titles in Cells	Determines whether the field Title is shown in the cell.
Show Values in Cells	Determines whether

This visualization also acts as a Pivot Table, like the current cross tabbed tile, with rows and columns. In addition, it is similar with the Table visualization as it displays row totals.

You can set these properties in the following controls:

Setting	Description
Show Grand Total Row	Determines whether to display the grand total of the values of the Color and Detail variables on the X-axis (either as data in the cells or in the Popup).
Show Sub Total Row	Determines whether to display the sub totals of the values of the Color and Detail variables on the X-axis (either as data in the cells or in the Pop-up).
Show Grand Total Column	Determines whether to display the grand total of the values of the Color and Detail variables on the Y-axis (either as data in the cells or in the Popup).
Show Sub Totals Column	Determines whether to display the sub totals of the values of the Color and Detail variables on the Y-axis (either as data in the cells or in the Pop-up).

Map Plot Settings

Use Map Plots to display geographic data, where you have longitudes and latitudes associated with individual data points. These plots clearly show data correlations and clustering that is geographic in nature.

In a Map Plot, the visualization expects Latitude and Longitude measures to be associated. It will then retrieve from the selected map tile provider the appropriate background map to display under the data points. This background map is constructed by retrieving individual map tiles at set zoom levels.

As the background map is provided automatically, it relies on:

- ☐ A range of supplied longitudes & latitudes to provide a bounding area
- ☐ An active Internet connection to retrieve the map tile images


Panopticon ships with a number of cross reference datasets to determine the appropriate latitude/longitude for datasets. These have been provided through subsets of the data available at GeoNames.org. (http://www.geonames.org)

More detailed geo-coding data is available from this website, and many others.

The map plot settings pane is displayed after clicking the **Options**



button.



Setting	Description
Map Provider	Determines which Map Provider should be used for providing Map tiles. Initially only a single map provider is defined, but more can be added by modifying the configuration.
Show Shapes	Determines whether shapes will be displayed. Turned on by default.
Min Radius	The minimum radius in pixels of the data point.
Max Radius	The maximum radius in pixels of the scatter point.
Show Line	Determines whether to plot lines between two positions on the map. Enables the <i>Line, Line Color</i> , and <i>Line Color</i> properties.
Line	Two ways to plot the line: Rhumb Lines – straight lines

	Great Circle Arc – curve between dots showing the path over the earth spherical surface
Line Width	Width of the plot line.
Line Color	Color of the plot line: Use Variable - colors can be specified for the elements in the visualization through the Color variable. Custom Color — displays the Custom Color section. Line Color — Custom Color — Custom Color — Custom Color — #c0c0c0 Click the Color box to display the Color dialog and select the color or enter the Hex color code.
Show Arrows	Determines whether to display arrows to indicate where lines start and end.
Arrow Offset	Where the arrows will be positioned in the lines. • 0 – start • 0.5 – middle • 1 - end
Show Labels	Determines whether labels will be displayed.
Label Mode	Enabled when Show Labels is checked. This property determines how data point labels are shown. Values can be: Distinguishable All
Shape	The shape of the scatter point. This can be: Filled Circle Filled Square Use Variable shapes can be specified for the elements in the visualization through the Shape variable.
Show Borders	Determines whether a border is drawn around each data point.
Keep Zoom and Pan	Determines whether the saved zoom and pan state on data refresh and initial dashboard load are kept.
Show Zoom Levels	Determines whether a zoom level indicator should be displayed on the Map Plot.
Max Zoom Level	The maximum zoom to be applied when there is a single data point, rather than a collection, so a latitude / longitude bounding box cannot be established.

Network Graph Settings

A Network Graph displays relationships between entities and can be used to identify correlations or flows between items.

The Network graph supports a two-level breakdown defining the "From", and "To", where each node (vertex / point), is either in the "From", or "To" levels of the breakdown, and each edge (or line), represents the data specific to this "From \rightarrow To" relationship.

The size of the node is specific to the number of interactions/relationships it has with other nodes. There can be up to two lines connecting two nodes, which can display arrows to show direction; and represent the "From \rightarrow To" combinations, e.g., $A \rightarrow B$, and $B \rightarrow A$. Each line can also be colored to map to a numeric variable.

Customers use network graphs for investigating correlations, transactional flows, latency, and throughput bottlenecks.

Options

button.

The network graph settings pane is displayed after clicking the **Options**



Setting	Description
Node Min Radius	The minimum radius of each node.
Node Max Radius	The maximum radius of each node.
Min Edge Thickness	The minimum thickness of each edge that represents the connection between nodes.
Max Edge Thickness	The maximum thickness of each edge that represents the connection between nodes.
Show Edge Direction	Whether to display the direction of the edges.

Numeric Line Graph Settings

Show Edge Direction

Numeric Line Graphs differ from the standard line graph in that they have a numeric X axis, rather than one based upon time.

They are commonly used in both scientific and financial scenarios to show trends in functions that are based on two numeric inputs (X and Y).

Common uses include the display of Yield Curves.

Numeric Line Graphs can also be used to display selected cuts through a Surface Plot.


The numeric line graph settings pane is displayed after clicking the **Options**






Setting	Description
Line Width	Specifies the width in pixels of the lines.
Point Radius	Specifies the radius of each point in pixels that the line passes through.
Shade Area Below Line	Defines that opacity shades are applied between the lines and the zero Y grid line.
Shade Area Opacity (%)	Specifies the opacity (transparency) of the shaded area, expressed in percent 0-100 of the opacity value currently set on the line.
Show Coordinates	Determines whether the graph coordinates (i.e., X-Y plots, or Date/Time-Y plots) on mouse over are displayed in the visualization.

Other visualization-specific properties can be set by clicking on the $\underline{\text{X-Axis}}$ variable drop area and then selecting the $\underline{\text{X-Axis}}$ tab:



Or also, by clicking on the $\underline{\text{Y-Axis}}$ variable drop area and then selecting the $\underline{\text{Y-Axis}}$ tab:



Numeric Needle Graph Settings

Numeric Needle Graphs display price distributions.

Unlike a traditional Bar Graph, the X Axis is numeric rather than categorical. Bars are positioned along the X axis according to their X value, and their height is determined by their Y values. For the Horizontal variant, the X Axis represents the height, and the Y axis the price.

This allows gaps, and clustering in price to be more accurately identified, and are typically used for displaying price distributions and order book displays.

The numeric needle graph settings pane is displayed after clicking the **Options**




button.




Setting	Description
Needle Width	Specifies the width in pixels of each needle: NOTE: This is overridden when a column is added in the <i>Size</i> variable. Consequently, the width of the needles will be based on the comparison of their size in relation to where they are located on the X axis.
Max Focus Radius	Determines the maximum radius of the focus circle when hovering on the needles. This also controls the padding of the axis in the direction in which the needles expand, allowing the focus circle to have enough space to be drawn.
Show Borders	Specifies whether a border is drawn around needles. These are only visible if the Needle Width is greater than 1 pixel.
Show Labels	Specifies whether node labels will be displayed.
Show Coordinates	Determines whether the graph coordinates (i.e., X-Y plots, or Date/Time-Y plots) on mouse over are displayed in the visualization.

Other visualization-specific properties can be set by clicking on the $\underline{\text{X-Axis}}$ variable drop area and then selecting the $\underline{\text{X-Axis}}$ tab:



Or also, by clicking on the $\underline{Y-Axis}$ variable drop area and then selecting the $\underline{Y-Axis}$ tab:



Numeric Stacked Needles Graph Settings

Numeric Stacked Needles again display price distributions.

Unlike the standard Numeric Needle Graph, multiple items can be identified at a single price.

A common usage is displaying client activity within an order book.

The numeric stacked needle graph settings pane is displayed after clicking the **Options**




button.




Setting	Description
Needle Width	Specifies the width in pixels of each needle: NOTE: This is overridden when a column is added in the <i>Size</i> variable. Consequently, the width of the needles will be based on the comparison of their size in relation to where they are located on the X axis.
Max Focus Radius	Determines the maximum radius of the focus circle when hovering on the needles. This also controls the padding of the axis in the direction in which the needles expand, allowing the focus circle to have enough space to be drawn.
Show Borders	Specifies whether a border is drawn around needles. These are only visible if the Needle Width is greater than 1 pixel.
Show Labels	Specifies whether node labels will be displayed.
Show Coordinates	Determines whether the graph coordinates (i.e., X-Y plots, or Date/Time-Y plots) on mouse over are displayed in the visualization.

Other visualization-specific properties can be set by clicking on the $\underline{\text{X-Axis}}$ variable drop area and then selecting the $\underline{\text{X-Axis}}$ tab:



Or also, by clicking on the $\underline{\text{Y-Axis}}$ variable drop area and then selecting the $\underline{\text{Y-Axis}}$ tab:




Pareto Chart Settings

The Pareto Chart is a combination of the <u>Bar Graph</u> and <u>Categorical Line Graph</u>, and can be used for comparing actuals to forecasts, and if the dataset is available, comparing individual to cumulative returns.

The traditional usage of a Pareto chart displays individual values in a descending order as bars, with the cumulative total represented by the line.


The pareto chart settings pane is displayed after clicking the **Options**






Setting	Description
Bar Width Ratio (%)	Defines the ratio of the width within the bars. Default is .5.
Show Bar Borders	Determines whether borders are drawn around bars or stacks within bars.
Show Bar Labels	Specifies whether labels are drawn inside the bars.
Show Bar Values	Specifies whether values are displayed in bars.
Dot Axis Alignment	Determines whether the dot axis is aligned to the Right or Left .
Dot Radius	Specifies the radius of each data point in pixels.
Show Dot Borders	Determines whether a border is drawn around each dot.
Show Lines	Determines whether a line is drawn between the dots category constituents. Allows a categorical line graph to be displayed.
Line Width	Specifies the width in pixels of the line if enabled.

Other visualization-specific properties can be set by clicking on the $\underline{\text{Left Y}}$ variable drop area and then selecting the $\underline{\text{Left Axis}}$ tab:



Or also, by clicking on the Right Y variable drop area and then selecting the Right Axis tab:



Pie Chart Settings

Pie Charts are one of the oldest and best-known visualizations for displaying contributions to a total.

Panopticon can produce standard Pie Charts in which the pie slice represents a numeric variable that is proportional to the total size of the pie. The color variable can represent either a category or another numeric variable.


Pie Charts can be flat, showing a single set of slices. They can also be hierarchical and display multiple levels of data in a variant called a Multilevel Pie Chart. This is also known as a Sun Burst or a Radial Treemap.

The user can modify the visible depth level and drill into slices to investigate further detail.

A recommended alternative to the Pie Chart is the <u>Treemap</u>, which can display a larger number of data points, and is easier to compare constituent data points.

The pie chart settings pane is displayed after clicking the **Options**





Setting	Description
Show Borders	Determines whether borders are drawn around each pie slice. This is enabled by default.
Show Labels	Determines whether labels are displayed within each pie slice.
Show Groups	Determines whether a multilevel Pie Chart (or Sun Burst) is displayed, where each hierarchy level is represented in a nested group.

Record Graph Settings

A record visual is effectively a transposed table and can be used to display the metrics for one, or a few individual records (or aggregated records).


Like the table, metrics are added to "Visual Members", but correspond to rows in the record (rather than columns in a table).

Row cells display their text value which may wrap into multiple lines.

Text can be colored either with a background or foreground.

The record graph settings pane is displayed after clicking the **Options**





Setting	Description
Show Grid	Determines whether grid lines are visible or not.
Word Wrap	Determines whether to wrap the text.
Value Alignment	Alignment of the value: By Data Type Left Center Right

Scatter Plot Settings

Scatter Plots are used to identify trends, clustering and outliers across a number of numeric variables, especially when investigating large data volumes.

Each scatter point is represented by:

1/		٠.	
X	Po	SIT	ınr

Y Position

Size

Color (numeric or categorical)


A line of best fit can also be added to highlight outliers.

Panopticon's Scatter Plot data visualizations are easy to set up and highly customizable. You can configure your display in ways that will make the most sense to you and your users, and users have all the tools they need to filter and manipulate the Scatter Plot to concentrate on the most relevant subsets in the data.

The scatter plot settings pane is displayed after clicking the Options




button.




Setting	Description	
Show Borders	Determines whether a border is drawn around each scatter point.	
Show Best Fit Line	Determines whether a Line of Best Fit is added to the Scatter Plot.	
Show Labels	Determines whether labels will be displayed. If enabled, select how scatter point labels are shown: Distinguishable All	
Min Radius	The minimum radius in pixels of the scatter point.	
Max Radius	The maximum radius in pixels of the scatter point.	
Show Line	Determines whether to plot lines between two positions or dots on the scatter plot. Enables the <i>Line Width</i> and <i>Line Color</i> properties.	
Line Width	Width of the plot line.	
Line Color	 Color of the plot line: Use Variable - colors can be specified for the elements in the visualization through the Color variable. Custom Color - displays the Custom Color section. 	
Show Arrows	Determines whether to display arrows to indicate where lines start and end.	
Arrow Offset	Where the arrows will be positioned in the lines. • 0 – start • 0.5 – middle • 1 - end	
Background Image	Defines that a background image is displayed behind the scatter plot. You can either: • click Resource then Choose File and select the background image in the Open dialog that displays. • click URL and enter the URL of the image file. This value can be parameterized and use Snapshot and retrieve the image upon each parameter value change.	
Legacy Shape	Allows older workbooks to be updated and use the shape variable. Default is Use Variable . Other shapes can also be selected.	
Show Coordinates	Determines whether the graph coordinates (i.e., X-Y plots, or Date/Time-Y plots) on mouse over are displayed in the visualization.	

Other visualization-specific properties can be set by clicking on the $\underline{X-Axis}$ variable drop area and then selecting the $\underline{X-Axis}$ tab:



Or also, by clicking on the $\underline{\text{Y-Axis}}$ variable drop area and then selecting the $\underline{\text{Y-Axis}}$ tab:




3D Scatter Plot Settings

3D Scatter Plots are a 3D perspective version of the 2D Scatter Plot. They provide a clearer understanding of physical shapes in a 3D space. The Scatter Plot 3D is made up of a series of points where each point has X Position, Y Position and Z Position.

In addition, items can be sized by numeric data values, and colored by numeric or text data values. Items can also be shown as different shapes – either standard shapes available in Panopticon or custom shapes that you add to a custom shape palette.

The 3D Scatter Plot settings pane is displayed after clicking the Options





Setting	Description
Show Borders	Determines whether borders are visible around each scatter point.
Show Labels	Determines whether labels will be displayed. If enabled, select how scatter point labels are shown: Distinguishable All
Min Radius	The minimum radius in pixels of the scatter point.
Max Radius	The maximum radius in pixels of the scatter point.
Show Axes	Determines whether axes are displayed.
Show Axes Titles	Determines whether axes titles are displayed.
Show Ground Plane	Determines whether the ground plane is displayed.


Shapes Settings

The Shapes visualization allows the display of Choropleth Graphs and other displays built from SVG Paths.

The Shapes visualization can be used to display data where both physical location and size are important.

They clearly show data correlations and clustering that is geospatial in nature.

Unlike the Geographic Scatter Plot, the size of each shape is fixed, imparting the importance of the item. Consequently, data should be relative to each shape size, such as area densities.



Setting	Description
Show Borders	Determines whether borders are visible around each shape.

Surface Plot Settings

Surface Plots are used to identify trends and outliers within numeric surfaces.


The Surface is made up of a series of points where each point has:

- X Position
- Y Position
- □ Color (which represents the Z axis).

The Surface Plot can support data sets where the X and Y positions can both be regular and irregular in their distribution.


Additionally, the color scale can be continuous or stepped to show a surface gradient.

The surface plot settings pane is displayed after clicking the **Options** button.




Setting	Description
Show Points	Determines whether surface data points are shown.
Rectilinear Grid	Determines whether distinct X and Y values are changed into a rectilinear grid where missing values are filled in with a default of zero (or the ground level).
Show Coordinates	Determines whether the graph coordinates (i.e., X-Y plots, or Date/Time-Y plots) on mouse over are displayed in the visualization.

Other visualization-specific properties can be set by clicking on the $\underline{X-Axis}$ variable drop area and then selecting the $\underline{X-Axis}$ tab:



Or also, by clicking on the $\underline{\text{Y-Axis}}$ variable drop area and then selecting the $\underline{\text{Y-Axis}}$ tab:



3D Surface Plot Settings

3D Surface Plots are a 3D perspective version of the 2D Surface Plot.

They provide a clearer understanding of the overall "shape" of the surface, but they also introduce occlusion problems; not all data points can be seen due to the display perspective.

The Surface Plot 3D is made up of a series of points where each point has:

- X Position
- Y Position
- Z Position (encoded by color)


The Surface Plot 3D can support data sets where the X and Y positions can both be regular and irregular in their distribution.

The color scale can be continuous or stepped to show a surface gradient.

Grid lines, a ground plane, and markers for data points can be shown if required.

The 3D surface plot settings pane is displayed after clicking the Options





Setting	Description
Show Axes	Determines whether axes are displayed.
Show Axes Titles	Determines whether axes titles are displayed.
Show X Grid	Determines whether the X Grid lines are displayed and if checked the space in pixels between them.
Preferred X Grid Space	Specifies the X Grid lines spacing. Default is 100 .
Show Y Grid	Determines whether the Y Grid lines are displayed and if checked the space in pixels between them.
Preferred Y Grid Space	Specifies the Y Grid lines spacing. Default is 100.
Show Points	Determines whether markers are drawn over surface data points.
Show Ground Plane	Determines whether a ground plane should be drawn below the 3D surface
Rectilinear Grid	Determines whether distinct X and Y values are changed into a rectilinear grid where missing values are filled in with a default of zero (or the ground level).

Table Visualization Settings

A table can be used to display a small dataset where all the values are visible or the aggregate values of a larger data set.

The table can be configured to show hierarchies, allowing sub totals and grand totals to be displayed. Additionally, branches of the hierarchy can be expanded and collapsed.

The table can be sorted by clicking on a column heading, and sorting is applied across the defined hierarchy.


Columns widths can be adjusted manually or automatically, and columns can be hidden when required.

Columns cells can be represented in their value form or, alternatively, graphically as a series of micro-charts including:

	Bullet Graph			
	Bar Graph			
	Dot Plot			
The	e table settings pane is disp	played after clicking the Opt	ions Options	button
	Show Sub Totals			
	Show Grand Total			
	Show Totals Above			
	Virtual Mode			

Setting	Description
Show Sub Totals	Determines whether Sub Total aggregate rows are shown in the table.
Show Grand Total	Determines whether the Grand Total aggregate row is shown in the table.
Show Totals Above	Determines whether the Grand Total or Sub Totals are displayed above the rows in the table.
Virtual Mode	Determines whether the table will be in a virtual or flat mode in the Web client. If so, the collapse and expand options will not be available.
Only Include Visible Columns	Determines whether to only include the visible table columns when exporting data. Default is true .

Other visualization-specific properties can be set by clicking on the **Records** variable drop area and then selecting the $\underline{\text{X-Axis}}$ tab:



Setting	Description
Word Wrap	Determines whether to wrap the X-axis text.
Show Grid Lines	Determines whether grid lines are drawn on the X-axis.
Axis Bar Thickness	The margin in pixels for the axis. If set to zero, the axis is removed.
Alignment	The alignment of the column text header: Left, Center, or Right
Foreground	Foreground color of the X-axis.
Background	Background color of the X-axis.
Column Axis Bar Thickness	The thickness of the bar from the column axis.

Ticker Tile Settings

The Ticker Tile is used to display three metrics, typically:

- Price
- Change in Price
- % Change in Price


Where the price is displayed in a double height label, the change in price to the bottom left of the tile, and the color shown as the background of the tile, and the numeric value displayed in the bottom right of the tile.

Icons can also be added to the tile to indicate the change in other metrics.

As with all visualizations, as data changes the tile will automatically update.

The ticker tile settings pane is displayed after clicking the **Options**





Setting	Description
Apply Color To	Sets how the color variable is displayed: Background or Text

Treemap Settings

Treemaps represent hierarchical data sets, showing both each level in the hierarchy and how they interact with each other.

They are represented by a colorful mosaic of rectangular cells based on your data. The size of a cell reflects its importance. The color conveys urgency or variance:

- White Target/Benchmark Performance
- □ Red Under Performance
- Blue Over Performance

The intensity of the red or blue shades indicates the level of under- or over-performance.

Most people can learn to understand the information presented in a Treemap in under a minute – even if that Treemap is showing data representing an underlying data set of thousands of records.

Our Treemaps are not static pictures. The real value of the visualization is quickly apparent when you interact with the data. Users can zoom, filter, and view details on demand, as well as link to and highlight other sources of information. For example, fund managers can link to a trading system directly from within the Treemap.

EX supports two different styles of Treemaps:

- Classic Treemaps
- Cluster Treemaps

The treemap settings pane is displayed after clicking the Options



Style Cluster ▼

Setting	Description	
Style	Specifies the style that will be applied in displaying performance of a Treemap level. Available options are:	
	Classic	
	Best for displaying performance at leaf level.	
	Custer	
	Best for simultaneously displaying performance at all levels. This is the default style.	

Waterfall Chart Settings

Waterfall Charts are a form of cumulative Bar Chart, showing the cumulative effect across a series of changes.

Options

button.

They can aid in the understanding of how performance changes contribute to a final position.


Color can be used to represent either a Stage in the process, or the change in performance for that stage.

The waterfall chart settings pane is displayed after clicking the **Options**



Setting	Description
Bar Width Ratio (%)	Defines the ratio of the width within the bars. Default is .5.
Value Labels	Defines what type of value labels are shown in bars: Bar Value or Cumulative Value .
Show Borders	Determines whether borders are drawn around bars.
Show Connecting Lines	Determines whether connecting lines are drawn between bars.

Other visualization-specific properties can be set by clicking on the $\underline{Y\text{-Axis}}$ variable drop area and then selecting the $\underline{Y\text{-Axis}}$ tab:



TIMESERIES VISUALIZATION SETTINGS

Candle Stick Graph Settings

Candle stick graphs are a traditional financial visualization for display of time-based price distributions. Specifically, for each time slice, they display:

- Opening Price
- Highest Price
- Lowest Price
- Closing Price


The Candle is filled if the closing price is lower than the open and empty if the closing price is higher than the open.

The vertical line (or candle wick) displays the range of traded prices across the period.

The candle stick graph settings pane is displayed after clicking the **Options**




button.



Setting	Description
Body Thickness	Specifies the width in pixels of the Candle Stick Body.
Wick Thickness	Specifies the width in pixels of the Candle Stick Wick.
Show Coordinates	Determines whether the graph coordinates (i.e., X-Y plots, or Date/Time-Y plots) on mouse over are displayed in the visualization.

Other visualization-specific properties can be set by clicking on the $\underline{\text{Y-Axis}}$ variable drop area and then selecting the $\underline{\text{Y-Axis}}$ tab:



Setting	Description
Independent Y-Axis Scaling	Determines whether to have each visualization Y-axis in a cross tab automatically scaled independent of the others.

Horizon Graph Settings

Horizon Graphs are a fantastic way to overview many time series in a limited rectangular space. Since this visualization packs the information in a line graph in 1/6th the space through smart pre-attentive color encoding, it allows for an overview of many time series. Users can scan huge amounts of data points across all relevant time series and immediately identify areas of concern that require closer scrutiny.


Our Horizon Graph visualization is particularly useful when you need to see many time series on a single screen. This makes it easy to compare trends and spot patterns that would be very difficult or impossible to see in a standard report.



The horizon graph settings pane is displayed after clicking the **Options**



Setting	Description
Height	Specifies the vertical height in pixels for an individual Horizon.
Padding	Specifies the vertical space in pixels between adjoining Horizons.




Setting	Description
Margin	Margin from the Y axis.

Line Graph Settings


Line Graphs are easy to understand and are a great way to communicate important time-based trends, clustering, and outliers.


They work especially well when comparing ten or fewer data sets (our <u>Horizon Graph</u> is a good solution for displaying time series data with ten or more data sets).

The line graph settings pane is displayed after clicking the **Options** button.



Setting	Description
Line Width	Specifies the line width in pixels.
Dot Radius	Specifies the radius of each data point in pixels.
Dash Pattern	Specifies the line pattern. Available options are: Dotted Dashed Solid
Line Interpolation	Specifies whether the line is Stepped , Linear , or Smooth interpolation.
Value Interpolation Time Gaps	Determines whether time axis gaps (Working Week/Time) are interpolated.
Value Interpolation Na Value Gaps	Determines whether Na value (or missing) gaps are interpolated.
Shade Area Below Line	Defines that opacity shades are applied between the lines and the zero Y grid line.
Shade Area Opacity (%)	Specifies the opacity (transparency) of the shaded area, expressed in percent 0-100 of the opacity value currently set on the line.
Show Last Value	Determines if the flag of the last value will be displayed.





Setting	Description
Independent Y-Axis Scaling	Determines whether to have each visualization Y-axis in a cross tab automatically scaled independent of the others.

Needle Graph Settings


Needle Graphs display time-based transactions or occurrence frequencies, rather than time-based trends. They are simply time-based Bar Graphs where each bar is located at a particular time point on the axis.

They work especially well when combined with a Line Graph.


The most common use of a Needle Graph is when showing the trading volume for a stock, typically underneath the price performance.

The needle graph settings pane is displayed after clicking the **Options**






Setting	Description
Needle Width	Specifies the width in pixels for each needle:
Set Width to Time Slice	Determines whether the Needle width will be extended to the width of the time slice. NOTE: Will not go past a null/empty time slice.
Show Borders	Determines whether borders are drawn around needles. These are only visible if the Needle Width is greater than 1 pixel.
Show Coordinates	Determines whether the graph coordinates (i.e., X-Y plots, or Date/Time-Y plots) on mouse over are displayed in the visualization.




Setting	Description
Independent Y-Axis Scaling	Determines whether to have each visualization Y-axis in a cross tab automatically scaled independent of the others.

Stacked Needle Graph Settings

The stacked needle graph settings pane is displayed after clicking the **Options** button.




Setting	Description
Needle Width	Specifies the width in pixels for each needle:
Set Needle Width to Time Slice	Determines whether the Needle width will be extended to the width of the time slice. NOTE: Will not go past a null/empty time slice.
Show Borders	Determines whether borders are drawn around needles. These are only visible if the Needle Width is greater than 1 pixel.
Show Coordinates	Determines whether the graph coordinates (i.e., X-Y plots, or Date/Time-Y plots) on mouse over are displayed in the visualization.




Setting	Description
Independent Y-Axis Scaling	Determines whether to have each visualization Y-axis in a cross tab automatically scaled independent of the others.

Grouped Needle Graph Settings

The grouped needle graph settings pane is displayed after clicking the **Options** button.



Setting	Description
Needle Width	Specifies the width in pixels for each needle:
Show Borders	Determines whether borders are drawn around needles. These are only visible if the <i>Needle Width</i> is greater than 1 pixel.
Show Coordinates	Determines whether the graph coordinates (i.e., X-Y plots, or Date/Time-Y plots) on mouse over are displayed in the visualization.



Setting	Description
Independent Y-Axis Scaling	Determines whether to have each visualization Y-axis in a cross tab automatically scaled independent of the others.

OHLC Graph Settings

OHLC Graphs also display time-based distributions of price data. For each time slice, they display:

- Opening Price
- Highest Price
- □ Lowest Price
- Closing Price

Similar with the <u>Candle Stick Graph</u>, a vertical line defines the range of traded prices across the period. However, in this case, the left notch determines the opening price, and the right notch determines the closing price.


Options

button.

The OHLC graph settings pane is displayed after clicking the **Options**



Setting	Description
Bar Thickness	Specifies the width in pixels of the OHLC Body.
Tick Length	Specifies the length in pixels of the Open and Close ticks.
Show Coordinates	Determines whether the graph coordinates (i.e., X-Y plots, or Date/Time-Y plots) on mouse over are displayed in the visualization.



Setting	Description
Independent Y-Axis Scaling	Determines whether to have each visualization Y-axis in a cross tab automatically scaled independent of the others.


Order Book Graph Settings

The Order Book Graph displays an aggregated order book of prices and associated sizes across time. For each time slice, it displays:


- Price (as Height)
- ☐ Tick Size (as Size)
- Order Size (as Color)
- Duration of Aggregated Orders at a given price (time period)



The order book graph settings pane is displayed after clicking the **Options**



Setting	Description
Show Borders	Determines whether a border is drawn around each bar.
Interpolate Across Time Axis Gaps	Determines whether time axis gaps (Working Week/Time) are interpolated.
Interpolate Across Na Value Gaps	Determines whether Na value (or missing) gaps are interpolated.
Show Coordinates	Determines whether the graph coordinates (i.e., X-Y plots, or Date/Time-Y plots) on mouse over are displayed in the visualization.



Setting	Description
Independent Y-Axis Scaling	Determines whether to have each visualization Y-axis in a cross tab automatically scaled independent of the others.

Price Band Graph Settings

The Pricing Band Graph displays the variance or spread between two time-based metrics.


Each grouping defined in the breakdown will be displayed as a separate layer of the overall graph, where typically color is used to display the category.

As it is expected that spread layers will occlude, the transparency is defaulted to 50% and can be modified as appropriate.


Typical use cases include comparing the pricing bid offer spreads from multiple liquidity providers.



The price band graph settings pane is displayed after clicking the **Options**



Setting	Description
Line Width	Select the line width (in pixels)
Spread Color Opacity	Specifies the level of color transparency/opacity for the Positive and Negative Spread colors. The value is from 0 to 255 with the default set to 128.
Line Interpolation	Specifies whether the line is Stepped , Linear , or Smooth interpolation.
Value Interpolation Time Gaps	Determines whether time axis gaps (Working Week/Time) are interpolated.
Value Interpolation Na Value Gaps	Determines whether Na value (or missing) gaps are interpolated
Show Coordinates	Determines whether the graph coordinates (i.e., X-Y plots, or Date/Time-Y plots) on mouse over are displayed in the visualization.



Setting	Description
Independent Y-Axis Scaling	Determines whether to have each visualization Y-axis in a cross tab automatically scaled independent of the others.

Spread Graph Settings

The Spread Graph displays the variance or spread between two time-based data series.

Typical use cases include comparing a stock's price performance to an Index or a bond's yield to a benchmark rate.

The spread graph settings pane is displayed after clicking the **Options**




Line Width 1 Spread Color Opacity 255 Line Interpolation Linear Value Interpolation Time Gaps Na Value Gaps Value Line Color #a6a6a6 Reference Line Color #a6a6a6 Positive Spread Color #69a0d2 Negative Spread Color #ea6258 **Show Coordinates**

Setting	Description
Line Width	Specifies the width in pixels of the Spread Graph data series lines.
Spread Color Opacity	Specifies the level of color transparency/opacity for the Positive and Negative Spread colors. The value is from 0 to 255 with the default set to 128.
Line Interpolation	Specifies the interpolation mode as Linear, Stepped, or Smooth.
Value Interpolation Time Gaps	Determines whether to interpolate across weekend and closed period gaps.
Value Interpolation Na Value Gaps	Determines whether Na value (or missing) gaps are interpolated.
Value Line Color	Specifies the color of the value line data series.
Reference Line Color	Specifies the color of the reference line data series.
Positive Spread Color	Specifies the color when the spread between the value and reference is positive.
Negative Spread Color	Specifies the color when the spread between the value and reference is negative.

Show Coordinates

Determines whether the graph coordinates (i.e., X-Y plots, or Date/Time-Y plots) on mouse over are displayed in the visualization.




Setting	Description
Independent Y-Axis Scaling	Determines whether to have each visualization Y-axis in a cross tab automatically scaled independent of the others.

Stack Graph Settings

Stack Graphs let you visualize quantitative changes to several data sets over time, and you can see how each data point contributes to the total. As with the Treemap the Height of the stack relates Importance, while the color relates Urgency or variance.

Stack Graphs are a great way to look at revenue or gross profit figures over time across several product lines. Stack Graphs are also good to use when you have up to ten or eleven time series data sets to look at, especially for data sets that have a large number of data points.

Setting	Description
Value Interpolation Time Gaps	Determines whether time axis gaps (Working Week/Time) are interpolated.
Show Border	Determines whether borders are drawn around stacks.
Show Coordinates	Determines whether the graph coordinates (i.e., X-Y plots, or Date/Time-Y plots) on mouse over are displayed in the visualization.



Setting	Description
Independent Y-Axis Scaling	Determines whether to have each visualization Y-axis in a cross tab automatically scaled independent of the others.

Timeseries Scatter Plot Settings


Time Series Scatter Plots display time-based transactions, similar to the Needle graphs. Like the scatter plot, it displays individual data points (or transactions), with a given numeric Y value and a given timestamp X value.

Common uses include displaying transaction volume across time relative to the price at which the volume was executed and displaying order book depth across time.


Typically, the graph is combined with line graphs to show the scatter points relative to defined boundaries.

The timeseries scatter plot settings pane is displayed after clicking the Options





Setting	Description
Shape	The shape of the scatter point. This can be: Filled Circle Circle Filled Square Square Use Variable – shapes can be specified for the elements in the visualization through the Shape variable
Min Radius	The minimum radius in pixels of the scatter point.
Max Radius	The maximum radius in pixels of the scatter point.
Show Borders	Determines whether a border is drawn around each scatter point.
Show Coordinates	Determines whether the graph coordinates (i.e., X-Y plots, or Date/Time-Y plots) on mouse over are displayed in the visualization.



Setting	Description
Independent Y-Axis Scaling	Determines whether to have each visualization Y-axis in a cross tab automatically scaled independent of the others.

Timeseries Surface Plot Settings


Time Series Surface Plots are used to identify trends and outliers within Time Series surfaces, typically forward curves across time.

The Surface is made up of a series of points where each point has:


- □ Time Position
- Y Position
- □ Color (which represents the Z axis).

The color scale can be continuous or stepped to show a surface gradient.

The timeseries surface plot settings pane is displayed after clicking the **Options** button.



Setting	Description
Show Points	Determines whether surface data points are shown.
Rectilinear Grid	Determines whether distinct y values and time slices are changed into a rectilinear grid where missing values are filled in with a default of zero (or the ground level).
Show Coordinates	Determines whether the graph coordinates (i.e., X-Y plots, or Date/Time-Y plots) on mouse over are displayed in the visualization.



COMBINATION VISUALIZATIONS SETTINGS

The Combination Graphs allow combining multiple variables as layers in a series graph sharing a common x-axis.

Unlike other visualizations, the Text-, Numeric- and Time Combination Graphs allow combination of many variables, based on different columns of a data table, each rendered independently, using a selected visualization.

The Time Combination Graph allows rendering using the following visualizations:

- Line
- Candle Stick
- □ Bar
- Grouped Bar
- Stacked Bar
- □ OHLC (Open-High-Low-Close)

	Order Book
	Price Band
	Scatter
	Spread
	Stack
The	Text- and Numeric Combination Graphs support the following visualizations:
	Line
	Price Band
	Bar
	Grouped Bar
	Stacked Bar
	Scatter
	Spread
	Stack

All combination graphs also support reference lines, left and right y-axis as well as cross-tabbing, to create multiple small visualizations across dimensions.


Guidelines in Using the Numeric Combination Graph

Sample data used in this section.

sample	var_x	var_y
s1	0	1
s1	1	2
s1	2	1
s1	3	2
s1	4	1
s2	0	3
s2	1	4
s2	3	4
s2	4	3
s3	0	5
s3	1	6
s3	2	5
s3	3	6
s3	4	5


When you want to visualize several samples, or series, as lines of the same numeric variable in the Numeric Combination Graph, there is a requirement that you do the following:

□ Create a Numeric Bucket column of type "Id" (unique values), based on the X-variable column



□ Include the X-variable Id Numeric Bucket in the *Items* on the visualization

Sample 1. Only the sample column is added on the Items list






Sample 2. sample and idX columns are added on the *Items* list.


Switch off Single Series for the Y-axis variable

With the above settings in place, you will get separate lines per each sample identity. You will then also be able to color those line by the sample identity. If your dataset has missing values, for one or several of the samples/series, you can bridge those value gaps by switching on interpolation of NA value gaps on the Y-variable.

Sample 3. Single series on Y is turned OFF



Sample 4. Interpolation of NA value gaps on Y is turned ON.



[Save Save Siew ← NumericCombination ← [Light] - 5 II @ B A A **①** Numeric Combination Data Table idX, Sample, X, Y SampleVars () → Columns ↓ Rows items → ↓ idX sample ::: Q Search Columns Visuals [] Size abc Auto Key abc idX Color Opacity Shape abc sample # var_x Details ✓ Ref Lines # var_y (I) Options Visualizations Left Axis var_y (<u>A</u> var_x Visualization Single Series Aggregate Sum Format Y Axis Alignment Left Color sample Shared Constant Opacity var_y ☑ Workbook Data Table Editor

Sample 5. Color line by the sample column

Creating Density Plots in the Numeric Combination Graph


Sample data used in this section.




В	2
В	2
В	3
В	3
В	3
В	4
В	4


A density plot describes the frequency or count of observations in data for each value along the x-axis. For a data set with a number of X-variable observation and two or more categories in the data, you create a density plot in the following way:

□ Put the **Category** text column on *Items*, the x-variable on *X* and the x-variable also on *Visuals*.




□ Create a Numeric Bucket column of typ Id, based on the x-variable column (named idX) and add it to Items, as the top level.







On the Visuals x-variable column, switch off **Single Series**, and set **Count** as aggregation method.



On the X-axis x-variable columns, set **Mean** as aggregation method



Optionally, put the category column on Color, and select the category coloring for the Visuals column. Also select Smooth as line interpolation, and switch on Shade Area Below Line.



Adding a Numeric Combination Graph

This section discusses the steps to create the numeric combination graph using the following sample dataset, where:

$$cos = COS([deg]*2/360*Pi)$$

$$sin = SIN([deg]*2/360*Pi)$$

Auto Key	cos	deg	sin
1	1.00	0.00	0.00
2	0.98	10.00	0.17
3	0.94	20.00	0.34
4	0.87	30.00	0.50
5	0.77	40.00	0.64
6	0.64	50.00	0.77
7	0.50	60.00	0.87
8	0.34	70.00	0.94
9	0.17	80.00	0.98
10	0.00	90.00	1.00


11	-0.17	100.00	0.98
12	-0.34	110.00	0.94
13	-0.50	120.00	0.87
14	-0.64	130.00	0.77
15	-0.77	140.00	0.64
16	-0.87	150.00	0.50
17	-0.94	160.00	0.34
18	-0.98	170.00	0.17
19	-1.00	180.00	0.00

Steps:

 The numeric combination settings pane is displayed after clicking the **Options** Visualization Title (i.e., Numeric Combination):




button or the




2. Set the following property:

Setting	Description
Show Coordinates	Determines whether the graph coordinates (i.e., X-Y plots, or Date/Time-Y plots) on mouse over are displayed in the visualization. Tap the slider to turn it on.

To build the hierarchical structure in the numeric combination graph, <u>drag text columns</u> to the *Breakdown Items* drop area (e.g., **Auto Key**).




4. To set the X-axis, drag numeric columns from the *Data Table* pane to the <u>X</u> variable drop area. For this sample visualization, the **deg** column will be the used as the height variable.



- 5. You can opt to drag columns to the Size, Color, Opacity, Shape, Reference Lines, and Details drop area.
- 6. Continue designing the visualization by dragging numeric columns from the *Data Table* pane to the **Visuals** variable drop area.


The column (e.g., **sin**) is added under the **Visualizations** tab list and, by default, uses the <u>Line graph</u> and the Left Y-Axis alignment.



The graph displays a single series based on the column added in the breakdown.

7. The properties that you can set will depend on the visualization type that you will add.

The general settings include:




Setting	Description					
Title	Title of the visualization.					
Visualization	If the visualization is incorrect, instead of deleting, you can just select another one in the <i>Visualization</i> drop-down list. The settings pane will be changed to display the corresponding properties of the selected visualization.					
Aggregate	Aggregation method to be used. Default is Sum .					
Format	The format that numbers will be displayed in. Panopticon uses the same formatting rules as MS Excel.					
Divide By	Select the <i>Divide By</i> value to divide a number: 1					
Y Axis Alignment	The Y-Axis alignment: Left or Right.					
Color	The <i>Color</i> variable that will be used for the column: None Shared Single Custom Single Column added to the <i>Column</i> variable					
Column/Value Column	The column used for the visualization. If the dragged column is incorrect, instead of deleting, you can just select another column in the <i>Column/Value Column</i> drop-down list.					

8. Visual members can be set to display any of the following visualizations:




Line




Setting	Description						
Single Series	Determines whether to use all columns in the breakdown to create a single series or if one column should be used to divide the data into multiple series.						
Opacity	Select the <u>Opacity</u> value.						
Line Width	Specifies the line width in pixels.						
Dot Radius	Specifies the radius of each data point in pixels.						
Line Interpolation	Specifies whether the line is Stepped , Linear , or Smooth interpolation.						
Value Interpolation Time Gaps	Determines whether time axis gaps (Working Week/Time) are interpolated.						
Value Interpolation Na Value Gaps	Determines whether Na value (or missing) gaps are interpolated.						
Shade Area Below Line	Defines that opacity shades are applied between the lines and the zero Y grid line.						
Shade Area Opacity (%)	Specifies the opacity (transparency) of the shaded area, expressed in percent 0-100 of the opacity value currently set on the line.						
Display Last Value	Determines if the flag of the last value will be displayed. Once enabled, the Show Last Value Title is displayed. Display Last Value Show Last Value Title Check the box to display the title of the last value in the flag.						
Dash Pattern	Specifies the line pattern. Available options are: Dotted Dashed Solid						


Sample 1. Single Series is enabled, and the Color is set to Custom Single (#2580bd).




Scatter




Setting	Description
Single Series	Determines whether to use all columns in the breakdown to create a single series or if one column should be used to divide the data into multiple series.
Size	Select the <u>Size</u> variable that will be used.
Shape	Select the Shape value.
Opacity	Select the <i>Opacity</i> value.
Show Borders	Determines whether a border is drawn around each scatter point.



Sample 2. *Single Series* is enabled in the Line and Scatter graphs. In addition, in the Scatter graph, the *Color* is set to **Custom Single** (#bb2525).




Spread




Setting	Description
Reference Column	The field that will be used as the reference line data series.
Line Width	Specifies the width in pixels of the Spread Graph data series lines.
Opacity	Select the <i>Opacity</i> value.

Spread Color Opacity	Specifies the level of color transparency/opacity for the Positive and Negative Spread colors. The value is from 0 to 255 with the default set to 128 .						
Line Interpolation	Specifies the interpolation mode as Linear, Stepped, or Smooth.						
Value Interpolation Na Value Gaps	Determines whether Na value (or missing) gaps are interpolated.						
Value Line Color	Specifies the color of the value line data series.						
Reference Line Color	Specifies the color of the reference line data series.						
Positive Spread Color	Specifies the color when the spread between the value and reference is positive.						
Negative Spread Color	Specifies the color when the spread between the value and reference is negative.						

Sample 3. Single Series is enabled in the Line graph. In addition, in the Spread graph, the Value Column is set to the **cos** column, and the Reference Column to the **sin** column.




Price Band




Setting	Description					
Single Series	Determines whether to use all columns in the breakdown to create a single series or if one column should be used to divide the data into multiple series.					
Reference Column	The field that will be used as the reference line data series.					
Line Width	pecifies the line width in pixels.					
Opacity	Select the <i>Opacity</i> value.					
Line Interpolation	Specifies whether the line is Stepped , Linear , or Smooth interpolation.					
Value Interpolation Na Value Gaps	Determines whether Na value (or missing) gaps are interpolated.					

Sample 4. Single Series is enabled in the Line and Price Band graphs. In addition, in the Price Band graph, the Color is set to **By Sign**, the Value Column is set to the **cos** column, and the Reference Color to the **sin** column.




Bar





Setting	Description
Opacity	Select the <i>Opacity</i> value.
Bar Width	Specifies the width in pixels for each bar.
Show Borders	Determines whether borders are drawn around bars. These are only visible if the Bar Width is greater than 1 pixel.

Sample 5. Single Series is enabled in the Line graph. In addition, in the Bar graph, the Column is set to the **sin** column, the Color to the **deg** column, and the Bar Width to **2**.



Stacked Bar or Grouped Bar






Additional settings include:

Setting	Description
Bar Width	Specifies the width in pixels of each bar. NOTE: This is overridden when a column is added in the <i>Size</i> variable. Consequently, the width of the bars will be based on the comparison of their size in relation to where they are located on the X axis.
Show Borders	Specifies whether a border is drawn around bars. These are only visible if the Bar Width is greater than 1 pixel.


Stack




Additional settings include:

Setting	Description
Single Series	Determines whether to use all columns in the breakdown to create a single series or if one column should be used to divide the data into multiple series.
Show Borders	Determines whether borders are drawn around stacks.

9. The numeric combination visualization includes an expanded axes pane, which includes specification of the properties for both the Left and Right Y axes.





Select or specify the following properties:

Setting	Description						
Scale	Determines whether the scale of the axis is Linear , Log , or Power .						
		• Linear – a change between two values is based on addition e.g., 30, 60, 90, 120, 180, etc.					
		Log - a change between two values is perceived on the basis of the ratio of the two values or based on multiplication.					
		Once selected, the <i>Base</i> control displays with the value of the common base for the logarithmic scale (i.e., 10).					
	Scale	Log	*				
		Base					
		10					
		e: log10(x) represents 100, 1000, etc.	the logarithm of x to the base 10				
	You can opt to enter a new <i>Base</i> value then click						

	NOTE: Value cannot be lower than 2. • Power – Works according to the SIGN (MEASURE) *LOG10 (MAX (1,							
	ABS (MEASURE))) formula. Works like the Log scale except it can handle negative values and every value between -1 and 1 is set to 0. For example for values between -100 and 100, the axis will be: -100, -10, 0, 10, 100							
Inverted	Determines whether the Y or Height axis is inverted.							
Show Title	Displays an Axis Title label. When enabled, you can opt to enter a custom <i>Title</i> for the axis which will override the title of the visualization variable.							
Axis Bar Thickness	The margin in pixels for the axis. If set to zero, the axis is removed.							
Preferred Tick Space	The preferred space in pixels between the minor grid lines across the axis.							
Minor Grid Line	How minor grid lines are drawn across the axis. Allowed values: None Dotted Dashed Solid							
Major Grid Line	How major grid lines are drawn across the axis. Allowed values: None Dotted Dashed Solid							
Tick Format	Set to From Variable to use the format string that is on the current variable displayed in the axis. Set to Metric Prefix to format the Tick labels in the numeric axes using the metric prefixes.							
Tickmarks	Click to add and set tick marks. Tickmarks t Value 0 Label Enter the Value and the Label. Click to add more or to delete.							
Range	The visible range for the Left and Right Y-axis variables can either be calculated dynamically (Dynamic Range) or set between predetermined limits by selecting Fixed Range . This enables the <i>Min</i> and <i>Max</i> text boxes and populates them with default values taken from the data set.							
Independent Y-Axis Scaling	Determines whether to have each visualization Y-axis in a cross tab automatically scaled independent of the others.							
Title and Format From	The title and format of the Left and Right Axes based on the selected fields.							

Text Combination Settings

This section discusses the steps and guidelines to create the text combination graph using the following sample dataset.


Sample Table

Auto Key	Gr	ld	Line	Bar	Scatter	Spread	SpreadRef	Stack
1	X	Α	3.00	4.00	2.00	1.00	3.0	1.0
2	X	В	4.00	5.00	3.00	2.00	3.0	3.0
3	X	С	5.00	6.00	4.00	2.00	4.0	2.0
4	Υ	D	3.00	4.00	2.00	5.00	4.0	4.0
5	Υ	E	4.00	5.00	3.00	6.00	4.0	1.0
6	Υ	F	5.00	6.00	4.00	5.00	4.0	3.0


Steps:

1. The text combination settings pane is displayed after clicking the **Options** *Visualization Title* (i.e., Text Combination):






2. To build the hierarchical structure in the text combination graph, <u>drag text columns</u> to the *Breakdown Items* drop area (e.g., **Id**, **Gr**, and **Auto Key**).



3. You can opt to drag columns to the <u>Size</u>, <u>Color</u>, <u>Opacity</u>, <u>Shape</u>, <u>Reference Lines</u>, and <u>Details</u> drop area. For this sample visualization, we dragged the **Id** column to the <u>Color</u> and <u>Shape</u> variables drop areas.



4. Continue designing the visualization by dragging numeric columns from the *Data Table* pane to the **Visuals** variable drop area.

- 5 II @ B A A ← TextCombo (+) [Light] **Text Combination** Data Table Id Gr Auto Key (+)(<u>-</u>] Text → Columns ₼ Items Q Search Columns Visuals [] Size abc Auto Key abc Gr Color Opacity Shape abc Id # Bar ✓ Ref Lines □ Details **ॐ** Style # Line # PriceBand ₹ Filters Options # Ref # Scatter Left Axis Visualizations Right Axis # Spread 4|1 **(** Line # SpreadRef # Stack Sum, Line Title Visualization Line Single Series Aggregate Sum Format #,##0.00 (\$) D В

The column (e.g., **Line**) is added under the **Visualizations** tab list and, by default, uses the <u>Line graph</u> and the Left Y-Axis alignment.

The X axis displays the multi-level hierarchy based on the three columns added in the breakdown (e.g., **Id**, **Gr**, and **Auto Key**). The Y axis displays the added visual member (e.g., **Line**).


5. The properties that you can set will depend on the visualization type that you will add.

Shared Single

Y Axis Alignment

The general settings include:

☑ Workbook Data Table Editor




Setting	Description
Title	Title of the visualization.
Visualization	If the visualization is incorrect, instead of deleting, you can just select another one in the <i>Visualization</i> drop-down list. The settings pane will be changed to display the corresponding properties of the selected visualization.
Aggregate	Aggregation method to be used. Default is Sum .
Format	The format that numbers will be displayed in. Panopticon uses the same formatting rules as MS Excel.
Divide By	Select the <i>Divide By</i> value to divide a number: 1
Y Axis Alignment	The Y-Axis alignment: Left or Right.
Color	 The Color variable that will be used for the column: None Shared Single Custom Single Column added to the Column variable
Column/Value Column	The column used for the visualization. If the dragged column is incorrect, instead of deleting, you can just select another column in the <i>Column/Value Column</i> drop-down list.

6. Visual members can be set to display any of the following visualizations:




Line




Setting	Description
Single Series	Determines whether to use all columns in the breakdown to create a single series or if one column should be used to divide the data into multiple series.
Opacity	Select the <i>Opacity</i> value.
Line Width	Specifies the line width in pixels.
Dot Radius	Specifies the radius of each data point in pixels.

Line Interpolation	Specifies whether the line is Stepped , Linear , or Smooth interpolation.
Value Interpolation Time Gaps	Determines whether time axis gaps (Working Week/Time) are interpolated.
Value Interpolation Na Value Gaps	Determines whether Na value (or missing) gaps are interpolated.
Shade Area Below Line	Defines that opacity shades are applied between the lines and the zero Y grid line.
Shade Area Opacity (%)	Specifies the opacity (transparency) of the shaded area, expressed in percent 0-100 of the opacity value currently set on the line.
Display Last Value	Determines if the flag of the last value will be displayed. Once enabled, the Show Last Value Title is displayed.
	Display Last Value Show Last Value Title
	Check the box to display the title of the last value in the flag.
Dash Pattern	Specifies the line pattern. Available options are: Dotted Dashed Solid

Sample 1. Single Series is enabled, the Line Width is set to **4**, the Dot Radius to **6**, and the **Shade Area Below Line** is enabled.




Sample 2. Single Series is disabled, the Line Width is set to **4**, the Dot Radius is set to **6**, and the **Shade Area Below Line** is enabled.



The last column in the breakdown (e.g., Auto Key) is used to divide the data into multiple series.


Spread




Setting	Description
Reference Column	The field that will be used as the reference line data series.
Line Width	Specifies the width in pixels of the Spread Graph data series lines.
Opacity	Select the <i>Opacity</i> value.

Spread Color Opacity	Specifies the level of color transparency/opacity for the Positive and Negative Spread colors. The value is from 0 to 255 with the default set to 128 .
Line Interpolation	Specifies the interpolation mode as Linear, Stepped, or Smooth.
Value Interpolation Na Value Gaps	Determines whether Na value (or missing) gaps are interpolated.
Value Line Color	Specifies the color of the value line data series.
Reference Line Color	Specifies the color of the reference line data series.
Positive Spread Color	Specifies the color when the spread between the value and reference is positive.
Negative Spread Color	Specifies the color when the spread between the value and reference is negative.

Sample 3. Single Series is enabled in the Line graph. In addition, in the Spread graph, the Value Column is set to **Spread**, and the Reference Column to **SpreadRef**.




Sample 4. Single Series is disabled in the Line graph. In addition, in the Spread graph, the Value Column is set to **Spread**, and the Reference Column to **SpreadRef**.



The last column in the breakdown (e.g., Auto Key) is used to divide the data into multiple series.

Bar




Setting	Description
Opacity	Select the <i>Opacity</i> value.
Bar Width	Specifies the width in pixels for each bar.
Show Borders	Determines whether borders are drawn around bars. These are only visible if the <i>Bar Width</i> is greater than 1 pixel.


Sample 5. Single Series is enabled in the Line graph. In addition, in the Bar graph, the Color is set to column **Id**, the Bar Width to **0.3**, and the Show Borders is enabled.




Sample 6. Single Series is disabled in the Line graph. In addition, in the Bar graph, the Color is set to column **Id**, the Bar Width to **0.3**, and the Show Borders is enabled.




Scatter



Setting	Description
Single Series	Determines whether to use all columns in the breakdown to create a single series or if one column should be used to divide the data into multiple series.
Size	Select the <u>Size</u> variable that will be used.




Sample 7. *Single Series* is enabled in the Line and Scatter graphs. In addition, in the Scatter graph, the *Shape* column is set to **Id** and the *Min Radius* to **3**.



Sample 8. Single Series is disabled in the Line and Scatter graphs. In addition, in the Scatter graph, the Shape and Color columns are set to **Id** and the Min Radius to **3**.




Price Band



Setting	Description
Single Series	Determines whether to use all columns in the breakdown to create a single series or if one column should be used to divide the data into multiple series.
Reference Column	The field that will be used as the reference line data series.
Line Width	Specifies the line width in pixels.
Opacity	Select the <i>Opacity</i> value.
Line Interpolation	Specifies whether the line is Stepped , Linear , or Smooth interpolation.

Value Interpolation Na Value Gaps Determines whether Na value (or missing) gaps are interpolated.


Stacked Bar or Grouped Bar



Additional settings include:

Setting	Description
Bar Width	Specifies the width in pixels of each bar. NOTE: This is overridden when a column is added in the <i>Size</i> variable. Consequently, the width of the bars will be based on the comparison of their size in relation to where they are located on the X axis.
Show Borders	Specifies whether a border is drawn around bars. These are only visible if the <i>Bar Width</i> is greater than 1 pixel.


Stack




Additional settings include:


Setting	Description
Single Series	Determines whether to use all columns in the breakdown to create a single series or if one column should be used to divide the data into multiple series.
Show Borders	Determines whether borders are drawn around stacks.

7. The text combination visualization includes an expanded axes pane, which includes specification of the properties for both the Left and Right Y axes.





Select or specify the following properties:




	NOTE: Value cannot be lower than 2. Power – Works according to the SIGN (MEASURE) *LOG10 (MAX (1, ABS (MEASURE))) formula. Works like the Log scale except it can handle negative values and every value between -1 and 1 is set to 0. For example, for values between -100 and 100, the axis will be: -100, -10, 0, 10, 100
Inverted	Determines whether the Y or Height axis is inverted.
Show Title	Displays an Axis Title label. When enabled, you can opt to enter a custom <i>Title</i> for the axis which will override the title of the visualization variable.
Axis Bar Thickness	The margin in pixels for the axis. If set to zero, the axis is removed.
Preferred Tick Space	The preferred space in pixels between the minor grid lines across the axis.
Minor Grid Line	How minor grid lines are drawn across the axis. Allowed values: None Dotted Dashed Solid
Major Grid Line	How major grid lines are drawn across the axis. Allowed values: None Dotted Dashed Solid
Tick Format	Set to From Variable to use the format string that is on the current variable displayed in the axis. Set to Metric Prefix to format the Tick labels in the numeric axes using the metric prefixes.
Tickmarks	Click to add and set tick marks. Tickmarks t Value 0 Label Enter the Value and the Label. Click to add more or to delete.
Range	The visible range for the Left and Right Y-axis variables can either be calculated dynamically (Dynamic Range) or set between predetermined limits by selecting Fixed Range . This enables the <i>Min</i> and <i>Max</i> text boxes and populates them with default values taken from the data set.
Independent Y-Axis Scaling	Determines whether to have each visualization Y-axis in a cross tab automatically scaled independent of the others.
Title and Format From	The title and format of the Left and Right Axes based on the selected fields.

Popup Titles in Text Combination Graph and Numeric Combination Graph


In the Text Combination Graph and Numeric Combination Graph, the first (top level) text column of *Items*, serves as an indexer for the x-axis instead of as a categoric breakdown column.

This is different from the Time Combination Graph, where the x-axis indexer is the time dimension, which is created through the time series transformation.

Therefore, in Text Combination and Numeric Combination, the *Details* popup will never show a category title if the *Items* setting has only one column.



Category titles will appear in the *Details* popup based on the second text column added to *Items* or added to *Rows* or *Columns*. When a second text column is added to *Items*, there is also a requirement to switch off **Single Series** on *Visuals* where applicable depending on the type of visualization (e.g., line).




Time Combination Settings

The Time Combination visualization operates in a similar way to the table. Instead of multiple input variables becoming different columns in a table, they become different layers in the time series combination visualization. So, unlike other visualizations, it can display a large number of time series variables, which can be rendered as: Line, Candle Stick, Bar, OHLC, Spread, Stack and Stacked Bar.

Steps:

1. The time combination settings pane is displayed after clicking the **Options** button or the *Visualization Title* (i.e., Time Combination):




2. Set the following property:

Setting	Description
Show Coordinates	Determines whether the graph coordinates (i.e., X-Y plots, or Date/Time-Y plots) on mouse over are displayed in the visualization. Tap the slider to turn it on.

3. Drag and drop time series columns from the Data Table pane to the Visuals variable drop area.


The column is added under the **Visualizations** tab list and by default, uses the <u>Line graph</u> and the Left Y-Axis alignment to the time combination visualization.



NOTE

The settings of the time combination visualization will depend on the time series visualization that will be added. Refer to the corresponding Settings section to define their properties.


4. The properties that you can set will depend on the timeseries visualization that you will add, but the general settings include:




Set or select the following properties:


Setting	Description
Title	Title of the visualization.
Visualization	If the visualization is incorrect, instead of deleting, you can just select another one in the <i>Visualization</i> drop-down list. The settings pane will be changed to display the corresponding properties of the selected visualization.
Aggregate	Aggregation method to be used. Default is Sum .
Format	The format that numbers will be displayed in. Panopticon uses the same formatting rules as MS Excel.
Divide By	 Select the <i>Divide By</i> value to divide a number: 1 1000 (by a thousand) 10000 1000000 (by a million) 1000000000 (by a billion)
Y Axis Alignment	The Y-Axis alignment: Left or Right.
Color	the <i>Color</i> variable that will be used for the column: None Shared Single Custom Single Column added to the <i>Column</i> variable
Column/Value Column	The time series column used for the visualization. If the dragged column is incorrect, instead of deleting, you can just select another column in the <i>Column/Value Column</i> drop-down list. NOTE: For the OHLC and Candle Stick Graph visualizations there are: Open Column, High Column, Low Column, and Close Column.


- 5. Visual members can be set to display any of the following visualizations:
 - Candle Stick or OHLC







Grouped, Stacked or Standard Bar








Line Graph




Scatter Plot




Setting	Description
Size	Select the Size variable that will be used.
Shape	Select the Shape value.
Opacity	Select the <i>Opacity</i> value.

Spread




Setting	Description
Reference Column	The field that will be used as the reference line data series.

• Price Band





Setting	Description
Reference Column	The field that will be used as the reference line data series.

• Order Book




6. The time combination visualization includes an expanded axes pane, which includes specification of the properties for both the Left and Right Y axes.





Select or specify the following properties:



	NOTE: Value cannot be lower than 2. Power – Works according to the SIGN (MEASURE) *LOG10 (MAX (1, ABS (MEASURE))) formula. Works like the Log scale except it can handle negative values and every value between -1 and 1 is set to 0. For example, for values between -100 and 100, the axis will be: -100, -10, 0, 10, 100
Inverted	Determines whether the Y or Height axis is inverted.
Show Title	Displays an Axis Title label. When enabled, you can opt to enter a custom <i>Title</i> for the axis which will override the title of the visualization variable.
Axis Bar Thickness	The margin in pixels for the axis. If set to zero, the axis is removed.
Preferred Tick Space	The preferred space in pixels between the minor grid lines across the axis.
Minor Grid Line	How minor grid lines are drawn across the axis. Allowed values: None Dotted Dashed Solid
Major Grid Line	How major grid lines are drawn across the axis. Allowed values: None Dotted Dashed Solid
Tick Format	Set to From Variable to use the format string that is on the current variable displayed in the axis. Set to Metric Prefix to format the Tick labels in the numeric axes using the metric prefixes.
Tickmarks	Click to add and set tick marks. Tickmarks to add and set tick marks. Value 0 to Label Enter the Value and the Label. Click to add more or to delete.
Range	The visible range for the Left and Right Y-axis variables can either be calculated dynamically (Dynamic Range) or set between predetermined limits by selecting Fixed Range . This enables the <i>Min</i> and <i>Max</i> text boxes and populates them with default values taken from the data set.
Independent Y-Axis Scaling	Determines whether to have each visualization Y-axis in a cross tab automatically scaled independent of the others.
Title and Format From	The title and format of the Left and Right Axes based on the selected fields.

LEGENDS

Four types of legend can be added to a dashboard:

Color (For Text & Numeric)

Icon
Shape
Timeseries

NOTE

One or more visualizations must be available on the dashboard that you can link to, before adding a Color, Icon, or Shape legend.

Adding a Color Legend

The Color Legend displays the color variables of the associated visualization. You can also set the orientation and style or enable the ability to do a filter or to display this part in the PDF output.

Steps:


1. After double-clicking or drawing a rectangle on the dashboard canvas, click Control on the Select Part



pane then click the Color Legend


Color Legend ico

The Color Legend Settings pane is displayed, and the Color Legend part is added on the dashboard canvas.




2. Select any of the available parent visualizations with color variable from the Linked Part drop-down list.

The color legend is connected to its parent visualization and the link between them is displayed. The color variables are retrieved from this visualization and displayed in the legend.



If the visualization can display multiple color variables, which is the case with the $\underline{\text{Table}}$ and $\underline{\text{Time Combination}}$, then the legend displays a drop list of possible variables to display.



There are two Color Legend styles:

Categorical

The categorical style color legend lists all text categories and colors used in the associated visualization for the selected source column.



Numeric

The numeric style color legend displays the color range used within the associated visualization for the selected numeric source column.



The style displayed depends on the active color variable of the linked visualization.


3. Set the color legend to **All Colors** or to a specific source column.




- 4. The style of a numeric color legend can be fixed to either:
 - Continuous



Discrete



- 5. For text color legends, you can select the following:
 - Orientation
 - Vertical




Horizontal




Alignment

The following examples are for *Vertical* orientation.

Left



Right




6. Tap the **Enable User Interaction** slider to turn it on and display the numeric color range slider.




Otherwise, the color legend is read-only, and the slider is hidden:



7. For text color legends (Categorical), you can enable filtering and allow selection of all items (Show Select All):



- 8. Tap the **Display in PDF** slider to turn it on and include this dashboard part in the PDF output.
- 9. To set the style of the Color Legend, click **Style**The page updates to display the *Style* pane.




10. Set the Font type, size, style (Bold and/or Italic).

For the part title, the font is set to Bold by default.


- 11. Click **Update Style** and select any of the following options:
 - Set current as default Save the changes and set it as the default.
 - Create custom style Save the changes and set it as a custom style.

The Style pane updates to display the Title control.



- Enter the custom style Title.
- If there are additional changes made, click Update Current Style in the Update Style drop-down.

The new custom style is added in the Workbook > Theme > Custom Styles list.



If published, the custom style configuration of the Color Legend will be added to the Global custom styles list and can be applied to other parts.

- Reset to default Revert to the original default settings.
- 12. Click the **Save** icon on the toolbar to save the changes.

Adding an Icon Legend

The Icon Legend displays the icon variables of the associated visualization.

Steps:


1. After double-clicking or drawing a rectangle on the dashboard canvas, click on the Select Part



pane then click the Icon Legend


Icon Legend icon.

The Icon Legend Settings pane is displayed, and the Icon Legend part is added on the dashboard canvas.




2. Select any of the available parent visualizations with icon variables from the Linked Part drop-down list.


The icon legend is connected to its parent visualization and the link between them is displayed. The icon variables are retrieved from this visualization and displayed in the legend.



To set the style of the Icon Legend, click Style
 The page updates to display the Style pane.




- 4. Set the Font type, size, style (Bold and/or Italic).
- Click Update Style
 and select any of the following options:
 - Set current as default Save the changes and set it as the default.
 - Create custom style Save the changes and set it as a custom style.
 The Style pane updates to display the Title control.



- Enter the custom style Title.
- If there are additional changes made, click **Update Current Style** in the *Update Style* drop-down.

The new custom style is added in the Workbook > Theme > Custom Styles list.



If published, the custom style configuration of the Icon Legend will be added to the Global custom styles list and can be applied to other parts.

- Reset to default Revert to the original default settings.
- 6. Click the **Save** icon on the toolbar to save the changes.

When saved, the Saved! notification is displayed.

Adding a Shape Legend

Shape Legend displays the shape variables of the associated visualization (Scatter Plot, Table, Time Combination, and Time series Scatter Plot). You can also set the orientation or enable the ability to do a filter or to display this part in the PDF output.

1. After double-clicking or drawing a rectangle on the dashboard canvas, click




on the Select Part



pane then click the Shape Legend

Shape Legend icon.

The Shape Legend Settings pane is displayed, and the Shape Legend part is added on the dashboard canvas.



- 2. Select the legend Mode:
 - Runtime Selectable


This mode is only applicable when connecting to a time combination graph.

Single Variable


Sets the shape legend to a specific source column of a parent visualization.

3. Select any of the available parent visualizations with shape variables from the Linked Part drop-down list.

The shape legend is connected to its parent visualization and the link between them is displayed. The shape variables are retrieved from this visualization and displayed in the legend.



For the **Single Variable** mode, the *Show Legend For* field is automatically filled with the column of the shape variable in the parent visualization.



For the **Runtime Selectable** mode, this automatically maps all the shapes of the time combination graph to the legend.


- 4. For test shape legends, you can display them either:
 - Vertical

	Industry		
	Basic Materials		
	Consumer Goods	S	
	Consumer Service	es	
	Financials		
	▼ Health Care		
	○ Industrials		
	Oil & Gas		
	Technology		
		ions	
	∪tilities		
	 Horizontal 		
	Industry	Consumos Conside	A Consumor Considera
	Basic Materials	Consumer Goods	Consumer Services
	Financials	▼ Health Care	○ Industrials
	Oil & Gas		△ Telecommunications
	∀ Utilities		
5.	Enable filtering and allow se	election of all items (Show	Select All):
5.	Enable filtering and allow se	election of all items (Show	Select All):
5.	Enable Filtering	election of all items (Show	Select All):
5.		election of all items (Show	Select All):
5.	Enable Filtering Show Select All	election of all items (Show	Select All):
5.	Enable Filtering Show Select All Industry	election of all items (Show	Select All):
5.	Enable Filtering Show Select All Industry (Select All)	election of all items (<i>Show</i>	Select All):
5.	Show Select All Industry (Select All) Basic Materials		Select All):
5.	Enable Filtering Show Select All Industry (Select All) Basic Materials Consumer Goods		Select All):
5.	Enable Filtering Show Select All Industry ✓ (Select All) ✓ Basic Materials ✓ Consumer Goods ✓ Consumer Service		Select All):
5.	Enable Filtering Show Select All Industry ✓ (Select All) ✓ Basic Materials ✓ Consumer Goods ✓ Consumer Service ✓ Financials		Select All):
5.	Enable Filtering Show Select All Industry ✓ (Select All) ✓		Select All):
5.	Enable Filtering Show Select All Industry ✓ (Select All) ✓ ■ Basic Materials ✓ ■ Consumer Goods ✓ ◆ Consumer Service ✓ ▲ Financials ✓ ▼ Health Care ✓ Industrials		Select All):
5.	Enable Filtering Show Select All Industry ✓ (Select All) ✓ ■ Basic Materials ✓ ■ Consumer Goods ✓ ◆ Consumer Service ✓ ▲ Financials ✓ ■ Health Care ✓ ○ Industrials ✓ □ Oil & Gas		Select All):
5.	Enable Filtering Show Select All Industry ✓ (Select All) ✓ ■ Basic Materials ✓ ■ Consumer Goods ✓ ♠ Consumer Service ✓ ▲ Financials ✓ ■ Industrials ✓ □ Oil & Gas ✓ ← Technology	25	Select All):
5.	Enable Filtering Show Select All Industry ✓ (Select All) ✓ ■ Basic Materials ✓ ■ Consumer Goods ✓ ◆ Consumer Service ✓ ■ Financials ✓ Industrials ✓ □ Oil & Gas ✓ ◆ Technology ✓ Telecommunication	25	Select All):
5.	Enable Filtering Show Select All Industry ✓ (Select All) ✓ ■ Basic Materials ✓ ■ Consumer Goods ✓ ♠ Consumer Service ✓ ▲ Financials ✓ ■ Industrials ✓ □ Oil & Gas ✓ ← Technology	25	Select All):

ॐ Style

7. To set the style of the Shape Legend, click **Style**

The page updates to display the Style pane.




8. Set the Font type, size, style (**Bold** and/or **Italic**).

For the part title, the font is set to **Bold** by default.


- 9. Click **Update Style** and select any of the following options:
 - Set current as default Save the changes and set it as the default.
 - Create custom style Save the changes and set it as a custom style.

The Style pane updates to display the Title control.



- Enter the custom style Title.
- If there are additional changes made, click **Update Current Style** in the *Update Style* drop-down.

The new custom style is added in the Workbook > Theme > Custom Styles list.



If published, the custom style configuration of the Shape Legend will be added to the Global custom styles list and can be applied to other parts.

Reset to default – Revert to the original default settings.



Adding a Series Legend


The Series Legend displays configured reference lines, their associated labels, and visual members.

Steps:

1. After double-clicking or drawing a rectangle on the dashboard canvas, click on the Select Part


pane then click the $\textbf{Series Legend} \quad \text{Series Legend} \quad \text{icon.}$


The Series Legend Settings pane is displayed, and the Series Legend part is added on the dashboard canvas.





2. Select any of the available parent visualizations from the *Linked Part* drop-down list.

The series legend is connected to its parent visualization and the link between them is displayed. The reference line listing from this visualization is retrieved and the constituent reference lines in a vertical column along with their associated levels are displayed.










Setting the *Custom Single* color for the visual members helps display the *Color Legend* for layers in the Combination Graph, in cases where the <u>Color</u> variable is not used.

Furthermore, the SMA10, SMA5, and SMA20 are the reference lines added under the BBU20 visual member.




On the Series Legend Settings pane, tapping the Enable User Interaction slider enables checkboxes of the
visuals and reference lines and users can check or uncheck them to filter which ones to display in the parent
visualization.

For example, if BBU20 is unchecked:




The visualization and reference lines for BBU20 will not be displayed.




If Volume is also unchecked:




The visualization for **Volume** will also not be displayed.



4. Tapping the Show Visual Members slider allows users to display visual members in the series legend.
Disabling Show Visual Members hides the visual members in the series legend. However, the reference lines will still be displayed.



- 5. Tap the **Display in PDF** slider to include this dashboard part in the PDF output.
- 6. To set the style of the Series Legend, click **Style**The page updates to display the *Style* pane.




7. Set the Font type, size, style (Bold and/or Italic).

- + Update Style +
- 8. Click **Update Style**

and select any of the following options:


- Set current as default Save the changes and set it as the default.
- Create custom style Save the changes and set it as a custom style.

The Style pane updates to display the Title control.



- Enter the custom style Title.
- If there are additional changes made, click **Update Current Style** in the *Update Style* drop-down.

The new custom style is added in the Workbook > Theme > Custom Styles list.



If published, the custom style configuration of the Series Legend will be added to the Global custom styles list and can be applied to other parts.

- Reset to default Revert to the original default settings.
- 9. Click the **Save** icon on the toolbar to save the changes.

When saved, the Saved! notification is displayed.

FILTERS

Filters allow to highlight outliers, patterns, and trends in the data. Filters must be populated with data columns in order for them to function.

Text, time, and numeric filtering can be applied to visualizations in a dashboard.

Filtering across a time window is another type of filter wherein, only the specified window of time is displayed in a time-series visualization. Time window filters are local to a dashboard, and only one filter can be present per dashboard.

Additionally, visualizations can be configured through their settings to ignore defined filters.

NOTE

One or more visualizations must be available on the dashboard, before adding filters on the dashboard.

Adding a Filter Box

Dashboards specific filters can be applied by adding and populating a filter box which is a container for numeric and categorical (text) filters.

You can add multiple filter boxes to a single dashboard.


Steps:

1. After double-clicking or drawing a rectangle on the dashboard canvas, click on the Select Part pane then click




the Filter Box Filter Box icon.

The Filter Box Settings pane is displayed, and the Filter Box part is added on the dashboard canvas.




- 2. Enter the filter box *Title* then click ...
- 3. Drag and drop columns (text, numeric, time, or time series) from the Data Table pane to this area:




The columns are added under the *Filter Box* columns list and the filter box is populated by the default <u>filter mode</u> <u>type</u> of the added columns:

- Multiple Selection for text columns
- Numeric Range for numeric and timeseries columns
- Date/Time Range for time columns



- 4. The *Orientation* of the filter box can either be:
 - Vertical (Default)



Horizontal

The filter width can be configured in two ways:

Dynamic

The filters will take the available space.



Fixed

The input Width will be applied to available filters. Default is 200.

This is an example for width that is set to 180.




- 5. You can also configure the filter box to:
 - Reset Button Visible

Tap the slider to turn it on and display a reset button at the bottom of the filter box.



Search Field Visible


Tap the slider to turn it on and display a search field, to limit the number of displayed filters at the bottom of the filter box.




Display in PDF

Tap the slider to turn it on and include the filter box in the PDF output.


6. To set the style of the Filter Box, click Style



The page updates to display the Style pane.




- 7. To modify the **Foreground** or **Background** color of the part and title:
 - click the corresponding *Color* box to display the *Color* dialog to:




- select the color, or
- click to enter the values


for RGB



for HSL



for the Hex color code




• or enter the Hex color code




- 8. Set the Font type, size, style (**Bold** and/or **Italic**).
 - The filter box title is set to **Bold** by default.
- 9. Set the filter box title's Alignment. Left, Middle, or Right.
- 10. Click **Update Style** and select any of the following options:
 - Set current as default Save the changes and set it as the default.
 - Create custom style Save the changes and set it as a custom style.

The Style pane updates to display the Title control.



- Enter the custom style Title.
- If there are additional changes made, click **Update Current Style** in the *Update Style* drop-down.

The new custom style is added in the Workbook > Theme > Custom Styles list.




If published, the custom style configuration of the filter box will be added to the Global custom styles list and can be applied to other parts.

• Reset to default – Revert to the original default settings.


When a filter is applied, ∇ filter icons appear to the right of the filter column title and on the toolbar of the dashboard. Clicking ∇ will remove the filter.

Also, **Show Active Filters** icon displays on the toolbar. This allows <u>viewing of all the active filters</u> on the dashboard and its visualizations.



9. Click the **Save** icon on the toolbar to save the changes.

When saved, the Saved! notification is displayed.




Filter Settings


The filter settings will depend on the column's type and filter mode.


Steps:


Click on a filter column name under the Filter Box columns list.
 The filter properties are displayed that you can adjust.



- 2. By default, the *Title* is the column name added to the filter box. You can opt to modify this value.
- 3. You can opt to select another Data Table from the drop-down list and then select the filter Column.
- 4. The filter properties depend on the column type.
 - For text columns:








The default *Mode* type depends on the column type and the number of values. Refer to <u>Filter Mode Types</u> for more information.

For text columns with <u>Free text</u> filter mode type, select the *Default Wildcard*:

Substring

The wildcard character is a substring to search for certain values in the *Free Text* filter box.


For example, entering **Bank** displays values (maximum of 10) that contain Bank.



Prefix

The wildcard character is a substring to search for certain values in the *Free Text* filter box.

For example, entering **Bank** displays values (maximum of 10) that begin with Bank.



None

The predicate used for filtering:


- o data on the dashboard will not have any wildcards automatically appended.
- o items in the suggestion list uses the **Prefix** mode wildcards (see previous example).


It is still possible to manually add wildcards into the search string.

Set the Suggestion List Max Size with the custom limit on how many options/suggestions should be, at the most, loaded and presented on the drop-down. Default is 10.


Enter a description or useful information about the filter into the *Tooltip* box.

• For numeric and timeseries columns:





- Select the *Divide By* value to divide a number:
 - 0 1
 - o 1000 (by a thousand)
 - 0 10000
 - o 1000000 (by a million)
 - o 1000000000 (by a billion)
- Specify the <u>Format</u> that numbers will be displayed in. Panopticon uses the same formatting rules as Excel.
- For Date/Time columns:



Specify the Date/Time Format.

- 5. Tap the **Append Separator** slider to add a separator after a column filter.
- 6. Click the **Save** icon on the toolbar to save the changes.


When saved, the Saved! notification is displayed.

Deleting Column Filters


You can delete any defined filters.

Steps:

1. Hover on a filter that you want to delete.




3. Click . The filter is deleted.



Filter Mode Types

Categorical filters can be one of the following types:



- Free Text Entry
- Multiple Selection List
- Multiple Select Drop Down List
- □ Single Select Drop Down List
- □ Single Selection List
- □ Include/Exclude List


In addition, there are also the following modes:

- Numeric Range
- Date/Time Range


In the Action Dropdown, an additional selection mode named Include List is available.

Free Text


Free Text is the default selection mode when the text filter column has more than 30 values.




In the dashboard, this mode shows a free text entry box.



When entering a value, matches are displayed allowing you to pick one from the list. You can do so by double-clicking on it.




For Free Text with **Substring** default wildcard, entering **Bank** for this example displays values in the suggestion list that contain **Bank**.



For Free Text with **Prefix** default wildcard, entering **Bank** for this example displays values in the suggestion list that begin with **Bank**.




For *Free Text* with **None** default wildcard, entering **Bank** for this example displays values in the suggestion list that begin with **Bank**. Also, there are no automatically appended wildcards on the dashboard.



The number of options/suggestions on the drop-down will depend on the Suggestion List Max Size. Default is 10.

Multiple Selection


Multiple Selection is the default selection mode when the text filter column has 0 to 15 values.




In the dashboard, this mode shows a list of distinct items that are alphabetically sorted. Multiple items may be selected from the checkbox list. By default, the **Show Select All** option is enabled.




You can also opt to tap the **Show Filter Text Box** slider to turn it on.



Uncheck the **Select All** box then enter a particular column into the filter text box.




Check the box to apply the fillter to the visualizations in the dashboard.



You can also enter one or more characters into the filter text box. The suggested list of columns that matched the entries will be displayed.




Check the boxes to apply the fillter to the visualizations in the dashboard.



Multiple Selection Drop Down List

Multiple Select Drop Down List is the default selection mode when the text filter column has 16 to 30 values.



In the dashboard, this mode shows a list of distinct items that are alphabetically sorted when expanded. By default, the **Select All** option is enabled.



Multiple items may be selected. When collapsed, the number of selected items are displayed.

Filters




You can also opt to tap the **Show Filter Text Box** slider to turn it on.

Uncheck the **Select All** box then enter a particular column into the filter text box.



Check the box to apply the filter to the visualizations in the dashboard.




You can also enter one or more characters into the filter text box. The suggested list of columns that matched the entries will be displayed.




Check the boxes to apply the filter to the visualizations in the dashboard.





Single Selection Drop Down List




In the dashboard, this mode shows a radio button drop down list of distinct items that are alphabetically sorted when expanded. By default, the **Select All** option is enabled.



Only a single item or all items may be selected. When collapsed, it shows the summary text or the single selected item. For the example below, the region selected is **Europe**.



Single Selection




In the dashboard, this mode shows a radio button list of distinct items that are alphabetically sorted. Only a single item or all items may be selected. By default, the **Select All** option is enabled.

Industry


- (Select All)
- Basic Materials
- Oconsumer Goods
- Oconsumer Services
- Financials
- Health Care
- Industrials
- Oil & Gas
- Technology
- Telecommunications
- Utilities

Include/Exclude List




This filter mode allows to include or exclude a set of values from a given column. It consists of a *Free Text* filter used for finding values to include or exclude and a list of values that are currently used in the filter.


Set the Suggestion List Max Size with the custom limit on how many options/suggestions should be, at the most, loaded and presented on the drop-down. Default is 10.




When entering a value, matches are displayed allowing you to pick one from the list.



Name




Name



The selected column value is displayed under the **Include/Exclude** button.




For the example above, the column value is included in the filter.



Click to delete a column value from the *Include/Exclude* list.

Include List



The **Include List** selection mode is a combination of the free text and multiple selection modes. In the dashboard, this mode displays as:




This selection mode supports:

- On demand searching of values and selecting several values. It is useful in cases where there are too many values in the configured column to use a multiple selection mode.
- □ Selection of all items if there is a configured value for Select All.



When selecting the select all item in the Include List, the parameter will be set to the configured select all value.




Clear


The primary use case of the Include List selection mode is to handle columns with large amounts of values. To avoid having to fetch and set the parameter to every value in the column when selecting all items, the select all value should be configured such that the parameterized query returns all items.

For other include list options, see filter include/exclude.


Numeric Range



In the dashboard, this mode shows the distribution plus minimum and maximum limits.



Date Time Range




In the dashboard, this mode shows the distribution of a Date/Time field, plus the minimum and maximum limits.

Filters



Modifying the Filter Box Layout

The layout of the filter box can be modified by right-clicking to display its context menu:



Show Active	
Displays all of the active filters.	
To describe	∇
Industry	Y
(Select All)	
Consumer Goods	
Consumer Services	
Financials	
✓ Health Care	
Industrials	
Oil & Gas	
✓ Technology	
Telecommunications	
✓ Utilities	
Exchange	
Mcap(USD)	Y
57,236,906,640.39	336,525,036,369.00
Collapse All	
Collapse of all the filters.	
Industry	Y
Exchange	
Mcap(USD)	7


Expand All

Expand all of the filters.

Industry	\overline{V}
(Select All)	
✓ Basic Materials	
Consumer Goods	
Consumer Services	
Financials	
✓ Health Care	
Industrials	
Oil & Gas	
✓ Technology	
Telecommunications	
✓ Utilities	
Exchange	
27 of 27 values	▼
Mcap(USD)	\forall
0	
57,236,906,640.39	336,525,036,369.00

Reset All

Reset all of the filters.



In all cases, clicking on a specific filter, allows it to swap from expanded to collapsed.

Adding a Time Filter Box

Time-series visualizations can be filtered to show a specified time window, through the *Time Filter* box. Only one can be added per dashboard.

Steps:


1. After double-clicking or drawing a rectangle on the dashboard canvas, click



on the Select Part

pane then click the **Time Filter Box**


The Time Filter Box Settings pane is displayed, and the Time Filter Box part is added on the dashboard canvas.



Select a Data Table from the drop-down list then select the time series filter Column.

The Time Filter Box now displays:


- Editable Minimum Date/Time
- Editable Maximum Date/Time
- Handles for quick filtering of the time period
- Time Slice Selection (Snapshot Time)
- Line Graph representation of the time series column



- 3. Select the Aggregate type.
 - If you set the aggregation method to **Cumulative Sum** or **Cumulative Sum by Max**, the *Sort By* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the sorting column for the aggregate.




Cumulative Sum By Max is, in practice, Cumulative Sum with a setting to use Max as the sort by aggregation.




• If you set the aggregation method to **Intercept** or **Slope**, the Y Variable drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the Y-axis variable column for the aggregate.




If you set the aggregation method to **Percent of Parent Reference**, **Percent of Total Reference**, or **Ratio of Sums**, the *Reference Column* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the reference column for the aggregate.




• If you set the aggregation method to **Percent of Total Change**, the *Previous Values Column* drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the previous column for the aggregate.



• If you set the aggregation method to **Percentile**, the *Percentile* field is displayed. Specify the value that can be used to calculate the value of the selected percentile.



If you set the aggregation method to Weighted Harmonic Mean, Weighted Mean, Weighted Population Variance, Weighted Stdev, Weighted Stdevp, Weighted Sum, or Weighted Variance, the Weight Column drop-down list is enabled and displays a list of numeric data columns in the selected data table that can be used as the weight column for the aggregate.



- 4. The Format field lets you specify the format that Date/Time will be displayed in.
- 5. Proceed to setting the time filter box settings:

Setting	Description	
Show Handles	Determines whether handles are displayed. Enabled by default.	
Snapshot Label Always Visible	Determines whether to always display the snapshot label. Enabled by default.	
Show Backward & Forward Button	Determines whether the Backward and Forward buttons are displayed to move through time slices. 2008-01-02 2008-01-02 2009-03-06	
Show Play/Pause Button	Determines whether the Play or Pause button is displayed and adds the ability to automatically play through all the time slices. It subsequently automatically moves through each time slice until it reaches the end of the time window, causing the playback to reset.	
Play Time	How long the play time will run if the Pay Mode is Ticks . Default is 30 .	
Play Mode	Determines whether the play mode is either Time or Ticks Setting to Time will playback the time slices as quickly as possible Setting to Ticks will playback a time slice based on the set <i>Play Time</i> For example, there are 8 time slices in the Time Series visualization, setting the <i>Play Time</i> to 16 will playback a time slice per 2 seconds (i.e., will move the snapshot one step per 2 seconds).	
Skip Empty Values	Determines whether to skip empty values.	
Display in PDF	Determines whether to include the time filter box in the PDF output.	
Left Margin	The margin area on the left side of the time filter box.	
Right Margin	The margin area on the right side of the time filter box.	

6. Click the Save icon on the toolbar to save the changes.


When saved, the notification is displayed.

GLOBAL FILTERING


The Global Filters section can be displayed in the workbook layout. Filters added to this section will be applied across all dashboards in a workbook.

Steps:

On the Dashboard and Workbook Settings pane, click the Workbook tab then the The Global Filter Settings pane is displayed.




- 2. Select the Global Filters Alignment: Left or Right.
- 3. Tap the Reset Button Visible slider to turn it on.
- 4. Tap the Search Field Visible slider to turn it on.
- 5. Drag and drop columns (text, numeric, time, or time series) from the *Data Table* pane to the **Global Filter** pill or drop area:




The columns are added under the *Filter Box* columns list and the *Global Filter* box is displayed and populated by the default <u>filter mode type</u> of the added columns:

- Multiple Selection for text columns
- Numeric Range for numeric and timeseries columns
- Date/Time Range for time columns




You may modify the settings of the dragged and dropped columns.


6. For the Text Filter, click to expand.




- 7. Modify any of the *Title*, *Data Table*, *Column*, and *Mode* values.
- 8. For the *Numeric Filter*, click to expand.



- 9. Modify any of the Title, Data Table, Column, Divide By, or Format values.
- 10. For the Time Column Filter, click to expand.



- 11. Modify any of the Title, Data Table, Column, or Date/Time Format values.
- 12. For any of the global filter types, tap the **Append Separator** slider to add a separator.



Deleting Global Filters

Click on a global filter instance under the Global Filter Settings pane and then click

Viewing Active Filters

Information on active filters applied on the dashboard and its parts can be viewed.


These filters can be done through:

- Filter controls
- Global filter
- Visualization filter

Steps:

Click the Show Active Filters icon on the toolbar.

All of the predicates of the active filters are displayed. For this complex there are four active.



Hover on any predicate to display its details.

Predicate 1:



Predicate 2:

▼ Super Region in (North, West)

Full Predicate: Super Region in (North, West)
Applies to: visualization.HorizontalBarGraph1
Generated by: TextFilter for Super Region in GlobalFilters

Predicate 3:

∀ Mcap(USD) >= 57,853,575,636.27

Full Predicate: Mcap(USD) >= 57,853,575,636.27

Applies to: visualization.CirclePack1

Generated by: NumericFilter for Mcap(USD) in GlobalFilters

Predicate 4:

🔻 Industry in (Basic Materials, Consumer Goods, Consumer Services, Financials, Health Care, Oil & Gas, Technology, Telecommunications)

Full Predicate: Industry in (Basic Materials, Consumer Goods, Consumer Services, Financials, Health Care, Oil & Gas, Technology, Telecommunications)
Applies to: visualization.CirclePack1
Generated by: TextFilter for Industry in Filters

Property	Description
Full Predicate	Predicate details.
Applies To	Parts in the dashboard where the predicate is applied.
Generated By	Source of the predicate which include the filter column data type in the filter control or global filter.

3. To clear any predicate in the list, click \mathbb{Y} .

ACTIONS

Actions allow Panopticon workbooks to be more interactive:


- ☐ Link information in dashboards to external systems
- Use Navigation Actions to pre-filter dashboards
- Open web pages contextually through URL Actions
- □ Execute JavaScript functions in context using Script Actions

Perform all of the above through the Action buttons

Actions use parameters to pass selected text values to external applications, to JavaScript functions and to other dashboards.

All methods provide the ability to view a summary data set, select particular items of interest and then jump to another data set focused on these particular items. This focused data set may be presented through another tab within the workbook (Navigation Action) or through an external system (URL Actions & Script Actions).

Actions are exposed to the user through the right-click context menu, with the **Action** icon to the left of the Action name.



Within Panopticon, the focused data set is achieved through the use of parameters in the data set. See <u>Adding Data Table Parameters</u> section for more details.

Parameters values, must be text and are specified through:


- Default values on the creation of the parameter in the data table
- Default values on the creation of the parameter on the <u>dashboard</u> pane
- □ Values specified as a result of right-clicking on an item and executing an action
- Values specified externally, when a workbook is accessed via the web browser, and the parent web page includes the specified values as inputs
- □ In the specific case of the parameter **_user_id**, the authenticated username is retrieved.
- □ In the other special case for the parameters \$TimeWindowStart, \$TimeWindowEnd, and \$Snapshot
- Other special cases for parameters used for zooming allow for \$XAxisValueMin, \$XAxisValueMax, \$YAxisValueMin, and \$YAxisValueMax

Typically, actions are created once the workbook design has largely been completed, with visualizations added to each **Dashboard** (tab), some being open to all data, and some being parameterized, visualizing data based on the default parameter values.

Interactive Parameters


Parameters are normally supplied from selected columns of the parent data table, or from action controls.

Additionally, actions can be specified to support interactive parameters that are entered when the action is executed. In this case for a parameter the *Value Source* list box is set to **\$Interactive**.



Actions can be constructed with combinations of data source and interactive parameters.

Typically, interactive parameters are used to pass data back to data repositories or external systems.



When interactive parameters are selected, the Input Validation and Error Message boxes are enabled.

- □ The *Input Validation* can be any regular expression (e.g., "A-Z{3}").
- The parameter will not be updated unless it passes the validation. Enter an Error Message to help in defining a better input to match the regular expression (e.g., "Please use a 3-letter code.")

When an action is executed which required an interactive parameter, an associated dialog box will be displayed.




This lists all parameters associated with the action. For the example above, data sourced parameters are listed completed with values. Interactive parameters are listed with text boxes for data entry.

The action is then executed when the **OK** button is clicked. This button is enabled when all interactive parameters have been completed.


If the **Cancel** button is clicked, the action is cancelled.

Time Parameters

Parameters are normally supplied from selected columns of the parent data table, or from action controls:




	Time parameters values can al available time parameters.	so be supplied through usir	ng the Time Window filter and selecting one of the three
	□ \$Snapshot		
	□ \$TimeWindowStart		
	□ \$TimeWindowEnd		
	When one of the time window f executed.	Iters is moved, an action a	ssociated with one of these time parameters will be
20	2008/01/02 2009/03	/06 2009/03/06	
ř			
A fi	A final time parameter can also	be specified. This is the Fe	ocusTime.
Foo	FocusTime is set when executi	ng an action from a time se	ries visualization and highlighting a particular time slice.
	07/2008		
Zo	Zoom Bound Parameters		
	Parameters can also be supplie zoom parameters:	ed through the visualization	zoom bounding box, by selecting one of the four available
	□ \$XAxisValueMin		
	□ \$XAxisValueMax		
	□ \$YAxisValueMin		
	□ \$YAxisValueMax		



These can be used to resample data at increased granularity, by requerying the data source passing the new zoomed range as bounding conditions.

Constant Parameters

Actions support specifying constant (non data-driven) values for parameters inside the action. Set the *Value Source* of the parameter to **\$Constant** and specify any text value.



The constant value will then always be used for that parameter whenever the action is executed.

In the above example, whenever Select Stock action is executed, the Ticker parameter will receive the value LOW.

Action Scope

Actions can either be specific to a single dashboard or defined for all dashboards in a workbook.

For the dashboards in a workbook, the following actions can be defined:

- Navigation Action
- □ URL Action
- Script Action
- Data Update Action

While for a single dashboard, you can define any of the following actions:

- Numeric Action Slider
- Numeric Range Action Slider
- Action Button
- Action Date Picker
- Action Date Range Picker
- Action Drop Down
- Action Form
- Action Text Box

NOTE

Any actions defined with workbook scope will be included on the listing of dashboard-specific actions.

Each of these actions are discussed in detail below.


Adding Navigation Actions

Navigation Actions let you pass parameters from one dashboard to another in the same workbook.

Steps:

1. On the Dashboard and Workbook Settings pane, click the Workbook tab.

The *Actions* pane is displayed. Initially, there are no actions defined for the workbook and the selected *Dashboard Scope* is **All**.




- 2. Select the *Dashboard Scope* where you will define the dashboard scope data parameters that will be passed to the target dashboard: **All** or **Current**.
- 3. Select the Source Data Table from the drop-down list.
- 4. Click the button then select **Navigation Action** in the drop-down list.




The new navigation action is added under the selected Dashboard Scope in the Actions list.


For example, if **Current** is the selected dashboard scope and the source data table is **Equity Portfolio**, then it will be displayed as:



However, if no source data table is selected, then the first one in the *Data Table* pane (i.e., StocksAnalysis) is the default associated to the new navigation action.




5. Click the new navigation action instance to expand and display the properties that you can define.




6. Enter or select the following properties:


Setting	Description
Name	The name of the navigation action and then click .
Dashboard Scope	The dashboard where you will define the dashboard scope data parameters that will be passed to the target dashboard. Can either be [All Dashboard] or the current dashboard.
Data Table	The source data table. This will eventually be displayed above the navigation action instance.
Target Dashboard	The dashboard where you want to pass the parameters to.
Parameters Name	The available parameters of the selected target dashboard.




7. Click the **Save** icon on the toolbar to save the changes.



Clicking the All Dashboard Scope, the new navigation action is available.



If the Dashboard Scope is [All Dashboard], the new navigation action will be displayed as:




Adding URL Actions

URL Actions lets you access a web page or file or even point to other resources on the web such as database queries and command output. You can also pass parameters to the URL.

Steps:

1. On the Dashboard and Workbook Settings pane, click the Workbook tab.


The *Actions* pane is displayed. Initially, there are no actions defined for the workbook and the selected *Dashboard Scope* is **All**.




- 2. Select the *Dashboard Scope* where you will define the dashboard scope data parameters that will be passed to the target dashboard: **All** or **Current**.
- 3. Select the Source Data Table from the drop-down list.
- 4. Click the button then select **URL Action** in the drop-down list.




The new URL action is added under the selected *Dashboard Scope* in the *Actions* list. For example, if **Current** is the selected dashboard scope and the source data table is **Equity Portfolio**, then it will be displayed as:



However, if no source data table is selected, then the first one in the *Data Table* pane (i.e., StocksAnalysis) is the default associated to the new URL action.



5. Click the new URL action instance to expand and display the properties that you can define.



6. Enter or select the following properties:


Setting	Description
Name	The name of the URL action and then click
Dashboard Scope	The dashboard where you will define the dashboard scope data parameters that will be passed to the target dashboard. Can either be [All Dashboard] or the current dashboard.
Data Table	The source data table. This will eventually be displayed above the URL action instance.
URL	The parameterized URL and then click The parameters are written within curly brackets, {ParameterName}. For actions allowing multiple value input, you can optionally specify a value separator within the curly brackets where you put the parameter name. The syntax is as follows: {ParameterName: Separator}

For example: {Company:+} Default separator is semicolon. Specifying for example a plus sign allows you to do multi search term searches on Google, for example. At execution, the parameter will be replaced with real field values associated with the selected visualization node. The easiest way to create parameterized URLs is to open an example web page and copy the URL. As an example, Yahoo Finance Key Statistics for Microsoft has the following web address: http://finance.yahoo.com/q/ks?s=MSFT If a parameter called Ticker has been set up in the data table, you can generate the URL by removing **MSFT** and replacing it with **{Ticker}**: http://finance.yahoo.com/g/ks?s={Ticker} **Target** The target area of the page where the output URL will be displayed. Available options are: blank _top _parent self


7. Click the added.

+ New Parameter

button to add parameters to the output URL. A new parameter instance is $% \left(1\right) =\left(1\right) \left(1\right) \left($




8. Click on the parameter instance to expand and define its properties.



For each parameter added, set or select the following properties:

Setting	Description
Name	Name of the URL action parameter and then click .
Value Source	Column from the data source table that will supply the contextual value. The value of this selected column for rows under the selected visualization node will be passed as the parameter values to the target URL.
Multiple Values	This passes multiple values for the parameter to the target area. Tap the slider to turn on. The <i>Value Separator</i> field displays.




You can delete any of the added parameters by clicking the corresponding **Delete** button.


- 9. Repeat step 7 to add more parameters.
- 10. Click the **Save** icon on the toolbar to save the changes.

When saved, the Saved! notification is displayed.

Clicking the All Dashboard Scope, the new URL action is available.



If the Dashboard Scope is [All Dashboard], the new URL action will be displayed as:




Adding Script Actions

Script actions allow execution of a defined JavaScript.

Steps:

1. On the Dashboard and Workbook Settings pane, click the Workbook tab.


The *Actions* pane is displayed. Initially, there are no actions defined for the workbook and the selected *Dashboard Scope* is **All**.




- 2. Select the *Dashboard Scope* where you will define the dashboard scope data parameters that will be passed to the target dashboard: **All** or **Current**.
- 3. Select the Source Data Table from the drop-down list.
- 4. Click the New Action button then select Script Action in the drop-down list.




The new script action is added under the selected *Dashboard Scope* in the *Actions* list. For example, if **Current** is the selected dashboard scope and the source data table is **Equity Portfolio**, then it will be displayed as:



However, if no source data table is selected, then the first one in the *Data Table* pane (i.e., StocksAnalysis) is the default associated to the new script action.



5. Click the new script instance to expand and display the properties that you can define.




6. Enter or select the following properties:

Setting	Description	
Name	The name of the script action and then click $^{ ilde{ ity}}}}}}}}}}}}}}}}}}}}}}}}}}}}}}}}}}}}$	
Dashboard Scope	The dashboard where you will define the dashboard scope data parameters that will be passed to the target dashboard. Can either be [All Dashboard] or the current dashboard.	
Data Table	The source data table. This will eventually be displayed above the script action instance.	
Script	The parameterized script. The parameters are written within curly brackets, {ParameterName}. For script actions allowing multiple value input, you can optionally specify a value separator within the curly brackets where you put the parameter name. The syntax is as follows: {ParameterName:Separator} For example: {Company: } Default separator is comma. At execution, the parameter will be replaced with real field values associated with the selected visualization node. NOTE: The entered JavaScript should not include constructs that utilize curly brackets, as these are reserved for the processing of parameters.	


7. Click the added.



button to add parameters to the output script. A new parameter instance is




8. Click on the parameter instance to expand and define its properties.



For each parameter added, set or select the following properties:

Setting	Description		
Name	Name of the script action parameter and then click .		
Value Source	Column from the data source table that will supply the contextual value. The value of this selected column for rows under the selected visualization node will be passed as the parameter values to the target URL.		
Multiple Values	This passes multiple values for the parameter to the target area. Tap the slider to turn on. The <i>Value Separator</i> field displays.		
	Multiple Values		
	Value Separator ,		
	Specify the value separator to be used.		




You can delete any of the added parameters by clicking the corresponding **Delete** button


- 9. Repeat step 7 to add more parameters.
- 10. Click the **Save** icon on the toolbar to save the changes.

When saved, the Saved! notification is displayed.

Clicking the All Dashboard Scope, the new script action is available.



If the Dashboard Scope is [All Dashboard], the new script action will be displayed as:




Adding Data Update Actions

Data update action lets you update data (typically in a database) by passing parameters into a data query.

Steps:

1. On the Dashboard and Workbook Settings pane, click the Workbook tab.


The *Actions* pane is displayed. Initially, there are no actions defined for the workbook and the selected *Dashboard Scope* is **All**.




- 2. Select the *Dashboard Scope* where you will define the dashboard scope data parameters that will be passed to the target dashboard: **All** or **Current**.
- 3. Select the Source Data Table from the drop-down list.
- 4. Click the New Action button then select Data Update Action in the drop-down list.




The new data update action is added under the selected *Dashboard Scope* in the *Actions* list. For example, if **Current** is the selected dashboard scope and the source data table is **Equity Portfolio**, then it will be displayed as:



However, if no source data table is selected, then the first one in the *Data Table* pane (i.e., StocksAnalysis) is the default associated to the new data update action.




5. Click the new data update action instance to expand and display the properties that you can define.




6. Enter or select the following properties:

Setting	Description	
Name	The name of the data update action and then click .	
Dashboard Scope	The dashboard where you will define the dashboard scope data parameters that will be passed to the target dashboard. Can either be [All Dashboard] or the current dashboard.	
Data Table	The source data table. This will eventually be displayed above the data update action instance.	

The defined parameters of the selected target data table will be displayed in the *Parameters* section.




Click on the parameter instance to expand and define its properties.



For each parameter added, set or select the following properties:

Setting	Description	
Value Source	Select the column value from the source table that will supply the contextual value.	
	If you select [Use Current Value], the current parameter value will be passed to the dashboard.	
Multiple Values	This passes multiple values for the parameter to the target area. Tap the slider to turn on. The <i>Value Separator</i> field displays.	
	Multiple Values	
	Value Separator ,	
	Specify the value separator to be used.	




You can delete any of the added parameters by clicking the corresponding **Delete** button.

7. You can also opt to specify one or several existing parameters that will get a new value when the Data Update


Action is executed. You can do so by clicking

on the *Parameter Resets* section.

A new *Reset Parameter* instance is added.



8. Click on the parameter instance to expand and define its properties.



9. For each reset parameter added, set the following properties:

Setting	Description	
Name	Any existing parameter that will get a new value when the Data Update Action is executed.	
Value	A static value or a reference of another parameter. NOTES:	
	• \$ClientTime is a special string parameter value in the Data Update Action that must be manually entered (no drop-down option). The browser current time will be used and formatted to look like the following string 2020-11-23T18:44:32.386000000000.	
	Setting the Parameter Reset Value as \$ClientTime is a valid solution for achieving a data refresh of the data table that uses the parameter. The parameter does not need to be included in any query statement or connection settings. It is enough that the parameter exists in the data	


table settings for the data table to reload each time the parameter value changes.

Repeat steps 7 to 9 to add more reset parameters.


10. Click the **Save** icon on the toolbar to save the changes.

When saved, the Saved! notification is displayed.

Clicking the All Dashboard Scope, the new data update action is available.




If the Dashboard Scope is [All Dashboard], the new data update action will be displayed as:



Filtering Workbook Actions Based on the Dashboard Scope or Source Data Table


Steps:

On the Dashboard and Workbook Settings pane, click the Workbook tab.
 The Actions pane is displayed with the list of all workbook actions set to the All Dashboard Scope.




NOTE Workbook actions are grouped based on their associated source data table.

2. To filter based on the source data table, select one from the Source Data Table drop-down list.




The workbook actions are displayed with the selected source data table.

With the All dashboard scope:



With the Current dashboard scope (e.g., How to Actions):



Adding an Action Form

The Action Form enables binding multiple action controls to a single action. In cases where multiple parameters that affect data loading are used, this allows for setting of all the parameters at once instead of once per action control.

The form part can be configured to use five different action modes. However, unlike the <u>Action Button</u>, the parts tied to the action form are the ones that dictate the set of parameters for the mode. These components can be any of the existing action parts, except the action button.

NOTE

The parameter that the action part controls is used in the action the form executes. This means that the action part parameter will no longer affect the dashboard parameter. Parameter changes and data updates will still happen, but only within the context of the form.

Furthermore, action parts as form components are only allowed to configure their target parameters based on the mode of the form part. For *Navigate* and *Set Parameter* modes, the action parts can target the dashboard parameters. For the other modes, the set of targetable parameters is not known, so they can set a parameter of any name.

This section discusses the steps and guidelines to add an action form using the following dashboard parameters and data tables.

Sample Data Table 1: Result

Text	Num	From	То
{p_text}	{p_numeric}	{p_timefrom}	{p_timeto}

Sample Data Table 2: TextOptions

Option	Туре	Qty
Apple	Fruit	5
Banana	Fruit	11
Pear	Fruit	3
Orange	Fruit	6
Lemon	Fruit	5
Grape	Fruit	12
Kiwi	Fruit	5
Red	Color	3
Blue	Color	7
Green	Color	10
Yellow	Color	3

Sample Data Table 3: TextType

Туре	
Color	
Fruit	

Sample Parameters

Parameter Name	Туре	Default Value
p_text	Text	Default
p_numeric	Numeric	0
p_timefrom	Time	2021-01-01T00:00:00.000
p_timeto	Time	2021-02-01T00:00:00.000
Туре	Text	Fruit

Steps:

1. After double-clicking or drawing a rectangle on the dashboard canvas, click




pane then click the Numeric Action Slider




ab

ab


The Action Form pane is displayed, and the Action Form part is added on the dashboard canvas. The Controller ID is automatically generated (e.g., ActionForm1) which is used when associating the form to other action parts.



2. Optionally enter the action form *Title*. The title of the form on the dashboard is updated.



3. Select any of the Action Modes:



Set Parameters

Updates parameters on the current dashboard. The connected action parts can select any parameter on the current dashboard to set.

Navigate

Updates the parameters on the target dashboard. The connected action parts can select any parameter on the target dashboard.



Execute Script

Allows the execution of a script.



Enter the parameterized Script.

The parameters are written within curly brackets, {ParameterName}.

The connected action parts define which parameters will be available in the script. If a connected action defines a parameter by name "ParameterName", this value ca be used in the script in the form.

For script actions allowing multiple value input, you can optionally specify a value separator within the curly brackets where you put the parameter name. The syntax is as follows:

{ParameterName:Separator}

For example: {Company: | }

Default separator is comma. At execution, the parameter will be replaced with real field values associated with the selected visualization node.


Update Data

Allows data update (typically in a database) by passing parameters into a data query.

The connected action parts will be able to select any parameter of the configured target data table.



You can opt to specify one or several existing parameters that will get a new value when the **Update Data** action is executed. You can do so by clicking + on the *Parameter Resets* section.



Click on the parameter instance to expand and define its properties.

Open URL

Allows access to a web page or file or even point to other resources on the web such as database queries and command output.



Enter the parameterized URL.

The parameters are written within curly brackets, {ParameterName}.

Similar to the script mode, the required parameters need to be defined by the connected action parts.

For actions allowing multiple value input, you can optionally specify a value separator within the curly brackets where you put the parameter name. The syntax is as follows:

{ParameterName:Separator}

For example: {Company:+}

Default separator is semicolon. Specifying for example a plus sign allows you to do multi search term searches on Google, for example.

At execution, the parameter will be replaced with real field values associated with the selected visualization node.

The easiest way to create parameterized URLs is to open an example web page and copy the URL. As an example, Yahoo Finance Key Statistics for Microsoft has the following web address:

http://finance.yahoo.com/q/ks?s=MSFT

If a parameter called Ticker has been set up in the data table, you can generate the URL by removing **MSFT** and replacing it with **{Ticker}**:

http://finance.yahoo.com/q/ks?s={Ticker}


Select the Target area of the page where the output URL will be displayed.





4. To set the style of the Action Form, click Style

The page updates to display the Style pane.




5. Set the Font type, size, style (Bold and/or Italic).

The part's font is set to **Bold** by default.


- Click the Foreground or Background box to display the Color dialog and set the color or enter the Hex color code.
- 7. Click **Update Style** and select any of the following options:
 - Set current as default Save the changes and set it as the default.
 - Create custom style Save the changes and set it as a custom style.

The Style pane updates to display the Title control.



- Enter the custom style Title.
- If there are additional changes made, click Update Current Style in the Update Style drop-down.

The new custom style is added in the **Workbook > Theme > Custom Styles** list.



If published, the custom style configuration of the Action Form will be added to the Global custom styles list and can be applied to other parts.

- Reset to default Revert to the original default settings.
- 8. Click the **Save** icon on the toolbar to save the changes.

When saved, the Saved! notification is displayed.

The Action Form can now be used as the form controller of the following action parts:

- Action Date Picker
- Action Date Range Picker
- Action Dropdown


- Action Text Box
- Numeric Action Slider
- Numeric Range Action Slider

Sample 1: Using the **Set Parameter** mode and adding <u>Action Text Box</u> and <u>Action Dropdown</u> components to **ActionForm1** with the following target parameters.

Action Part	Target Parameter	Default Value
Action Text Box	p_text	Default
Action Dropdown	Туре	Fruit

The action parts can be configured to either be a **Standalone** or a **Form** component.


Action Text Box




When an action part is set to **Form**, it can be connected to any form controller on the same dashboard. The parameters that the action part can set depends on how the form is configured.

If a part should not be connected to a form, it can be set to **Standalone** instead.


A line connects the component to the associated action form.




Upon selection of the action form, it lists **p_text(ActionTextBox1)**. This means that the parameter **p_text** is being set by the connected action part **ActionTextBox1**.




For the second component, again a line connects it to **ActionForm1**.



Upon selection of the action form, it additionally lists that the **Type** parameter is being set by the newly connected **ActionDropDown1** part.




Changing the value in the action text box from **Default** to **New Value** and clicking the form button will trigger the *Set Parameter* action and set the value of **p_text** on the dashboard.




Sample 2. Using the **Set Parameter** mode and adding a new Action Form (**ActionForm2**) with an Action Drop Down component:

Action Part	Value Column	Target Parameter	Default Value
Action Dropdown	Option	p_text	Default


The Controller ID is automatically generated (e.g., ActionForm2) for the new action form.




For the action dropdown component, the target parameter is **p_text** and the value column is **Option**.



This means that the value selected in the dropdown list will update the **p_text** parameter on the dashboard after clicking **ActionForm2**.



For example, when selecting **Lemon** in the dropdown, it sets the **p_text** parameter for all action parts connected to the form without updating the parameter on the dashboard. The parameter will only be set on the dashboard after clicking the form button.



Adding a Numeric Action Slider

The Numeric Action Slider allows the entry of a numeric parameter.

Whenever the slider value is changed, the associated action is executed.

Steps:

After double-clicking or drawing a rectangle on the dashboard canvas, click




pane then click the Numeric Action Slider


The Numeric Action Slider pane is displayed, and the Numeric Action Slider part is added on the dashboard canvas.

icon.

For this example, the following parameters are defined:



These parameters are used on the *Title* of the Line graph (e.g., **Price History for {Ticker} with Slider Value = {Slider Value:0.00%})**.




2. The numeric action slider can be configured to either be a Standalone or a Form component.

When set to **Form**, the numeric action slider can be connected to any form controller on the same dashboard. The parameters that the action part can set depends on how the form is configured.


NOTE

An action form part must be defined first to associate the numeric action slider as a component. Refer to Adding an Action Form more information.

A line connects the component to the associated form.




If the numeric action slider should not be connected to a form, it can be set to **Standalone** instead. Select the *Target Parameter* that will be updated by this action part.



- 3. Enter the *Title* of the numeric action slider.
 - Otherwise, if left blank, the title of the control will be **Set <Target Parameter>**.
- 4. Select the Label Position: Left or Top.
- 5. Select the Label Width:
 - Auto, or

- Fixed then enter the width (default is 15).
- 6. You can opt to enter the allowed Minimum and Maximum values.
- 7. Enter the *Format* that the numeric value will be displayed.
- 8. Tap the Display in PDF slider to turn it on and include the numeric action slider in the PDF output.
- 9. To set the style of the Numeric Action Slider, click **Style**

The page updates to display the Style pane.




10. Set the Font type, size, style (Bold and/or Italic) of the part and title.

The part title's font is set to **Bold** by default.


- 11. Click the **Foreground** or **Background** box to display the *Color* dialog and set the slider color or enter the Hex color code.
- 12. Click **Update Style** and select any of the following options:
 - Set current as default Save the changes and set it as the default.
 - Create custom style Save the changes and set it as a custom style.

The Style pane updates to display the Title control.



- Enter the custom style Title.
- If there are additional changes made, click Update Current Style in the Update Style drop-down.

The new custom style is added in the Workbook > Theme > Custom Styles list.



If published, the custom style configuration of the Numeric Action Slider will be added to the Global custom styles list and can be applied to other parts.

- Reset to default Revert to the original default settings.
- 9. Click the **Save** icon on the toolbar to save the changes.

When saved, the Saved! notification is displayed.

Adding a Numeric Range Action Slider

The Numeric Range Action Slider allows sliders of two parameters.

Whenever the slider values are changed, the associated action is executed.

Steps:

1. After double-clicking or drawing a rectangle on the dashboard canvas, click



on the Select Part




pane then click the Numeric Range Action Slider Range Slider icon

The Numeric Range Action Slider pane is displayed, and the Numeric Range Action Slider part is added on the dashboard canvas.

For this example, the following parameters are defined:

Parameter Name	Туре	Default Value
Ticker	Text	COST
AdjCloseMin	Numeric	30
AdjCloseMax	Numeric	205

These parameters are used on the *Title* of the Line graph (e.g., **Price History for {Ticker} with the Adj Close range of {AdjCloseMin} to {AdjCloseMax})**.




2. The numeric range action slider can be configured to either be a Standalone or a Form component.

When set to **Form**, the numeric range action slider can be connected to any form controller on the same dashboard. The parameters that the action part can set depends on how the form is configured.


NOTE

An action form part must be defined first to associate the numeric range action slider as a component. Refer to Adding an Action Form more information.


A line connects the component to the associated form.



If the numeric action slider should not be connected to a form, it can be set to **Standalone** instead. Select the *Low Parameter* and *High Parameter* that will be updated by this action part.



- 3. Enter the *Title* of the numeric range action slider.
- 4. Select the Label Position: Left or Top.
- 5. Select the Label Width:
 - Auto, or
 - Fixed then enter the width (default is 15).
- 6. You can opt to enter the allowed *Minimum* and *Maximum* values.
- 7. Enter the *Format* that the numeric value will be displayed.
- 8. Tap the Display in PDF slider to turn it on and include the numeric action slider in the PDF output.
- 9. To set the style of the Numeric Range Action Slider, click **Style**The page updates to display the *Style* pane.




10. Set the Font type, size, style (Bold and/or Italic) of the part and title.

The part title's font is set to **Bold** by default.


- 11. Click the **Foreground** or **Background** box to display the *Color* dialog and set the slider color or enter the Hex color code.
- + Update Style and select any of the following options:
 - Set current as default Save the changes and set it as the default.
 - Create custom style Save the changes and set it as a custom style.

The Style pane updates to display the Title control.



- Enter the custom style Title.
- If there are additional changes made, click **Update Current Style** in the *Update Style* drop-down.

The new custom style is added in the Workbook > Theme > Custom Styles list.



If published, the custom style configuration of the Numeric Range Action Slider will be added to the Global custom styles list and can be applied to other parts.

- Reset to default Revert to the original default settings.
- 13. Click the Save icon on the toolbar to save the changes.



Adding an Action Button

The action button control allows users to execute an action. It can also just pass the entered parameter value if the string is exactly equal to the {parameter-name}.

Steps:

1. After double-clicking or drawing a rectangle on the dashboard canvas, click

ab




pane then click the **Action Button**

icon. The Action Button pane is displayed, and the Action Button part is added on the dashboard canvas.


For this example, the following parameters are defined:

Parameter Name	Туре	Default Value
Ticker	Text	COST
Slider Value	Text	0

These parameters are used on the *Title* of the Line graph (e.g., **Price History for {Ticker} with Slider Value = {Slider Value:0.00%})**.



2. Select any of the Action Modes:



Set Parameters



The *Parameters* pane lists the available parameters to set the data loading for each interaction with the Action Button.

Click on a <u>parameter</u> instance to expand and set the values that the action requires.

Navigate


Allows the selection of the dashboard where you want to pass the parameters.



Click on a <u>parameter</u> instance to expand and set the values that the action requires.

Execute Script

Allows the execution of a script.



Enter the parameterized Script.

The parameters are written within curly brackets, {ParameterName}.

For script actions allowing multiple value input, you can optionally specify a value separator within the curly brackets where you put the parameter name. The syntax is as follows:

{ParameterName:Separator}


For example: {Company: | }

Default separator is comma. At execution, the parameter will be replaced with real field values associated with the selected visualization node.

You can opt to add new parameters by clicking ⁺ and define the <u>parameter</u> values that the action requires.

Update Data


Allows data update (typically in a database) by passing parameters into a data query.



Click on a parameter instance to expand and set the values that the action requires. You can also opt to click to delete a parameter.

You can also opt to specify one or several existing parameters that will get a new value when the **Update Data** action is executed. You can do so by clicking


on the *Parameter Resets* section.



Click on the <u>parameter</u> instance to expand and define its properties.

Open URL

Allows access to a web page or file or even point to other resources on the web such as database queries and command output.



• Enter the parameterized URL.

The parameters are written within curly brackets, {ParameterName}.

For actions allowing multiple value input, you can optionally specify a value separator within the curly brackets where you put the parameter name. The syntax is as follows:

{ParameterName:Separator}

For example: {Company:+}

Default separator is semicolon. Specifying for example a plus sign allows you to do multi search term searches on Google, for example.

At execution, the parameter will be replaced with real field values associated with the selected visualization node.

The easiest way to create parameterized URLs is to open an example web page and copy the URL. As an example, Yahoo Finance Key Statistics for Microsoft has the following web address:

http://finance.yahoo.com/q/ks?s=MSFT


If a parameter called Ticker has been set up in the data table, you can generate the URL by removing **MSFT** and replacing it with **{Ticker}**:

http://finance.yahoo.com/q/ks?s={Ticker}

Select the Target area of the page where the output URL will be displayed.




Click ⁺ to add parameters to the output URL.




Click on the <u>parameter</u> instance to expand and define its properties.

The title of the action button defaults to the selected action mode.




- 3. Enter the new *Title* of the action button.
- 4. For the *User Input*, you can:
 - check the **Enabled User Input** box to allow the entry of parameter value that will be executed once the action button is clicked.

Then, select the parameter.




This will be displayed on the dashboard as:



check the Show Label box to display the label (selected by default).
 When unchecked, the parameter name is not displayed before the input field.




- 5. Enter a description or useful information about the action button into the Tooltip box.
- 6. Tap the **Show as Hyperlink** slider to turn it on and display the layout style of the button to a hyperlink.
- 7. Tap the **Display in PDF** slider to turn it on and include the action button in the output PDF.
- 8. To set the style of the Action Button, click **Style**The page updates to display the *Style* pane.




- 9. Set the Font type, size, style (**Bold** and/or **Italic**) of the part and button.
- Click the Foreground or Background box to display the Color dialog and set the color or enter the Hex color code.
- + Update Style and select any of the following options:
 - Set current as default Save the changes and set it as the default.
 - Create custom style Save the changes and set it as a custom style.

The Style pane updates to display the Title control.



- Enter the custom style Title.
- If there are additional changes made, click Update Current Style in the Update Style drop-down.

The new custom style is added in the Workbook > Theme > Custom Styles list.




If published, the custom style configuration of the Action Button will be added to the Global custom styles list and can be applied to other parts.

- Reset to default Revert to the original default settings.
- 12. Click the **Save** icon on the toolbar to save the changes.


Defining Action Parameter Properties

For each parameter added or defined in the actions, you can set their Value Source:




Current Value

The current value of the parameter is used.




Interactive

Allows values to be entered when the action is executed.




Constant Value

Allows the constant value of the parameter to be defined.



Parameter

Allows the selection of the source parameter.



Adding an Action Date Picker

The Action Date Picker allows the entry of a Date/Time parameter.

Whenever the date picker value is changed, the associated action is executed.

Steps:

After double-clicking or drawing a rectangle on the dashboard canvas, click



on the Select Part


pane then click the Action Date Picker Date Picker icon.

The Action Date Picker pane is displayed, and the Action Date Picker part is added on the dashboard canvas with the current date and the Set button to the right.

For this example, the following parameters are defined:


Parameter Name	Туре	Default Value
Ticker	Text	COST
TWS	Text	2008-01-01
TWE	Text	2009-03-01
SS	Text	2009-03-01

These parameters are used on the Title of the Line graph (e.g., Start: {TWS: yyyy-MMM-dd HH:mm:ss}, End = {TWE: yyyy-MMM-dd HH:mm:ss}, Snapshot: {SS: yyyy-MMM-dd HH:mm:ss}).




2. The action date picker can be configured to either be a **Standalone** or a **Form** component.


When set to **Form**, the action date picker can be connected to any form controller on the same dashboard. The parameters that the action part can set depends on how the form is configured.



A line connects the component to the associated form.



If the action date picker should not be connected to a form, it can be set to **Standalone** instead. Select the *Target Parameter* that will be updated by this action part.




3. Enter the *Title* of the action date picker button.

If set to the **Standalone** type and the *Title* is blank, the button will be **Set <Target Parameter>.**

4. Select the Date/Time Format.

Clicking on the Date/Time box displays the date picker in calendar mode.



The text of the date can be directly entered, or alternatively it can be clicked on, to bring up a date picker in the Web client.

- 5. Tap the **Hide Button** slider to turn it on. This means the action control will update the parameter whenever the value of the date picker changes.
- 6. Tap the **Default to Today** slider to turn it on. This allows the action date picker to check the current value of the dashboard parameter. If it is set to null/empty, an action is executed to update the parameter and trigger the loading of the parameterized data with the current date.
- 7. Tap the Relative Date UTC Offset slider to turn it on then enter the UTC Offset value (default is +0000).

By default, when an action date picker performs a relative date calculation, the point in time that the calculation is relative to will be based on the time zone picked up from the browser (i.e., the timezone the user is in). Since parameters do not encode the time zone information, the resulting value from the relative date calculation will be affected by the time zone the relative calculation is performed in.

Example:

User timezone: UTC+0200

Expression: now UTC Offset: none

Current time: 2001-01-01T00:00:00.000+0000 Evaluated time: 2001-01-01T02:00:00.000+0200 Parameter value: 2001-01-01T02:00:00.000

The **now** expression is evaluated in relation to the current time and when formatted, the time zone information is no longer encoding, resulting in a parameter value offset from UTC by **+0200**.

The UTC offset setting allows for configuring an offset from UTC for the time the calculation is relative to, independent of the timezone the user is in.

Example:

User timezone: UTC+0200

Expression: now UTC Offset: +0600

Current time: 2001-01-01T00:00:00:00.000+0000 Evaluated time: 2001-01-01T02:00:00.000+0200 Parameter value: 2001-01-01T06:00:00.000

Since the UTC offset is +0600, the resulting parameter value is formatted with the offset from UTC rather than as the time zone the user is in.

This allows the parameter values generated by date pickers to target a specific UTC offset instead of generating values based on the time zone the user is currently in.

8. Instead of turning the **Default to Today** slider on, enter the *Default Relative Date String* then click . This allows the relative date calculation (based on today's date), by parsing the input text string.

This method uses the following pattern:

SIGN NUMBER UNIT

Where:

- SIGN is either a '+' or '-'
- NUMBER is any number
- **UNIT** which can be any of the following:
 - m minute
 - H − hour
 - D − day
 - ♦ B business day
 - ♦ M month
 - Y year

For example:

Pattern	Description
-5m	Back 5 minutes from current time.
-1D	Back 1 day from today.
+D	Forward 1 day from today.
-1B	Back 1 business day from today (ignore Saturday and Sunday).
+1B	Forward 1 business day from today (ignore Saturday and Sunday).
-1M	Back 1 month from today.
-1Y	Back 1 year from today.
-7D	Back 7 days from today.
-14D	Back 14 days from today.


When these values are entered, the correct date should be selected, and then the data requests are executed based on this date.

The special **now** term can also be used, this represents the current Date/Time. For example:

- Using **now** will set the date picker to the current Date/Time
- now-7D will set the date picker to 7 days ago. This is the same as specifying


-7D

For example:




The date will be **now-7D** by default.

For example, **now** is September 14, it will go back 7 days (September 7) and then the date will be recalculated along with the Date/Time format.




In addition, you can use the SIGN UNIT NUMBER pattern to modify the relative date calculation.

For example, if you enter **-1M**, the recalculated relative date will be August 14.




Complex expressions can also be entered to recalculate the relative date. These expressions are evaluated from the left to right pattern. The **now** term can also be used as a pointer to the currently evaluated value of the relative time expression.

For example, if you enter **now-5M-2D+3Y** in the Action Date Picker Settings pane:




The date will be now-5M-2D+3Y by default.




In the expression, you can also use **startOf** and **endOf** functions. Both functions take the same arguments, a relative time string, and a unit.


For example, if you enter startOf(now, D):




The date will display the start of the current day:




Lastly, you can define a complex expression with the functions. For example, if you enter startOf(now-7D, W):




The date will display the start of the previous week:






- 9. Tap the Display in PDF slider to turn it on and include the action date picker in the PDF output.
- 10. To set the style of the Action Date Picker, click **Style**The page updates to display the *Style* pane.




- 11. Set the Font type, size, style (**Bold** and/or **Italic**) of the part and button.
- 12. Click the **Foreground** or **Background** box to display the *Color* dialog and set the color or enter the Hex color code.
- 13. Click **Update Style** and select any of the following options:
 - Set current as default Save the changes and set it as the default.
 - Create custom style Save the changes and set it as a custom style.

The Style pane updates to display the Title control.



- Enter the custom style Title.
- If there are additional changes made, click Update Current Style in the Update Style drop-down.

The new custom style is added in the Workbook > Theme > Custom Styles list.



If published, the custom style configuration of the Action Date Picker will be added to the Global custom styles list and can be applied to other parts.

Reset to default – Revert to the original default settings.



Adding an Action Date Range Picker

The Action Date Range Picker allows setting a date range (*From Date* and *To Date*) and triggering an action. Whenever the date range picker values are changed, the associated action is executed.

Steps:

1. After double-clicking or drawing a rectangle on the dashboard canvas, click on the Select Part

Date Range

icon.


pane then click the Action Date Range Picker Picker

The Action Date Range Picker pane is displayed, and the Action Date Range Picker part is added on the dashboard canvas with the current date range (parameters From Date to To Date) and the **Set** button.

For this example, the following parameters are defined:

Parameter Name	Туре	Default Value
Ticker	Text	COST
TWS	Text	2008-01-01
TWE	Text	2009-03-01
SS	Text	2009-03-01

These parameters are used on the *Title* of the Line graph (e.g., **Start: {TWS: yyyy-MMM-dd HH:mm:ss}, End = {TWE: yyyy-MMM-dd HH:mm:ss}, Snapshot: {SS: yyyy-MMM-dd HH:mm:ss}**).




2. The action date range picker can be configured to either be a **Standalone** or a **Form** component.

When set to **Form**, the action date range picker can be connected to any form controller on the same dashboard. The parameters that the action part can set depends on how the form is configured.


NOTE

An action form part must be defined first to associate the action date range picker as a component. Refer to Adding an Action Form more information.

A line connects the component to the associated form.




If the action date picker should not be connected to a form, it can be set to **Standalone** instead. Select the parameters that will be used for the *From Parameter* and *To Parameter* dates range.



- 3. Enter the *Title* of the action date range picker button.
- 4. Select the Date/Time Format.

Clicking on the Date/Time box displays the date picker in calendar mode.



The text of the date can be directly entered, or alternatively it can be clicked on, to bring up a date picker in the Web client.

5. Tap the **Hide Button** slider to turn it on. This means the action control will update the parameter whenever the value of the data picker changes.

- 6. Tap the **Default to Today** slider to turn it on. This allows the action date range picker to check the current value of the dashboard parameter. If it is set to null/empty, an action is executed to update the parameter and trigger the loading of the parameterized data with the current date.
- 7. Tap the Relative Date UTC Offset slider to turn it on then enter the UTC Offset value (default is +0000).

By default, when an action date range picker performs a relative date calculation, the point in time that the calculation is relative to will be based on the time zone picked up from the browser (i.e., the timezone the user is in). Since parameters do not encode the time zone information, the resulting value from the relative date calculation will be affected by the time zone the relative calculation is performed in.

Example:

User timezone: UTC+0200

Expression: now UTC Offset: none

Current time: 2001-01-01T00:00:00.000+0000 Evaluated time: 2001-01-01T02:00:00.000+0200 Parameter value: 2001-01-01T02:00:00.000

The **now** expression is evaluated in relation to the current time and when formatted, the time zone information is no longer encoding, resulting in a parameter value offset from UTC by **+0200**.

The UTC offset setting allows for configuring an offset from UTC for the time the calculation is relative to, independent of the timezone the user is in.

Example:

User timezone: UTC+0200

Expression: now UTC Offset: +0600

Current time: 2001-01-01T00:00:00.000+0000 Evaluated time: 2001-01-01T02:00:00.000+0200 Parameter value: 2001-01-01T06:00:00.000

Since the UTC offset is **+0600**, the resulting parameter value is formatted with the offset from UTC rather than as the time zone the user is in.

This allows the parameter values generated by date pickers to target a specific UTC offset instead of generating values based on the time zone the user is currently in.

- 8. Instead of turning the **Default to Today** slider on, enter the following date range values:
 - Relative From Date or the start Date/Time
 - Relative To Date or the end Date/Time

This allows the relative date calculation (based on today's date), by parsing the input text string.

This method uses the following pattern:

SIGN NUMBER UNIT

Where:

- SIGN is either a '+' or '-'
- NUMBER is any number
- UNIT which can be any of the following:
 - o m minute
 - H hour
 - D day
 - B business day
 - M month
 - Y year


For example:

Setting	Description
-5m	Back 5 minutes from current time.
-1D	Back 1 day from today.
+D	Forward 1 day from today.
-1B	Back 1 business day from today (ignore Saturday and Sunday).
+1B	Forward 1 business day from today (ignore Saturday and Sunday).
-1M	Back 1 month from today.
-1Y	Back 1 year from today.
-7D	Back 7 days from today.
-14D	Back 14 days from today.

When these values are entered, the correct date should be selected, and then the data requests are executed based on this date.

The special **now** term can also be used, this represents the current Date/Time. For example:

- Using now will set the date picker to the current Date/Time
- now-7D will set the date picker to 7 days ago. This is the same as specifying -7D
 For example:



The From date will be **now-7D** and the To date will be **now** by default.


For example, **now** is September 14, it will go back 7 days (September 7) and then the date will be recalculated.



In addition, you can use the **SIGN UNIT NUMBER** pattern to modify the relative date calculation. For example, if you enter **-1M**:




The recalculated relative date will be August 14:




Complex expressions can also be entered to recalculate the relative date. These expressions are evaluated from the left to right pattern. The **now** term can also be used as a pointer to the currently evaluated value of the relative time expression.

For example, if you enter now-5M-2D+3Y as the Relative To Date and now as the Relative From Date:




The date will be **now-5M-2D+3Y** by default.





In the expression, you can also use **startOf** and **endOf** functions. Both functions take the same arguments, a relative time string, and a unit.

Lastly, you can define a complex expression with the functions. For example, if you enter **startOf(now-7D, W)** as the *Relative From Date* and **endOf(now, D)** as the *Relative To Date*:



The *From* date will display the start of the previous week and the *To* date will display the end of the current day:





- 9. You may opt to set new From Label and To Label.
- 10. Tap the Auto Fire Quick Ranges slider to turn it on. This automatically updates the date ranges as you click in the drop-down in the Web client. Otherwise, you have to select a date range first in the drop-down and then click to update.
- 11. Set the Range Limit of the date by selecting the number of days. By default, the range limit is -1.




12. When a *Range Limit* has been set, the *Range Limit Error* box is enabled. It is mandatory to enter an error message to help in defining a better input to match the set limit.

For example: "The Range Limit is set to 30 days. Modify the To date within this limit."




- 13. Tap the Display in PDF slider to turn it on and include the action date picker in the PDF output.
- 14. To set the style of the Action Date Range Picker, click **Style**The page updates to display the *Style* pane.



- 15. Set the Font type, size, style (Bold and/or Italic) of the part and button.
- Click the Foreground or Background box to display the Color dialog and set the color or enter the Hex color code.
- 17. Click **Update Style** and select any of the following options:
 - Set current as default Save the changes and set it as the default.


• Create custom style – Save the changes and set it as a custom style.

The Style pane updates to display the Title control.




- Enter the custom style Title.
- If there are additional changes made, click Update Current Style in the Update Style drop-down.

The new custom style is added in the Workbook > Theme > Custom Styles list.



If published, the custom style configuration of the action date range picker will be added to the Global custom styles list and can be applied to other parts.


- Reset to default Revert to the original default settings.
- 18. Click the **Save** icon on the toolbar to save the changes.




Selecting Relative Dates in Action Date Picker and Action Date Range Picker Controls

Both the Action Date Picker and Action Date Range Picker controls have pre-populated quick ranges that allow you to readily select a date range.


For example, for an Action Date Picker, if the current date is September 14, 2021 clicking will display:



Clicking This Year will recalculate the current date to the start of the current year (January 1, 2021):




For the Action Date Range Picker, clicking will display:



The recalculated date range will include the start and end dates based on the selected quick range.

For example, clicking **This Year** will recalculate the current date range from the start of the current year (January 1, 2021) to the end of the current year (December 31, 2021):



Select any of the following quick ranges:

Setting	Description
Last 10 minutes	Back 10 minutes from current time.
Last 20 minutes	Back 20 minutes from current time.
Last 30 minutes	Back 30 minutes from current time.
Last Hour	Back 1 hour from current time.
Last 90 minutes	Back 90 minutes from current time.
Last 2 Hours	Back 2 hours from current time.
Last 4 Hours	Back 4 hours from current time.
Last 6 Hours	Back 6 hours from current time.
Last 8 Hours	Back 8 hours from current time.
Last 24 Hours	Back 1 day from today.
Last 7 Days	Back7 days from today.
Last 1 Month	Back 1 month from today.
Last 3 Months	Back 3 months from today.
Last 6 Months	Back 6 months from today.
Last 1 Year	Back 1 year from today.
Today	Start of current day.
From Yesterday	Start of 1 day from today.
This Week	Start of the week from today.
This Month	Start of the month from today.
This Quarter	Start of the quarter from today.

This Year	Start of the year from today.
Prior Day	Start of 1 day from today.
Prior Business Day	Back 1 business day from today (ignore Saturday and Sunday).
Prior Week	Start of the prior week from today.
Prior Month	Start of the prior month from today.
Prior Quarter	Start of the prior quarter from today.
Prior Year	Start of the prior year from today.

NOTE	If the preferred quick range is not available, it is always possible to enter a relative date inside the date picker.

Adding an Action Dropdown

The Action Dropdown allows the selection of the parameter value that will be used by the action.

Steps:

1. After double-clicking or drawing a rectangle on the dashboard canvas, click on the Select Part



pane then click the **Action Dropdown**


Dropdown icon

The Action Dropdown pane is displayed, and the Action Dropdown part is added on the dashboard canvas.

For this example, the following parameters are defined:

Parameter Name	Туре	Default Value
Ticker	Text	COST
Slider Value	Text	0

These parameters are used on the *Title* of the Line graph (e.g., **Price History for {Ticker} with Slider Value = {Slider Value:0.00%})**.




2. The action dropdown can be configured to either be a **Standalone** or a **Form** component.


When set to **Form**, the action dropdown can be connected to any form controller on the same dashboard. The parameters that the action part can set depends on how the form is configured.



A line connects the component to the associated form.



If the action dropdown should not be connected to a form, it can be set to **Standalone** instead. Select the *Target Parameter* that will be updated by this action part.



- 3. Select the Data Table that will be source of the Value Column and Title Column.
- 4. Select a Value Column.
- 5. Select a Title Column.
- 6. For the *Sorted Column*, select either **Value** or **Title**. If you did not select a *Title Column*, the *Sorting* drop-down is disabled and the *Value Column* is automatically used for sorting.
- 7. Optionally, specify a sorting mode for the values: Ascending, Descending, or None.

NOTE


The Sort order setting is based on "Sorting" + Value/Title drop-down and "Order" + Ascending/Descending.

- 8. Enter the drop-down Title.
 - Otherwise, if left blank, the tile of the control will be Set <Target Parameter>.
- 9. Tap the **Show Title** slider to display the *Title* in the drop-down.
- 10. Select the Label Position: Top or Left.
- 11. Select the Selection Mode.
- 12. Tap the **Show Select All** slider to allow selection of all items. Consequently, this causes an array of parameter values to be passed to the action or auto parameterization.

Style

- 13. Enter the Select All Value.
- 14. Enter a description or useful information about the action drop down into the *Tooltip* box.
- 15. Tap the Display in PDF slider to turn it on and include the action button in the output PDF.
- 16. To set the style of the Action Dropdown, click **Style**


The page updates to display the Style pane.



- 17. Set the Font type, size, style (Bold and/or Italic) of the part and title.
- 18. Click **Update Style** and select any of the following options:
 - Set current as default Save the changes and set it as the default.


• Create custom style – Save the changes and set it as a custom style.

The Style pane updates to display the Title control.



- Enter the custom style *Title*.
- If there are additional changes made, click Update Current Style in the Update Style drop-down.

The new custom style is added in the Workbook > Theme > Custom Styles list.



If published, the custom style configuration of the Action Dropdown will be added to the Global custom styles list and can be applied to other parts.

Reset to default – Revert to the original default settings.

19. Click the **Save** icon on the toolbar to save the changes.

When saved, the Saved! notification is displayed.

Adding an Action Text Box

The Action Text Box allows users to submit free-text input values for a parameter associated with the action part. It can also be used for entering password parameters.

The currently applied parameter value will be displayed in the action text box.

Steps:

1. After double-clicking or drawing a rectangle on the dashboard canvas, click Control on the Select Part


pane then click the Action Text Box Text Box icon

The Action Text Box pane is displayed, and the Action Text Box part is added on the dashboard canvas.

For this example, the following parameters are defined:

Parameter Name	Туре	Default Value
Ticker	Text	COST
Slider Value	Text	0

These parameters are used on the *Title* of the Line graph (e.g., **Price History for {Ticker} with Slider Value = {Slider Value:0.00%})**.




2. The action text box can be configured to either be a **Standalone** or a **Form** component.

When set to **Form**, the action text box can be connected to any form controller on the same dashboard. The parameters that the action part can set depends on how the form is configured.


NOTE

An action form part must be defined first to associate the action text box as a component. Refer to Adding an Action Form more information.

A line connects the component to the associated form. By default, the *Show Title* slider is turned on and the title is displayed to describe what parameter the text box is setting (e.g., **Set Ticker**). Tap to slider to turn it off.



If the action text box should not be connected to a form, it can be set to **Standalone** instead. Select the *Target Parameter* that will be updated by this action part.



3. Enter the Title of the text box button.

If set to the Standalone type and the Title is blank, the button will be Set <Target Parameter>.

4. Select the *Input Type*: **Text**, **Numeric**, or **Time**.

If **Time** is selected, the *Format* field is enabled. Select the <u>Date/Time format</u>.


5. Select the Input Value Type: Single or Multiple.

If the Input Value Type selected is **Multiple**, you can opt to select e Delimiter character:

- 6. Set the custom Input Validation:
 - Enter a Regular Expression to match the input data.
 - The parameter will not be updated unless it passes the validation. Enter an *Error Message* to help in defining a better input in the Action Text Box.
- 7. Set the Input Sanitation:
 - Enter a Regular Expression to match the input data.
 - Enter a Replace Value which is the value to replace all matches from the regex with.

Whenever changing the text inside the action text box, this sanitation will be applied to whatever value is entered.


8. Select the Input Field Style: Text Field (One Line), Text Area (Multiple Lines), or Password.



- 9. Tap the Wrap Text slider (applies to Text Area).
- 10. Tap the **Hide Button** slider for the action control to update the parameter whenever the value of the text box changes.
- 11. Tap the Show Clear Button slider to display a button that will clear the text box when clicked.




- 12. Enter the Clear Button Title, if required.
- 13. Set the *Clear Button Width*. The value can either be calculated dynamically (default is **Dynamic**) or set to a fixed value (**Fixed**).
- 14. Set the *Button Width*. The value can either be calculated dynamically (default is **Dynamic**) or set to a fixed value (**Fixed**).
- 15. Tap the **Display in PDF** slider to turn it on and include the action button in the output PDF.
- 16. Enter a description or useful information about the action text box into the *Tooltip* box.
- 17. To set the style of the Action Text Box, click **Style**The page updates to display the *Style* pane.




- 18. Set the Font type, size, style (Bold and/or Italic) of the part, button, and title.
 - The title's font is set to **Bold** by default.
- 19. Click the **Foreground** or **Background** box to display the *Color* dialog and set the button's color or enter the Hex color code.
- 20. Click Update Style + Update Style -
- and select any of the following options:
- Set current as default Save the changes and set it as the default.
- Create custom style Save the changes and set it as a custom style.

The Style pane updates to display the Title control.



- Enter the custom style Title.
- If there are additional changes made, click Update Current Style in the Update Style drop-down.

The new custom style is added in the Workbook > Theme > Custom Styles list.



If published, the custom style configuration of the Action Text Box will be added to the Global custom styles list and can be applied to other parts.

• Reset to default – Revert to the original default settings.

21. Click the **Save** icon on the toolbar to save the changes.

When saved, the notification is displayed.

GENERAL PARTS

Das	hboards can be enhanced by	adding o	r setting	the followin	g general	parts:
	Text Label					

- = TOXT EUDE
- □ Panel
- Image Box
- □ <u>Iframe</u>
- JavaScript Part

Adding a Text Label

You can add labels or explanatory text to a dashboard using a text label.


Steps:

1. After double-clicking or drawing a rectangle on the dashboard canvas, click on the Select Part



pane then click the **Text Label** Text Label icon.

The Text Label pane is displayed, and the Text Label part is added on the dashboard canvas.




2. Select the Text Mode:

Manual



Enter the text.


Data




Select the source Data Table, Column, Aggregate, and specify the Format.

NOTE For text time series columns, only TextUnique and TextContactDistinct aggregates are supported.

- 3. Select the Vertical Align: Bottom , Middle , or Top
- 4. Select the Horizontal Align: Left , Center , or Right
- 5. Tap the Vertical Scrollbar slider to turn it on.
- 6. To set the style of the Text Label, click **Style**The page updates to display the *Style* pane.




- 7. To modify the Foreground or Background color:
 - click the corresponding *Color* box to display the *Color* dialog to:




- select the color, or
- click to enter the values


for RGB



for HSL



for the Hex color code




• or enter the Hex color code




- 8. Set the Font type, size, style (Bold and/or Italic).
- 9. Click **Update Style** and select any of the following options:
 - Set current as default Save the changes and set it as the default.
 - Create custom style Save the changes and set it as a custom style.

The Style pane updates to display the Title control.



- Enter the custom style *Title*.
- If there are additional changes made, click **Update Current Style** in the *Update Style* drop-down.

The new custom style is added in the Workbook > Theme > Custom Styles list.



If published, the custom style configuration of the text label will be added to the Global custom styles list and can be applied to other parts.

• Reset to default – Revert to the original default settings.



Panel


Dashboards can be flat or consist of groups of dashboard parts. Grouping of parts can be done by adding them in a panel.

Steps:


1. After double-clicking or drawing a rectangle on the dashboard canvas, click on the Select Part

pane then click the **Panel** icon.

The Panel pane is displayed, and the Panel part is added on the dashboard canvas.



2. Add parts or visualization in the panel.



- 3. Select one of the two Layout configurations:
 - Relative


A 100x100 coordinate system that is converted based on the size of the browser window.



Then set the number of Rows and Columns in the grid.


Stack

Stacks items horizontally or vertically, creating a single row or column layout.




Set the *Direction*, either **Vertical** or **Horizontal**.

Vertical Direction:



Horizontal Direction:



Parts in stack layouts cannot overlap, so collisions are automatically handled while resizing items.


💖 Style

Tap the **Fixed Layout** slider so the size of items as seen on the screen will not change, even as the resolution changes. A fixed axis stack is allowed to overflow the bounds of the panel, resulting in scrollbars.

4. To set the style of the Panel, click \mathbf{Style}



The page updates to display the Style pane.



- Click the Foreground or Background box to display the Color dialog and set the color or enter the Hex color code.
- 6. Set the Font type, size, style (**Bold** and/or **Italic**).
- 7. Click the **Border** box to display the *Color* dialog and set the color or enter the Hex color code.
- 8. Set the values for the panel Border, Padding, Border Radius, and Margin, if required.
- 9. Click the **Save** icon on the toolbar to save the changes.

When saved, the Saved! notification is displayed.

Adding an Image Box

You can add logos or other graphics to a dashboard using an Image Box.

These can be retrieved from disk or retrieved at display time from an external URL.

Steps:


1. After double-clicking or drawing a rectangle on the dashboard canvas, click




pane then click the Image Box Image

The Image Box pane is displayed, and the Image Box part is added on the dashboard canvas.

icon.



- 2. Select the Stretch Mode: Fit, Fill, or Stretch.
- 3. Select the Vertical Align: Top , Middle , or Bottom
- 4. Select the Horizontal Align: Left , Center , or Right
- 5. You can either:
 - enter the URL of the image file in the Fetch from URL text box and click .
 This enables the Cross Origin Mode drop-down list which allows for cross-origin attribute configuration on the image when doing a Copy Dashboard Image. Available states include:



- click Choose file to browse the image file in the *Open* dialog.
- 6. Tap the Display in PDF slider to include the image in the PDF output.
- 7. Click the **Save** icon on the toolbar to save the changes.

 When saved, the notification is displayed.

Adding an Iframe Part

The Iframe Part allows a web page to be displayed within a dashboard or page.


Steps:

1. After double-clicking or drawing a rectangle on the dashboard canvas, click on the Select Part



pane then click the **Iframe** Iframe

The Iframe pane is displayed, and the Iframe part is added on the dashboard canvas.



2. Enter the URL of the page you want to embed in the dashboard.

3. Click the **Save** icon on the toolbar to save the changes.

When saved, the Saved!

notification is displayed.

Adding a JavaScript Part

The JavaScript dashboard part allows the designer of a workbook to include a bespoke JavaScript code inside a dashboard.


Steps:

1. After double-clicking or drawing a rectangle on the dashboard canvas, click General on the Select Part



pane then click the JavaScript Part JavaScript Part icon.

The JavaScript pane is displayed, and the JavaScript part is added on the dashboard canvas.



The JavaScript part settings support the following functions:

- postLink(config)
- getDataRequestObject(config)

handleDataUpdate(config, data)

The argument config in all of the three functions will be an object with a single property **element**. config.element is the DOM element that is to be used if a UI is required. The same instance of config will be used throughout the lifetime of the JavaScript dashboard part. This means it can also be used to save references to other DOM elements, functions, or data.

2. Define the functions, as required:

• postLink (config) is called after the dashboard part is added to the DOM. The function can optionally return a destroy function. The return value is called when the dashboard part is disposed and removed from the DOM. This will happen when the user switches to another dashboard. Note that this is the only function that is required to implement this dashboard part.

Then select the Data Table.

- getDataRequestObject(config) is optional, and only used if the dashboard part needs to load data. The function specifies which columns to load, aggregation, and the shape of the data. The data table used for the dashboard part is selected in the Designer, in the drop-down list.
- handleDataUpdate(config, data) is the callback used when the data has finished loading from
 Panopticon Real Time. If the data table consists of a realtime data source then this function will be called for each update from Panopticon Real Time.

Below is a very simple JavaScript example, with no data loading:



□ Save

4. Click the **Save** icon on the toolbar to save the changes.

Adding a Tabbed Panel

Allows you to add a tabbed panel within a dashboard where visuals can be assigned to each tab.

Steps:

After double-clicking or drawing a rectangle on the dashboard canvas, click


General

on


on the Select Part

pane then click the Tab Panel Tab Panel icon.


The tabbed panel is displayed on the dashboard with the first tab (i.e., **New Tab 1**).




- 2. You can opt to define the name or title of the tab by doing one of the following:
 - · Double-click on the tab and enter the name or title, or
 - Right-click on the tab and select Rename. Then enter the name or title.
- 3. Add visualizations on the panel as needed.



4. Click **Add Tab** to add a new tab.



5. Repeat steps 2 to 4 to define and add more tabbed panels.





- 6. You can also opt to do any of the following:
 - Rearrange the order of the tabs.
 - Delete a tab by right-clicking on it and selecting **Remove** in the context menu.
- 7. Click the **Save** icon on the toolbar to save the changes.

MANAGING THEMES IN A WORKBOOK


Workbook themes are set of configurable settings that affect all colors and fonts of dashboards and visualizations in a workbook. This configuration also includes setting which among the <u>color palettes</u> will be available for the <u>Color variable</u> in the visualizations. Furthermore, the general colors to be used in visualizations such as axis, background, border, and focus colors can be defined.

On an opened workbook, users can dynamically switch to one of the provided default workbook themes: **Light, Light2023, Dark**, or **Dark2023**. These default themes are independent of workbooks and can be stored externally (e.g., *Themes* folder in the AppData).





Management of the workbook theme is done in the *Theme Settings* pane.



Modifying a Workbook Theme

A user with a Designer role can modify the available themes in a workbook.


Steps:

1. Select the theme to be used in the workbook.




The properties of this theme can be modified on the *Theme Settings* pane.

2. On the *Dashboard and Workbook Settings* pane, click the **Workbook** tab and then the button. The *Theme Settings* pane displays.




3. To select the *Diverging*, *Sequential*, and *Text* color palettes to use within the workbooks, click the **Color Palettes** section to expand.



NOTE

For more information on how to create, <u>modify</u>, <u>duplicate</u>, or <u>delete</u> *Single*, *Sign*, *Text*, *Sequential*, or *Diverging* palettes, refer to the sections below.

- 4. Check the boxes of the provided color palettes that will be included for each category.
- 5. Click the radio button of the preferred Default color palette for each category.
- 6. To set the general colors to be used for visualizations, click the **General Colors** section to expand.




The default general colors will be based on the theme being modified. For the **Light** theme, it is named **GeneralColorsLight**, for the **Dark** theme, it is named **GeneralColorsDark**, for the styles of older workbooks, it is named **GeneralColors<Workbook>** (e.g., **GeneralColorsHow To Actions**), and for the new themes, it is named **General<theme name>**. These default general colors cannot be deleted.

For this example, we will modify the general colors for the Light workbook theme (GeneralColorsLight).

- 7. Click on any of the color boxes to display the *Color* dialog and select or enter the preferred color.
- 8. However, instead of modifying the settings of the default general colors, click It will be added in the *General Colors* drop-down list.

Once saved, in the *Open Workbook layout in Design mode*, when the **Light** workbook theme is selected on the opened workbook, all of the defined general colors will be added as options in the *General Colors* drop-down list of a Color variable in a visualization.

For example:




9. Select any of the duplicate general colors and click

Set default

to make it the default.

- 10. To delete any of the duplicate general colors, select it in the *General Colors* drop-down list and click Remove
- 11. To set the *Foreground*, *Background*, *Primary*, *On Primary*, and *Secondary* colors for the editor style of the **Dark** theme, click the **Editor** section to expand.




You may opt to modify the colors of the following properties:

Property	Description
Foreground	Foreground color of the workbook.
Background	Background color of the workbook.
Primary	Primary color of the workbook.
Secondary	Secondary color of the workbook.


On Primary Foreground color within the primary color.

- 12. Click on any of the color boxes to display the *Color* dialog and select or enter the preferred color.
- 13. To set the shape palettes that can be used with the workbook theme, click the **Shape Palette** section to expand.




For more information in how to <u>create</u>, <u>modify</u>, <u>duplicate</u>, or <u>delete</u> shape palettes, refer to the sections below.

14. To define the default styles of the workbook theme, click **Default Styles** section to expand.




See <u>Default Style Settings of a Theme</u> for more information.

- 15. Click **Force Apply** to reset all local part styles in the workbook.
- 16. To modify the custom style configuration of the parts in the workbook, click **Custom Styles** to expand.




- 17. Click on a custom style of a part to modify the settings.
- 18. Click **Remove** of a custom style to delete.
- 19. To modify the dashboard templates in the workbook, click **Dashboard Templates** to expand.




- 20. Click on a dashboard template to modify the settings then click Update template
- 21. Click **Remove** of a dashboard template to delete.

22. To add a new dashboard template, add parts on the dashboard as placeholders, then click



23. Click **Publish** to publish the workbook theme.

The Publish Theme dialog displays.




- 24. Select the folder or subfolder that you have a permission to publish the workbook theme.
- 25. To replace an existing workbook theme, check the **Replace existing theme** box.



COLOR PALETTES IN A WORKBOOK

The <u>single</u>, <u>sign</u>, <u>text</u>, <u>sequential</u>, and <u>diverging</u> color palettes that are used in text or numeric <u>color variables</u> in visualizations can be created, <u>modified</u>, <u>duplicated</u>, or <u>deleted</u> on the *Color Palettes* section of the *Theme Settings* panel.



NOTE

- A user with a Designer role, can also create, modify, duplicate, or delete color palettes in a workbook on the <u>Color Palettes</u> tab of the <u>Themes</u> page.
- Changes made on the Color Palettes section of the Theme Settings
 pane will only be associated with the inline theme of the workbook in the
 Web client and will not be reflected on the Color Palettes tab of the
 Themes page.

Creating a New Single Color Palette In a Workbook

These are the single colors that will be shared in a workbook for:

- records in Table and Record visualizations for the background, text, or shape
- visual members in Combination visualizations for the background or text

Light and medium single color palettes are provided in Panopticon Real Time, but you can also add new ones.


Steps:

On the Single section, click the Add Palette icor
 The New Single Palette dialog displays.



- 2. Enter the Title then click .
- 3. Click the Color box to display the Color dialog and set the palette color or enter the Hex color code.
- 4. Click Ok

The new single color palette is added in the list (e.g., **Medium Yellow**). Note that it is already included and can be <u>modified</u>, <u>duplicated</u>, and <u>deleted</u>.




Creating a New Sign Color Palette In a Workbook

The Sign color palette is used to signify the positive or negative values in numeric visual members.


Steps:

On the Sign section, click the Add Palette icon
 The New Sign Palette dialog displays.



- 2. Enter the Title then click .
- 3. To set the *Positive Color* (default is **Gray**) and the *Negative Color* (default is **Red**), click the **Color** box to display the *Color* dialog and select the palette color or enter the Hex color code.
- 4. Click Ok

The new Sign color palette is added in the list (e.g., **Red-Green**). Note that it is already included and can be modified, duplicated, and deleted.



Creating a New Text Color Palette In a Workbook


The configuration pane for the *Color* variable changes depending on the column data type.

When a text column is added to the *Color* variable, the configuration pane displays the color associated with each categorical item, as specified with a default color palette (e.g., **Twenty Eight Colors**).

Steps:

1. On the *Text* section, click the **Add Palette**

The Next Text Palette dialog displays.



- 2. Enter the Title.
- 3. Select the Number of Colors in the drop-down list. Default is 28 colors.

The Other list is updated accordingly.

4. Click the Color box to display the Color dialog and set the other colors or enter the Hex color code.



The new text color palette is added in the list (e.g., **Sixteen Colors**). Note that it can be deleted.

Text					0	
Include Name						
~	Coffee Bean	0	d'	Ф	Ü	
~	Fourteen Colors	0	d'	Ф	Ü	
~	New Text Palette	0	d'	Ф	Ü	
~	Panopticon BI	0	d'	Ф	Ü	
~	Seven Light Colors	0	·	Ф	Ü	
~	Seven Standard Colors	0	·	Ф	Ü	
~	Sixteen Colors	0 .	1	Ф	Ü	
~	Spectral	0 .	1	Ф	Ü	
~	Sunshine	0 .	1	Ф	ŵ	
~	Twenty Eight Colors	0	1	Ф		
	Twenty Eight Colors Print	0	, de	Ф		
~	Vintage	0 .	1	凸	Ŵ	

Creating a Sequential or Diverging Numeric Color Palette in a Workbook

Panopticon visualizations support two types of Numeric Color Palettes: Sequential and Diverging.

Sequential Color Palettes

Sequential palettes use a two-color gradient between a minimum and a maximum value. Numeric column containing only positive values default to a Sequential Palette using the White-Blue color palette.

In this case the range Mid point is disabled, and the Min and Max points are populated with defaults from the data set.

Diverging Color Palettes

Diverging Palettes use a three-color gradient between a minimum, middle and a maximum value. Numeric columns containing both positive and negative values default to the Diverging Palette with the Red White Blue color palette selected.


Diverging Palettes use the Range Midpoint. The Min, Mid and Max points are populated with defaults from the data set.

To create a new sequential numeric color palette:

1. On the Sequential section, click the Add Palette icon.



The New Sequential Palette dialog displays.




- 2. Enter the *Title* and click .
- 3. Select the Number of Colors in the drop-down list. Default is 4 colors.

The number of colors from Min to Max is updated accordingly.

- 4. Set the *Outliers*, *Min*, and *Max* colors. Click the **Color** box to display the *Color* dialog and set the colors or enter the Hex color code.
- 5. Click Ok

The new sequential numeric color palette is added in the list and can be <u>deleted</u> (e.g., **Yellow-Orange**).




To create a new diverging numeric color palette:

1. On the *Diverging* section, click the **Add Palette**



The New Diverging Palette dialog displays.




- 2. Enter the *Title* and click .
- 3. Select the *Number of Colors* in the drop-down list. Default is **7** colors.

The number of colors from Min, Mid, to Max is updated accordingly.

4. Set the *Outliers*, *Min*, and *Max* colors. Click the **Color** box to display the *Color* dialog and set the colors or enter the Hex color code.



The new diverging numeric color palette is added in the list and can be <u>deleted</u> (e.g., **Yellow-White-Red**).



Modifying Color Palettes in a Workbook


Any of the included or checked color palettes can be modified.

NOTE

- For the selected default color palette, only the Number of Colors and assigned colors can be modified.
- Color palettes that are not selected cannot be modified.

Steps:


Click the Edit icon of an included or checked color palette.
 The corresponding dialog box displays.



- 2. Modify the Title, Number of Colors, and colors.
- 3. Click to commit the changes or for the standard color palettes click revert to the original settings.

Creating a Duplicate of a Color Palette

Click the **Duplicate** icon of a color palette. A copy of the color palette is added in the list (e.g., **Fourteen Colors 1**).




You can opt to modify the settings.

Deleting Color Palettes in a Workbook

New or duplicate color palettes can be deleted. Click the **Delete** icon to remove the color palette in the list.

SHAPE PALETTES IN A WORKBOOK

Shape palettes that can be used with the workbook theme can be created, modified, duplicated, or deleted on the *Shape Palettes* section of the *Theme Settings* pane.



NOTE

- A user with a Designer role, can also create, modify, duplicate, or delete shape palettes in a workbook on the Shape Palettes tab of the *Themes* page.
- Changes made on the Shape Palettes section of the Theme Settings
 pane will only be associated with the inline theme of the workbook in the
 Web client and will not be reflected on the Shape Palettes tab of the
 Themes page.
- Panopticon is shipped with two shape palettes (Default Shape Palette and Arial).


Creating a New Shape Palette in a Workbook

Steps:




1. Click Add Palette

A new shape palette displays (i.e., **ShapePalette.0**).




2. Click ShapePalette.<Number>.

The section expands to allow its definition.



- 3. Enter the shape palette *Title* and click \checkmark .
- 4. To make this shape palette the default for the workbook theme, tap the **Default Palette** slider to turn it on.




5. To add the shapes, click +



You can either:

- · click on a shape.
- Add SVG
 click
 Add SVG
 Select one or more SVG files in the Open dialog box that displays.

The added shapes are displayed.



To delete a shape, click it's corresponding **Delete** icon.

- 6. Select the Defauilt Shape in the drop-down list.
- 7. Click the Save icon on the toolbar.
- 8. When saved, the ontification is displayed.


The new shape palette is available in the *Shape Palette* drop-down list in the *Shape variable* when the workbook theme, where it is added, is used (i.e., **Light**).

Modifying Shape Palettes in a Workbook

Any of the shape palettes can be modified.

Steps:


1. Click on a shape palette to expand.



- 2. You can modify the following properties:
 - Title
 - Default Palette. Tap to enable or disable.
 - Add Shapes
 - Default Shape
- 3. Click the **Save** icon on the toolbar to save the changes.
- 4. When saved, the ontification is displayed.

Creating a Duplicate of a Shape Palette

Click the **Duplicate** icon of a shape palette. A copy of the shape palette is added in the list (e.g., **Default Shape Palette 1**).



You can opt to modify the settings of this duplicate copy.

Deleting Shape Palettes in a Workbook

Any shape palette can be deleted except the default. Click the **Delete** icon to remove the shape palette in the list.

WORKBOOK TOOLBAR

Panopticon Designer provides several toolbar options:

on the Open Workbook in Design Mode




on the Open Workbook in View Mode






Setting	Description
Data Refresh	Manually refreshes the data.
Pause Real-Time	Clicking the icon changes it to and pauses the streaming data sources.
Copy Image	Exports the whole dashboard image to the clipboard.
Create PDF Report	Set the dashboards that will be included in the PDF report. NOTE: This feature is enabled when the workbook changes are saved.
Bookmarks	Add and manage bookmarks.
Alerts	Manage alerts and notifications.
Copy	Copy a visualization or part.
Cut 🔏	Cut a visualization or part.
Paste 🖹	Paste a copied or cut visualization or part.
Undo / Redo	Once Undo is clicked, the Redo icon is enabled, which allows the reversal of the undo.
Workbook Issues	Lists the issues in the workbook.




Also, before the list of available dashboards in the workbook is the **Back** icon




Click this icon to go back to the Workbooks and Folders Summary page.

If the workbook is not yet saved, a notification displays.




You can either click:



Copying Dashboard Image

Steps:

Click the Copy Image icon on the toolbar.
 The Copy to Clipboard button displays.



2. Click to copy and paste the whole dashboard image to another application.


Ad Hoc PDF Generation

Select the dashboards to be included in the generated PDF.




Steps:

Click the Create PDF Report icon on the toolbar.
 The PDF Settings dialog displays.



- 4. Select the dashboards to be included:
 - All dashboards
 - Current dashboard
 - Selected

The checkboxes are enabled and all the dashboards are checked by default.



Check only those that will be included in the generated PDF.

Some visualizations show a portion of the available content adding scroll bars. E.g., table, horizon graph, etc.

- The final two options of the dialog relate to these visualizations.
- 5. To output all the content within a visualization that has scroll bars, for example, to output all the rows within a table, check the **Create multiple pages to show all data items** box.
- 6. To hide scroll bars from the output PDF pages, check the Hide scroll bars box.
- 7. Click button to start the PDF generation.



This will allow Panopticon Real Time to read all the datasets necessary to output the dashboard and produce the PDF file.




Ad hoc PDF generation in the Web client using Google Chrome (or other browsers) may be hindered by the AdBlock Extension.

To remove the AdBlock Extension in Google Chrome, perform these steps:

- 1. Click the **Chrome Menu** icon on the browser toolbar.
- 2. Highlight *Tools*, then click Extensions from the sub-menu.
- 3. Click Remove in the AdBlock Plus entry (e.g., uBlockOrigin).
- 4. Click **Remove** in the confirmation message that displays.

Bookmarking

Bookmarks are saved configurations of the active dashboard and workbook. A bookmark can be added, by authenticating, and clicking on the **Bookmarks** \square icon.



Bookmarks are not available with anonymous access workbooks.

Bookmarks do not save data, but do save the selected:

- Dashboard
- Parameters
- □ Filters
- Breakdowns, Hierarchies, Visible Depth, and Drill Level
- Variables (Size, Color, X, Y, etc.)

Consequently, although the underlying data may change, a specific view of that data can be specified and bookmarked for future usage.


Bookmarks can be added and are available to all authenticated users of the workbook.

Bookmarks also generate a unique URL, which can be sent to another individual with access, allowing them to see exactly the same view of the selected dashboard.


New bookmarks can be added by clicking the New




A new instance of the bookmark is added under the *My Bookmarks* section in the *Bookmarks* pane. The bookmark is initially named **<Workbook> - <Dashboard> - Bookmark<number>**.



Click **Modify** icon to define the settings of the bookmark. The *Bookmark Settings* pane is displayed.



Property	Description
My Bookmarks	User's own bookmarks.
Shared Bookmarks	Bookmarks shared to the user.
Delete Bookmark	Remove the bookmark.




Viewing and Fixing Workbook Issues

You can view and fix workbook detected issues which may include:

- wrong column type, missing column values, or missing columns in a data table used in a visualization
- missing data table in Actions


Steps:

Workbook issues are signified with icon on the toolbar.




2. Click . The list of all of the detected workbook issues is displayed.

For this example, there are three issues.




3. Click on an issue. The variables or parts with detected issues are highlighted with red font or border. For parts or visualizations, an **Invalid Configuration** error and its cause are displayed.

Example 1: Missing column issue




- 3.1. Click on the variable to view the missing or invalid column value.
 - For this example, the *Column* (**Symbol**) is not available for the Y variable.
- 3.2. Select or define the missing or invalid column. Once fixed, the issue is removed from the list.




4. Click on a Workbook issue, if available.

Example 2: Missing data table in Actions issue


All of the actions along with visualizations with missing data table are highlighted.



4.1. Click the Workbook tab on the Dashboard pane. The Actions pill is displayed with a red border and the actions with missing data table are displayed in red. The part or visualization is also displayed with an Invalid Configuration error and its cause.



4.2. You may need to <u>define</u> the missing data table and select for the actions and visualizations which are marked with an error. Once fixed, the corresponding issues are removed from the list.



ALERTING

The Alerts function allows a notification to be sent when the data in a visualization has met the predefined settings. If alerts are required to be sent via email, the following properties must be configured first in the Panopticon.properties file.

Property	Alert
Attribute	alert.creation.only.by.administrators
Description	Enable or disable whether only Administrators can create alerts.
Default Value	false
Property	Alert
Attribute	email.address
Description	The email address where the alert will be sent from.
Default Value	
Property	Alert
Attribute	email.password
Description	The email password, if available.
Default Value	
Property	Email
Attribute	email.host
Description	The host name used by the email server.
Default Value	
Property	Email
Attribute	email.port
Description	The port number used by the email server.
Default Value	

Otherwise, when trying to enable an alert, this error will be displayed:

Alerts can not be enabled:

 Sender email settings not set in Panopticon.properties file. Please contact server administrator.

OK


Save the updated file and restart Tomcat.


Setting Up Alerts on the Web Client

Alerts can be defined against:

- Streaming data sources (including CEP Engines and message queues)
- □ Periodically refreshed data sources (like Oracle, SAP Sybase, SQL Server, and so on)


Alert definition can be done by right-clicking on a streaming numeric or text data in a visualization in the Web client and setting the limits, duration, what will be included, how many and when an email will be sent.






Steps:


1. Open a workbook on the *Workbook and Folders Summary* page and right-click on a streaming numeric or text data in a visualization. Select *New Alert* on the context menu.



The Alerts dialog displays with the name of the visualization where the alert will be set.



Sample Text Alerting




Sample Numeric Alerting

2. Enter or select the following properties:

Property	Description
Name	Name of the alert.
Description	Description of the alert.
Variable	Available variable columns in the visualization where the alert is set.
Condition	Allows setting the following <i>Limit</i> of all the available numeric variables in the visualization: Upper or Equal To (<=)
	 Lower or Equal To (>=) Upper values (<) Lower values (>) Between – values between the <i>Lower</i> and <i>Upper</i> values For text variables, there are four types of conditions:


Equals - The string is equal to another string, e.g., Country=Sweden Not Equals - The string is not equal to another string Wildcard: The string matches a wildcard expression, e.g., Country=Norwa* would match Country=Norway Regex: The string matches a regex expression, e.g., Country=I[a-zA-Z]+a would match Country=India and Country=Indonesia For the Last	Not Ed Wildca Count Reges zA-Z]-	quals – The string is not equal to another string ard: The string matches a wildcard expression, e.g., ry=Norwa* would match Country=Norway The string matches a regex expression, e.g., Country=I[a-	
second(s)	For the Last Checks if a	a would match Country=India and Country=Indonesia	
Parameters Available parameters in the visualization. The maximum number of times an alert will be sent on the set Date/Time unit: second(s) minute(s) hour(s) day(s) Send E-mail Determines when an alert email will be sent: on enter on leave on enter/leave If unchecked, the notification will only be displayed on the Web client. Include Determines whether the image of the visualization or dashboard will be included in the alert email. For the included image of the visualization, check the Use current drill path box to generate a drilled image in the email. CC CC mailing groups that will receive the alert, separated by a comma. Sound The sound that will be played for a triggered alert. The available sounds are mp3 files placed in the AppData/Sounds folder (i.e., C:\vizserverdata\Sounds). Panopticon is shipped with one sound (i.e., bell_ping_1s.mps). Sound Webhook alarm_clock beep_short bell_ping_1s Default is None.	minutehour(s	d(s) e(s) s)	
Action Limit The maximum number of times an alert will be sent on the set Date/Time unit: second(s) minute(s) hour(s) day(s) Send E-mail Determines when an alert email will be sent: on enter on leave on enter/leave If unchecked, the notification will only be displayed on the Web client. Include Determines whether the image of the visualization or dashboard will be included in the alert email. For the included image of the visualization, check the Use current drill path box to generate a drilled image in the email. CC CC mailing groups that will receive the alert, separated by a comma. The sound that will be played for a triggered alert. The available sounds are mp3 files placed in the AppData/Sounds folder (i.e., C:\vizserverdata\Sounds). Panopticon is shipped with one sound (i.e., bell_ping_1s.mps). Sound Webhook alarm_clock beep_short bell_ping_1s Default is None.	Breakdown Current bre	eakdown of the visualization.	
unit: second(s) minute(s) hour(s) day(s) Send E-mail Determines when an alert email will be sent: on enter on leave on enter/leave If unchecked, the notification will only be displayed on the Web client. Determines whether the image of the visualization or dashboard will be included in the alert email. For the included image of the visualization, check the Use current drill path box to generate a drilled image in the email. CC CC mailing groups that will receive the alert, separated by a comma. Sound The sound that will be played for a triggered alert. The available sounds are mp3 files placed in the AppData/Sounds folder (i.e., C:\vizserverdata\Sounds). Panopticon is shipped with one sound (i.e., bell_ping_1s.mps). Sound Webhook alarm_clock beep_short bell_ping_1s Default is None.	Parameters Available p	parameters in the visualization.	
 on enter on leave on enter/leave If unchecked, the notification will only be displayed on the Web client. Include Determines whether the image of the visualization or dashboard will be included in the alert email. For the included image of the visualization, check the Use current drill path box to generate a drilled image in the email. CC CC mailing groups that will receive the alert, separated by a comma. Sound The sound that will be played for a triggered alert. The available sounds are mp3 files placed in the AppData/Sounds folder (i.e., C:\vizserverdata\Sounds). Panopticon is shipped with one sound (i.e., bell_ping_1s.mps). Sound Webhook Active Hours Default is None. 	unit: secon minute hour(s	d(s) e(s) s)	
included in the alert email. For the included image of the visualization, check the Use current drill path box to generate a drilled image in the email. CC CC mailing groups that will receive the alert, separated by a comma. The sound that will be played for a triggered alert. The available sounds are mp3 files placed in the AppData/Sounds folder (i.e., C:\vizserverdata\Sounds). Panopticon is shipped with one sound (i.e., bell_ping_1s.mps). Sound Webhook alarm_clock beep_short bell_ping_1s Default is None.	on enton leaon ent	ve ver/leave	
Sound The sound that will be played for a triggered alert. The available sounds are mp3 files placed in the AppData/Sounds folder (i.e., C:\vizserverdata\Sounds). Panopticon is shipped with one sound (i.e., bell_ping_1s.mps). Sound Webhook alarm_clock beep_short bell_ping_1s Default is None.	included in For the inc	the alert email. luded image of the visualization, check the Use current drill	
are mp3 files placed in the AppData/Sounds folder (i.e., C:\vizserverdata\Sounds). Panopticon is shipped with one sound (i.e., bell_ping_1s.mps). Sound Webhook alarm_clock beep_short bell_ping_1s Default is None.	CC CC mailing	CC mailing groups that will receive the alert, separated by a comma.	
Webhook Webhooks that will be executed when the alert is triggered.	are mp3 fil C:\vizs sound (i.e. ✓ Sound Webho	es placed in the AppData/Sounds folder (i.e., erverdata\Sounds). Panopticon is shipped with one , bell_ping_1s.mps). ok alarm_clock beep_short Hours bell_ping_1s	
		Webhooks that will be executed when the alert is triggered.	
Active Hours Determines when an alert should be active. Proceed to step 3.	<u>Webhook</u> Webhooks	that will be executed when the alert is triggered.	

3. Check the **Active Hours** box. The dialog changes to display:



By default, the duration is from 9:00 AM to 5:00 AM on Monday, Tuesday, Wednesday, Thursday, and Friday.

To modify the Active Hours, click
 The Clock settings display.



- 5. Select the Hour, Minutes, and AM/PM settings.
- 6. To modify the Active Days, check the boxes of the desired days.
- 7. To apply the active hours in another time zone, select the desired value from the *Show in Timezone* drop-down list box.

Once set, the From and To limits will be applied for that time zone. If not set, the server default time zone will be used.

- 8. Tap the Activated slider to turn it on.
- 9. Click . The new alert is added on the *Alerts* page.

NOTE When creating alerts for grand total, ensure that no breakdown is set.

An alert displays with the following properties or settings:

Property	Description
Title	Name of the alert that was entered in the <i>Alerts</i> dialog.
Workbook	The path and name of the workbook where the alert was set.
Dashboard	The dashboard name where the alert was set.
Created By	The author of the alert.
Creation Time	The Date/Time when the alert was set.
Enabled	Determines if the alert is enabled (or active).
Status	Status of the alert.
Times Triggered	The number of times the alert was triggered.
Sent Emails	The number of emails sent.
Notifications	The number of notifications sent.
Triggered Webhooks	The number of triggered webhooks.

You can then opt to perform any of the following operations:

- Sort alerts
- Search for alerts
- Enable an alert
- Modify alerts
- Delete alerts
- Display active alerts
- Deactivate/activate all alerts
- View triggered alerts
- Import alerts
- Export alerts


Sorting Alerts

By default, the list of alerts is sorted by Title in an ascending order. You can modify the sorting of the list by clicking


the or button of the *Title, Workbook, Dashboard, Created By, Creation Time, Enabled, Status, Triggered, or Triggered Today* columns. The icon beside the column that was used for the sorting will indicate if it was in an ascending or descending order.

Searching for Alerts


To search for a particular alert, enter it in the Search box.




You can also enter one or more characters into the *Filter Applications* box and the suggested list of alerts that matched the entries will be displayed.



Enabling Alerts on the Alerts Page



Tap the **Enabled** slider to turn it on.




Enabling alerts can also be performed on a visualization's Alerts panel.


Other Alerts operations can be modified, enabled, and deleted in the workbook where it was set.

Displaying Active Alerts

Tap the **Show only active alerts** slider to turn it on.




Only the active or enabled alerts are displayed on the **Alerts** tab.




Activating or Deactivating All Alerts

Alerts can be activated or deactivated in one click.

To activate all deactivated alerts, click **Activate All** . All of the deactivated alerts are activated.



To deactivate all activated alerts, click **Deactivate All** . All of the activated alerts are deactivated.






Viewing Triggered Alerts

View the details of all the triggered events of activated alerts.

Steps:

1. Click the Alert Events tab on the Alerts page.

The Alerts Triggered Events page displays with the following information.



Property	Description
Trigger Time	The Date/Time when the alert was triggered.
Title	Title of the alert.
Description	Description the alert.
Workbook Name	The workbook name where the alert was set.
Dashboard	The dashboard name where the alert was set.


- 2. You can also do any of the following options:
 - Click or of a column title to sort the list.
 - Enter a triggered alert title in the Search box to do a search.
 - Click to delete a triggered alert.
 - Click
 Clear All to clear the list.
 - Click a **Title** link to go to the workbook where the alert was triggered.

Importing Alerts

Allows you to import alerts shared by other others.

Steps:

On the Alert Definitions tab, click the Import Alerts icon.
 The Upload Alert dialog displays.



- 2. To upload an alert, do one of the following:
 - Drag the file from your desktop and drop on the dialog, or
 - Click Choose alert and then browse and select one on the Open dialog that displays.



A notification displays once the color palettes file is uploaded.

Click Close the dialog. The uploaded color palette is added in the list.

Exporting Alerts

Allows you to download alerts.

Steps:

- 1. On the Alerts list, select the checkbox of the alerts you want to export.
- Click Export Alerts icon.

The selected alerts are downloaded.

Modifying Alert Settings

Steps:

- Open a workbook with an alert and click on the Alerts icon.
 The Alerts panel displays with the list of alerts.
- 2. Click an alert to modify.

The Alerts dialog displays.

3. Make the necessary changes then click




Deleting Alerts

Alerts can be deleted on:

- the Alerts panel
- an Alerts dialog
- the Alerts tab

Deleting Alerts on the Alerts Panel:


Open a workbook with an alert and click on the Alerts icon.
 The Alerts panel displays with the list of alerts.



2. Check the box of an alert and click the **Delete** icon. You can also check several boxes to delete multiple alerts.

Deleting Alerts on an Alerts Dialog:

Open a workbook with an alert and click on the Alerts icon.
 The Alerts panel displays with the list of alerts.




- 2. Click an alert. The Alerts dialog displays.
- 3. Click the **Delete** icon

Deleting Alerts on the Alerts tab:


1. Go to the Alerts tab.

The Alerts tab displays the list of alerts.



2. Click the of an alert to delete.

A confirmation message displays.



3. Click Yes


Enabling Alerts

Alerts can be enabled either on:

- the Alerts panel
- an Alerts dialog


Enabling Alerts on the Alerts Panel:

Open a workbook with an alert and click on the Alerts icon.
 The Alerts panel displays with the list of alerts.



2. Tap the **Activated** slider to turn it on.

Enabling Alerts on an Alerts Dialog:



- 2. Click an alert. The Alerts dialog displays.
- 3. Tap the Activated slider to turn it on and click OK.

Sample Email Alerts

An alert is generated when the alert set state changes from Off to On and recorded in the alert history.

An alert is only issued by email if the alert has not already been sent in the last 'n' minutes as defined in the *Alerts* dialog.

When an alert is issued, an email is sent to the defined email address.

The email includes:

- Link to the workbook or dashboard
- Condition and limit value
- □ Breakdown
- Name of the visualization where the alert was set
- PNG image of the visualization or dashboard


Dashboard: http://localhost:8080/panopticon/workbook/#/ecs kx/Visual

Condition: Sum(fills) >= 10.0

The alert was triggered by the following items:

algotype:Opportunistic, algoname:Liquidity Driven, sym:O12989, ordername:SIX-NOVN SELL 797k


Visual > Order Map




Sample Web Client Alerts

When an alert is triggered, aside from the email notifications, a visual indication or pop-up in active Web clients will draw attention to the alerting visualization or dashboard.

In the example below, an alert initially displays highlighted in blue:




The alert eventually fades away and the pop-up screen fills up with the four latest triggered alerts.




The pop-up stays on screen until it is closed by clicking the button.

Saved alert notifications can be opened on the *Notifications* panel by clicking the ____ icon.



Clicking on a notification highlights the item in the workbook that triggered the alert.




Click the button to delete a notification or click to delete all of the notifications.

Sample Webhook Alerts

In Panopticon, outgoing webhooks can be added (based on incoming webhook URLs from other systems) and used as a channel for sending messages about triggered alerts, similar to how such messages can also be sent by email.

Webhooks that will be executed when the alert is triggered, can be selected in the Alert dialog.




Below is the list of special server parameters available for webhooks that are attached to an alert.


Parameter Name	Description	Value
_alert_title	Returns the alert title.	Alert1


_alert_dashboard_url	Returns the URL to the dashboard where the alert was created.	http://localhost:8080/panopticon/workbook/#/Workbook1/Dashboard1
_alert_description	Returns the alert description.	Example alert description.
_alert_reason	Returns the reason(s) the alert was triggered. The reasons are presented as all alert conditions and their limits.	Sum(usdunfilledvalue) >= 1.0, Sum(fills) >= 1.0
_alert_triggering_items	Returns all items that caused the alert to be triggered. The items are comma separated and each individual item is presented in square brackets.	[algotype:Opportunistic, algoname:Liquidity Driven, sym:O13052, ordername:L-BP. SELL 40k], [algotype:Opportunistic, algoname:Liquidity Driven, sym:O12828, ordername:L-SRP SELL 6k]

USING THE OPEN WORKBOOK IN VIEW MODE


Users with a Designer role will have the following toolbar options on the Open Workbook in View Mode.








For users with an Administrator, Viewer, or Anonymous role, the toolbar options will only include:




On the *View Mode*, users can interact with the workbook using the visualization right-click <u>context menu</u>, <u>header controls</u>, shelves, variables and cross tab options. Most of these controls and the amount of interactivity are also available in the <u>Design Mode</u>.

Context Menu

Panopticon provides a right-click Context Menu in each visualization.



Visualization Context Menu



Visualization Context Menu of the Numeric Axis

- /	
7	Update Window
4	Update Focus Time
	Set snapshot here
	New Alert
	Exclude Time
	Drill to Top
	Copy Image
	Copy Data
	Export Raw Data
	Zoom
	Zoom out
	Show Shelves
	Pin Details
	Unpin All
	Data Log

Time Series Visualization Context Menu of the Time Axis

4	News on Company
4	Reuters Stock Quote
	New Alert
	Include Item
	Exclude Item
	Drill Down
	Drill to Top
	Copy Image
	Copy Data
	Export Raw Data
	Copy Cell Data
	Show Shelves
	Pin Details
	Unpin All
	Data Log

<i>4 4</i>	News on Company Reuters Stock Quote
	New Alert
	Drill to Top
	Copy Image
	Copy Data
	Export Raw Data
	Adjust Column Width
	Adjust All Column Widths
	Hide
	Show Shelves
	Unpin All
	Data Log

4	News on Company
4	Reuters Stock Quote
	New Alert
	Exclude Item
	Copy Image
	Copy Data
	Export Raw Data
	Show Sub Totals
	Show Grand Total
	Show Name
	Expand All
	Collapse All
	Show Shelves
	Unpin All
	Data Log

Table visualization context menus depending on where you click on the visualization

The visualization context menu options include:

Setting	Description
Automatic Parameterization	Run an automatic parameterization.
Action	Run a workbook action on the visualization.
New Alert	Create an alert.
Visualization Filtering	Allows visualization filtering. Options include: Include Item Exclude Item Exclude Time Clear
Drilling	Allows drilling into visualizations. Options include: Drill Down Drill Up Drill to Top
Data Export	Allows exporting of data. Options include:

	 Copy Image Copy Data Export Raw Data Copy Cell Data
Zooming	Allows zooming in and out of visualization sections.
Set Axis Range	Allows setting the numeric axis range (Dynamic or Fixed).
Show Shelves	Turned off by default. Check to allow the cross tab, breakdown, and variables to be displayed.
Pinning	Allows pinning of the <u>Details</u> pop-up. Options include: Pin Details Unpin Unpin All
Data Log	Displays execution meta data of the visualization.

The additional time series visualization context menu options include:

Setting	Description								
Set Snapshot Here	Available in the time series visualization context menu when the Snapshot Grid Line is rendered or set to Dotted , Dashed , or Solid in the Time Axis variable.								
Set Axis Range	Allows setting of the	time axis range:	:						
	Min Range	minutes	0						
	Increment Step	minutes	0						
	Min Range The minimum time axis range. Supported units are milliseconds, seconds, minutes, hours, days, months, quarters, and years.								
	Increment Step								
	Controls how much the time axis span is extended at the point when the latest value is at the end of the current time axis span. Supported units are milliseconds, seconds, minutes, hours, days, months, quarters, and years.								
	This setting helps in seeing how a real-time data set grows from left right along the time axis, giving a better impression and understand of the progress.								


The additional Table visualization context menu options include:

Setting	Description
Adjust Columns	Adjust column width in the table visualization.
Hide / Unhide Columns	Hide or display columns in the table visualization.
Show Hierarchy Column	Display the hierarchy column.
Expand / Collapse Hierarchy	Expand or collapse sections of the hierarchy.

Show Grand Total	Determines whether the Grand Total aggregate row is shown in the table.					
Show Sub Totals	Determines whether Sub Total aggregate rows are shown in the table.					
Show <column></column>	Display the breakdown column.					

Visualization Filtering

Visualizations themselves can be used as filters by selecting items, and right-clicking to display the context menu with these three options:




- □ **Include Item** filters the dashboard to include the selected items.
- **Exclude Item** filters the dashboard to exclude the selected items.
- Clear removes any visualization filters.



In the Web client, the *Include Item* and *Exclude Item* options are disabled when there is no breakdown or the root is selected in visualizations.

For time series visualizations, an additional option is available.



Exclude Time filters all the series to exclude the time point/s.

When a visualization filter is applied, filter icons appear at the left of the filter column title and on the toolbar of the dashboard. Clicking or will remove the filter.

Also, the **Show Active Filters** icon displays on the toolbar. This allows <u>viewing of all the active filters</u> on the dashboard and its visualizations.

Drilling into Visualizations

Visualizations themselves can be used to drill into lower or upper details by selecting items, and right-clicking to display the context menu with three options:



Drill Down – Drills down to the lower level of the selected value.

NOTE

Drilling without filter (or soft drill) is turned on for all aggregates that refer to:

- Nodes above the node like the parent or root
- Siblings of the node

Applicable to the following aggregates in the *Aggregate* drop-down list:

- Sibling Rank
- Percent of Total
- Percent of Total Reference
- Percent of Parent
- Percent of Parent Reference
- Percent of Total Change
- Cumulative Sum
- Cumulative Sum By Max
- Drill Up Enabled when the lower level of the selected item is displayed. Click to drill to the upper level.
- □ Drill to Top Drills to the top level of the selected value.

Drilling into visualizations can also be done by double-clicking on a value. Refer to <u>Double Click Mode Options</u> for more information.

Data Export

The data in a visualization can be exported and copied to a clipboard for future use in another application. In addition, the raw data of the visualization can also be exported.

Visualization Level data is exported by right-clicking on the visualization to display the context menu with two options:

Copy Image Copy Data Export Raw Data

For the Table visualization, Copy Cell Data is also available which allows copying of a single cell.


Copy Image
Copy Data
Export Raw Data
Copy Cell Data

The data exported will be what appears on screen, or in a linked table. Specifically, all the columns that appear in the Detail pop-up, including:


- Only those items that are visible (for example, items that have not been filtered)
- □ Same Visible detail (or depth) level displayed in the visualization.



Data for a single item can be exported by selecting the item.



Right-clicking and selecting Copy Data on the context menu displays the Copy to Clipboard button.




Click to copy and paste the data to another application such as MS Excel.



If **Export Raw Data** is selected, all the data from the source data table is exported, and not just the actively displayed nodes within a visualization.

Right-clicking and selecting Copy Image on the context menu displays the Copy to Clipboard button.



Click Copy


to copy and paste the whole dashboard image to another application.

Rubber Band Zoom and Selection

Rubber Band Selection allows multiple items to be selected or lassoed by defining an area with the mouse. When selected, the mouse pointer is displayed as a crosshair. Clicking and dragging the mouse defines the selected area in grey. Once confirmed the selected items are highlighted.


Rubber Band Selection is supported for the Network Graph and other visualizations that have:

- Numeric X and Y axes
- Date/Time X and Y axes






Mouse pointer has been dragged to define an area of interest.



After

The selected items are highlighted.



After selection


To unselect, click on any part of the visualization

Rubber Band Zoom is supported for visualizations that have:

- □ Text axes
- Numeric X and Y axes
- Date/Time X and Y axes


NOTE

- Rubber band zoom is available on all visualizations except Shapes.
- When the cross tab consists of two Text axes, Rubber Band Zoom is not available.




During

Mouse pointer has been dragged to define an area of interest.



After

Selected items are zoomed in and the **Zoom Out** icon has is displayed.





To revert to the original state of the visualization you can either:



Zooming In and Out with Mouse Wheel

You can use the mouse wheel to zoom in and out on the visualization.






Panning Around Within the Zoomed Area


Clicking on the zoomed area turns the mouse pointer into . Drag the mouse to pan around the zoomed area.

Setting Numeric Axis Range



For most of the visualizations with numeric axis, you can set the visible range for the Y and/or Y variable which can either be calculated dynamically (the default, enabled **Dynamic**).

Right-click on a Y or X axis and select **Select Axis Range** in the context menu.



The Range dialog displays.



NOTE Some of the visualizations have the **Always Include Zero** box. Check to let the axis scale start at zero and grow to any number that may show up in the data.

Or set between predefined limits by clicking **Fixed**. This displays the *Min* and *Max* text boxes that are populated with the default values taken from the data set.




You can opt to enter new Min and Max values.

Variable Visibility

Variable visibility defines whether the visualization cross tab, breakdown, and variable shelves are displayed.


This function is often useful in creating simple views for public websites or executive dashboards.

By default, Show Shelves is turned off.




Click Show Shelves to turn it on. The shelves are displayed.

Stacked Bar Graph (Horizontal)




Pinning Details Pop-up


Pinning keeps *Details* pop-up displayed in visualizations which supports easy tracking of some items of interest. Right-click on a visualization item and select **Pin Details** in the context menu.



The Details pop-up is displayed and pinned.




Repeat until you pin all of the Details pop-up that you want to display.



To unpin, you can either click or right-click on the item and select **Unpin** on the context menu. Select **Unpin All** in the context menu to remove all of the pinned *Details* pop-up.

Display the Execution Meta Data

View the last query/parameters that has been executed for a visualization by right-clicking on it and selecting **Data Log** in the context menu.



The execution meta data is displayed with the following details:



- Data table title
- □ Data source name, response time, and duration (ms)
- Available parameters in the data table
- Logs of the execution meta data

NOTE

In Panopticon version 2023.0, query logging is only implemented for the Kx kdb+connector.



Adjust Column Width in the Table Visualization

For the table visualization, the width of the columns can be automatically adjusted to fit the contents of a column or all of the columns.

Right-click on a column name and then select either:


Adjust Column Width



The column width is adjusted.



Adjust All Column Widths



All of the column widths of the table are adjusted.



Aside from selecting either of these context menu options, you can also manually drag the **Left-Right** arrow to widen or reduce the width of the columns.

Hover on a column border, the Left-Right arrow displays.



Drag the arrow to the desired width.




Hide or Display Columns in the Table Visualization

Table visual members can be hidden and displayed again. To hide a column, right-click on a column name and select **Hide**.



To display the hidden columns, right-click any of the visual members and select **Unhide Column>**




Displaying a Hierarchy Column in the Table Visualization




Industry	Supersector	Symbol	Mcap(USD)	1 Day Chang	1 Week Chan	1 Month Cha
Grand Total			\$14,776,798,934,247	-5035.40%	-4268.90%	14084.90%
⊞ Basic Mate	erials Total		\$889,465,969,106	-611.30%	-516.20%	1726.50%
⊡ Consumer	Goods Total		\$1,860,384,194,222	-642.00%	-334.80%	1518.80%
	∃Automobile	es & Parts To	\$328,426,116,057	-307.10%	-157.50%	445.00%
		0203.HK	\$1,820,170,747	-4.50%	-10.40%	25.10%
		3116.T	\$912,071,761	-9.40%	-4.10%	4.50%
		5101.T	\$1,239,086,057	-3.40%	3.10%	21.00%
		5108.T	\$9,723,912,200	-6.70%	-3.90%	-0.50%
		5110.T	\$1,257,373,228	-5.80%	-0.90%	2.00%
		5334.T	\$1,595,314,832	-7.00%	-2.90%	9.80%

Additionally, the right click context menu includes options for Expand All and Collapse All



However, when the **Virtual Mode** option is turned on in the <u>Table Settings</u>, the table will be in a flat mode and the expand and collapse options will no longer be available.






Expanding and collapsing can also be done by selecting specific items to display. Right-click on the item and then select *Show < Item>* on the context menu.


Additional Table Operations

Adjust Width of the Text Axis Leaf in Table Visualizations

In the Table visualization, you can adjust the width of the Text axis leaf by dragging the **Left-Right** arrow \iff . For example, in the Table below, the data or fields of the leaf are not fully displayed.



Hover on the border of the Text axis leaf and drag the Left-Right arrow to the desired width.



Move Columns in the Table Visualization

Move or re-arrange the columns by dragging them either to the left or to the right.




		Flat Table of Company Performance									
Name	Close(local)	Mcap(USD)	1 Month Cha		1 Week Chan	Day Chang	2 Week Chan	2 Week Chan	1 Month Cha	2 Month Cha	3 Month Cha
3i Group PLC	2.71	\$1,488,911,563	•		1.40%	3.80%	29.00%		35.20%	19.00%	2.00%
3M Co.	49.72	\$31,869,237,156	•		0.80%	-1.20%	4.70%	1	7.30%	-7.60%	-13.00%
77 Bank Ltd.	487.00	\$1,855,149,668	•		-2.90%	-5.80%	7.20%		5.60%	-4.10%	-9.10%
A.P	24,600.00	\$4,742,697,140	•		-8.10%	-1.00%	7.00%	I	-9.50%	-9.20%	-17.80%
A2A S.p.A.	1.14	\$1,906,029,009	•		-5.20%	-4.40%	14.10%		-0.20%	-12.90%	-15.60%
ABB Ltd.	15.89	\$32,461,622,181	•		-1.70%	1.20%	2.30%		16.10%	7.10%	-5.60%
Abbott	47.70	\$73,392,451,232	•		-2.20%	2.40%	-0.30%		-5.70%	-14.00%	-10.30%
ABC-Mart Inc.	1,892.00	\$556,753,517	•		-2.90%	-6.30%	1.00%		-10.40%	-42.10%	-47.50%
Aberdeen As	1.27	\$1,310,061,051	•		-9.50%	-0.10%	0.80%		-5.00%	-1.50%	21.50%
Abertis	11.77	\$4,574,542,373	•		-4.00%	-1.10%	6.70%	I	7.90%	-4.00%	-12.30%
Accenture Lt	27.49	\$17,063,968,693	•		-13.30%	-0.60%	-0.60%		2.80%	-5.60%	-8.10%

					Flat T	able of Company	Performance			
Name	Close(local)	Mcap(USD)	1 Day Chang	2 Week Chan	2 Week Chan	1 Month Cha	1 Week Chan	1 Month Cha	2 Month Cha	3 Month Cha
3i Group PLC	2.71	\$1,488,911,563	3.80%	29.00%		35.20%	1.40%	•	19.00%	2.00%
3M Co.	49.72	\$31,869,237,156	-1.20%	4.70%	I	7.30%	0.80%	•	-7.60%	-13.00%
77 Bank Ltd.	487.00	\$1,855,149,668	-5.80%	7.20%		5.60%	-2.90%	•	-4.10%	-9.10%
A.P	24,600.00	\$4,742,697,140	-1.00%	7.00%	I	-9.50%	-8.10%	•	-9.20%	-17.80%
A2A S.p.A.	1.14	\$1,906,029,009	-4.40%	14.10%		-0.20%	-5.20%	•	-12.90%	-15.60%
ABB Ltd.	15.89	\$32,461,622,181	1.20%	2.30%	Ī	16.10%	-1.70%	•	7.10%	-5.60%
Abbott	47.70	\$73,392,451,232	2.40%	-0.30%		-5.70%	-2.20%	•	-14.00%	-10.30%
ABC-Mart Inc.	1,892.00	\$556,753,517	-6.30%	1.00%		-10.40%	-2.90%	•	-42.10%	-47.50%
Aberdeen As	1.27	\$1,310,061,051	-0.10%	0.80%		-5.00%	-9.50%	•	-1.50%	21.50%
Abertis	11.77	\$4,574,542,373	-1.10%	6.70%	I	7.90%	-4.00%	•	-4.00%	-12.30%
Accenture Lt	27.49	\$17,063,968,693	-0.60%	-0.60%		2.80%	-13.30%	•	-5.60%	-8.10%

Visual Table Sorting

The table visualization additionally supports easy column sorting. Clicking on the column heading will sort on that column throughout the selected hierarchy. Clicking again will reverse the sort order (Ascending → Descending).





Setting Snapshot Time in a Time Series Visualization

A time series visualization consists of a series of time slices, within a defined time window. The snapshot time identifies a particular slice, which can be highlighted further in separate visualizations.

The snapshot is highlighted on the time series visualization through the aid of a vertical grid line.




The snapshot can be selected to focus on particular spikes or abnormalities in the data through either:

- Moving the snapshot on the time filter
- □ Right-clicking on the graph, and selecting **Set snapshot here**




The snapshot will be set for the selected time.

Setting the snapshot can also be displayed on the associated <u>Time Filter Box</u> of a time series visualization.




You can also drag the snapshot line anywhere in the visualization. Hover your mouse on the snapshot line and move it either to the left or to the right.




NOTE

The Set Snapshot Here option is only available in the time series visualization context menu when the *Snapshot Grid Line* is rendered or set to Dotted, Dashed, or Solid in the <u>Time Axis variable</u>.




Visualization Header Controls

Header controls are made available in visualizations when the Header Controls option is turned on.




By default, it is set to **Floating** option. The header controls are displayed when you hover on the upper right corner of the visualization.


How the visualization is displayed:



When you hover on the upper right corner of the visualization:



To always display the header controls, select the **Fixed** option.



Header controls may include:


Header Control	Description
Rubber Band Zoom	Allows zooming in on multiple items of interest in a visualization.
Rubber Band Selection	Allows multiple items in a visualization to be selected or lassoed.
Export Excel	Exports snapshot visualizations to a CSV-format file.
Toggle Display Mode	Displays a visualization as a table and vice versa.
<u>Maximize</u>	Maximizes the visualization to be displayed on the full dashboard area.

Exporting to Excel (TSV-format) of Visualizations

Click the **Export Excel** icon of a <u>snapshot visualization</u>. A copy of the CSV-format tile is downloaded.

Toggling Between a Visualization and a Table

Click the **Toggle Display Mode** icon of a visualization.



It will be replaced with a Table visualization.



From To 👯 Color Char	nge in Comms Size	CommsCount				
From To	Change in C	CommsCount	Date	Change in C	CommsCount	PriorComms
⊡ Aimee La Daren J Far	10	10	12/12/2000	10	10	0
⊟ Alan Com Seabron Ad	2	2	12/12/2000	2	2	0
☐ Al Herrm undisclose	-3	3	12/12/2000	-3	3	6
∃Amazon.c ebass@enr	3	3	12/12/2000	3	3	0
∃Andy Zip John Arnold	3	3	12/12/2000	3	3	0
⊡ Angie Ze Scott Hendr	1	1	12/12/2000	1	1	0
∃An La <an amy_yueh<="" td=""><td>3</td><td>3</td><td>12/12/2000</td><td>3</td><td>3</td><td>0</td></an>	3	3	12/12/2000	3	3	0
∃Ann M Sc Paul Kaufm	2	2	12/12/2000	2	2	0
⊡ Armin Sc Scott Hendr	3	3	12/12/2000	3	3	0
□ ARSyste Sally Beck <	-15	9	12/12/2000	-15	9	24
☐ Beverly B Edward Terry	2	2	12/12/2000	2	2	0
∃Blakes H 'parchitzel	4	4	12/12/2000	4	4	0
⊡ Bobette R lcampbel@	6	6	12/12/2000	6	6	0
☐ Bob M Hall Sally Beck	3	3	12/12/2000	3	3	0
∃Bode Mi 'abenton@	3	3	12/12/2000	3	3	0
	3	3	12/12/2000	3	3	0
Frank L Davis	10	10	12/12/2000	10	10	0
Glenn Kobes	3	3	12/12/2000	3	3	0
Robert Hayes	3	3	12/12/2000	3	3	0
∃ Brad Alford W David Du	3	3	12/12/2000	3	3	0
∃ Brian Red Robert P Vir	3	3	12/12/2000	3	3	0
⊡ Cameron 'eldon@inte	8	8	12/12/2000	8	8	0
'Jeff.Dasovi	24	32	12/12/2000	24	32	8
⊡ Carla Hof Tim Belden	12	12	12/12/2000	12	12	0


The Table details display the same breakdowns of the original visualization and all the visualization detail variables as visible members of the Table.

NOTE The Table will default to displaying zebra stripes.


When the Toggle Display Mode icon is clicked again, the Table will toggle back to the original visualization.

NOTE

- Closing and opening the dashboard will revert to the original visualization.
- Changing dashboard tabs will revert to the original visualization.
- Applying filters on the dashboard will not cause the Table to be toggled back to a visualization but will display the filtered view of the Table. For example: Industry = Basic Materials and Telecommunications





Consequently, toggling back will then display the filtered view of the visualization. The example below will only display Basic Materials and Telecommunications.



Maximize

Visualizations can be maximized to display the full dashboard area by clicking the **Maximize** icon. To return to normal, click the visualization **Restore** icon.






Before clicking Maximize

After clicking Maximize


Drilling Into, Sorting, Removing, Adding, and Swapping Columns in a Breakdown and Cross Tab Points

If there are no available columns added as a breakdown or cross tab *Row* or *Column*, click the corresponding icon to display and select from the list of text columns available on the associated data table of the visualization.

For example:



Right-clicking on a <u>Breakdown</u> column displays this context menu.



Right-clicking on a cross tab Row or Column displays this context menu.




Drilling into Hierarchy Displays

You can drill into cross tab columns, cross tab rows, and breakdown columns.

Steps:

1. Right-click on a column, select **Drill** and then the level you want to drill down into.






The selected level will appear gray.

2. Click the gray item to return to the default view that includes all categories in the data.

CAST GFCF


Removing Breakdown or Cross Tab Columns


Right-click on a column and select Remove Column on the context menu.



Adding Breakdown or Cross Tab Columns

Right-click on a column, select **Add Column** on the context menu and then the column to add. You can filter the list by entering a column into *Search Columns*.






Moving Breakdown Columns

The Move Right or Move Left options are only available when there is more than one breakdown column.


Right-click on a breakdown column and select **Move Right** or **Move Left** on the context menu.

You can also swap or move columns by selecting and dragging them to the preferred hierarchy level.

From: Industry > Supersector > Company



To: Supersector > Industry > Company



Toggling Between Rows and Columns of a Cross Tab

This feature supports the easy swapping between rows to columns, and vice versa in, the pivot points of a cross tab.

In a visualization that is cross tabbed, right-click on row or column and select **Swap Columns and Rows** on the context menu.

The rows and columns will be swapped in the Columns or Rows section of the visualization.

You can opt to revert to the original columns of the *Columns* and *Rows* by selecting the **Swap Columns and Rows** on the context menu.

[6] AXIS GRAPHS

With the 2023.0 release, Axis Graphs were introduced in Panopticon. These new Axis Graphs are the recommended visualization components to use for all use cases that they can meet. The Axis Graphs should be used with priority over the legacy graphs presented in this document, for example the different varieties of bar graphs, needle graphs, and line graphs.

Axis Graphs are different from the visualization parts available since before in Panopticon in the following ways:

The same part can produce several different graph types, such as line, bar, etc.
The same part can display multiple visualization layers superimposed
The same part can display multiple visualizations juxta positioned, i.e., side by side
The same part can use any kind of data type on the main axis: Numeric, Text, Continuous Time, Time Buckets or Time Series Transformed continuous time.

There are two different Axis Graphs: **X-Axis Graph** and **Y-Axis Graph**. As the names imply, X-Axis Graphs use the X-axis as the main axis, while Y-Axis Graphs use the Y-axis as the main axis. For example, a line graph where the line goes from left to right would be created with the X-Axis Graph, while a bar graph where the bars are drawn horizontally would be created with the Y-Axis Graph.

In an Axis Graph, you have the freedom to change from one data column to another on the main axis while designing the graph, even if it means changing from one data type to another. This capability provides full freedom to build graphs in an iterative, exploratory manner. This can be contrasted against the inherent limitation of the legacy visualization parts, which require that the data type of the main axis is decided à priori.

	X-Axis Graph	Y-Axis Graph
Main axis (domain axis)	X-axis	Y-axis
Numeric columns	Yes	Yes
Text columns, nominal mode	Yes	Yes
Text columns, series mode	Yes	Yes
Time Bucket columns	Yes	Yes
Time columns	Yes	No
Time Series Transformed time columns	Yes	No

X-AXIS GRAPH

The following visualization types are available in the X-Axis Graph:

X-Axis Graph	Nominal (Text)	Series (Numeric)	Series (Text)	Time	Time (Time Series Transformed)
Area		Yes	Yes	Yes	Yes
Band		Yes	Yes	Yes	Yes
Bar (Needle)	Yes	Yes	Yes	Yes	Yes
Box Whisker	Yes	Yes	Yes	Yes	Yes

X-Axis Graph	Nominal (Text)	Series (Numeric)	Series (Text)	Time	Time (Time Series Transformed)
Dot	Yes	Yes	Yes	Yes	Yes
Line	Yes	Yes	Yes	Yes	Yes
OHLC		Yes	Yes	Yes	Yes
Order Book					Yes
Waterfall	Yes		Yes		
Constant Reference Line	Yes	Yes	Yes	Yes	Yes
Constant Reference Band	Yes	Yes	Yes	Yes	Yes

Y-AXIS GRAPH

The following visualization types are available in the Y-Axis Graph:

X-Axis Graph	Nominal (Text)	Series (Numeric)	Series (Text)
Area			
Band	Yes	Yes	Yes
Bar (Needle)	Yes	Yes	Yes
Box Whisker	Yes	Yes	Yes
Dot	Yes	Yes	Yes
Line	Yes	Yes	Yes
OHLC			
Order Book			
Waterfall			
Constant Reference Line	Yes	Yes	Yes
Constant Reference Band	Yes	Yes	Yes

CREATING AN AXIS GRAPH

In the instructions below, it is assumed that the X-Axis Graph is used.

Add a Column to the Main Axis

The first step of creating an axis graph of either kind is to select a column for the main axis, called the **domain axis**. This instruction also shows in the empty visualization part: "Add x-axis – Drag and drop columns from the data table to the X pill". Any kind of column can be used, as explained in the table above.

When using text on the main axis, a hierarchic axis can be constructed, by adding several columns you can add for example **Year**, **Quarter**, then **Month** or **Region** then **Product Category**.

Regular text values, by default, will be treated as Nominal values when added to the main axis. This can be changed in the settings under the *X* pill. A text column that is a Time Bucket column generated from a Time column, will by default be treated as Series value. Numeric values and continuous time values are always Series. As shown in the tables above, some visualization types require that the data is Series data.

Add Visual Members

After adding a column to the main axis, the visualization part will show this instruction: "Add visuals – Drag and drop columns from the data table to the Y pill". The column is most often a numeric column but can also be text, in which case, the text values are aggregated as a Count. Several different kinds of visualizations are available to choose from for the visual member columns (e.g., line, bar, etc.). The tables above explain which types of visualizations are available depending on what kind of data columns you have on the main axis.

With Series data on the main axis, which can be numeric, text series, or time, the default visualization is **Line**. With a Nominal type of main axis, the default visualization is **Bar**. After adding a visual member, you can continue making settings on the visual properties. These settings are found on the settings panel of the visual member. The table below shows what settings are available for most commonly used visualization types:

	Bar	Line	Dot	Band	Area	Box Whisker	OHLC	Waterfall
Color	Yes	Yes	Yes	Yes	Yes	Yes	Yes	Yes
Opacity	Yes	Yes	Yes	Yes				
Size			Yes					
Shape			Yes					

Multiple Visual Members

Like legacy combination graphs, axis graphs can show multiple visualizations in layers. Additional visual members are added by repeating the drag-and-drop of data columns to the Y pill. Visual members can be rearranged by drag-and-drop, to control which one is behind and which one is in front.

Group By Setting for the Visual Member

Axis graphs are different from the legacy combination graphs in Panopticon, in how each visual member in the axis graphs has their own *Group By* setting. This means that, in the same graph, one visual member can show an overall total, while another visual member shows data grouped by a dimension in the data, such as Produce Category or Geographic Region. A stacked bar graph is created by making a group by setting on a bar visualization, and an area visualization is best used with a dimension added to the *Group By* setting.

Value Axis Assignment

Each visual member has a setting for assignment to either the left value axis or the right value axis. When two or more visual members are added to a graph, and both the left and the right value axes are enabled, you have a dual-axis graph. The settings for the left value axis and the right value axis are shared by all <u>visual member variables in the same group</u>.

Visual Member Groups

An axis graph can be organized into several sections that share the same main axis, where different visual members are shown in different sections. All visual members that are shown in the same section belong to the same Group. A group is added by pressing the grey tab with a plus sign on the left edge of the settings panel. Groups can be reordered by drag-dropping the group tabs. Each group has its own scaling and settings for the value axis (both left and right). The total available graph area can be evenly or unevenly distributed between the visual member groups. For example, a variable that requires a more detailed value axis scale can be allowed to occupy more screen space. The space given to each group is controlled by pulling the delimiter line between the groups, left of the left value axis.

Tooltip Settings


The settings that control what is showing in the Tooltip or Popup are handled under the *Tooltip* pill. This is slightly different from the legacy visualization parts, where the same settings are handled under a pill called *Details*.


Cross Tabbing


An axis visualization can be sectioned according to values in a text column. By adding text columns to the *Columns* pill and/or *Rows* pill, a grid of multiple visualizations with identical axes is created. The axis visualizations are not using the concept *Items* or *Breakdown*, which experienced users of Panopticon are used to seeing in other visualization parts. The result that other visualizations achieve through the Items setting, is handled to some extent automatically based on the main axis values, and to some extent by the optional Group By-setting of each visual member.


SAMPLES OF AXIS GRAPHS


These graphs can be tried and examined in the **Axis Graphs** example workbook.

































[7] GLOBAL PARAMETERS

Global Parameters are applied by default to open workbooks. It is commonly used for storing parameterized data source connection details, so that they are maintained outside of the workbook.


Users with an Administrator or Designer role can add, modify, or delete global parameters that will pull and enter specific data into the different sets that are assigned to workbook folders, as well as user specific folders for Designers.

For example:




Parameters Set In	Description
Organization's root folder (i.e., Global)	Inherited by all of the available folders and applied to all workbooks
Public root folder (e.g., Global > Orders)	Inherited by the public root folder's subfolders and applied to all public workbooks.
User's root folder (i.e., Global > ~)	Inherited by the user root folder's subfolders and applied to all private workbooks.

For example, an Administrator added these global parameters:



The same global parameters are inherited and displayed for a Designer user:




ADDING GLOBAL PARAMETERS

Follow the steps below to add global parameters with a Designer role.

Steps:

On the Parameters tab, click the Add icon of a global folder (root or subfolder).
 A new parameter entry displays.




- 2. Enter a Name for the new parameter.
- 3. Select the *Type*: **Text**, **Numeric**, or **Time**.
- 4. Enter the Default Value.

You can enter several default values, separated by a comma. Single quotes on parameter value/s are removed when saving global parameters. For the Time type, the following formats for the default value are accepted: "yyyy-MM-dd" "yyyy-MM-ddTHH:mm:ss" "yyyy-MM-ddTHH:mm:ss.SSS"

5. Check the *Encrypted* box to encrypt the value, if required.

NOTE Encryption is only supported for text parameters.


Click . The new parameter is added in the list.
 Global parameters added in the parent/root folder are inherited by the corresponding subfolders.




MODIFYING GLOBAL PARAMETERS


Steps:


On the Parameters tab, click the Edit icon of a parameter.
 The Name, Value, and Encrypted controls are enabled.



2. Make the necessary changes then click .









Deleting Global Parameters

Steps:

On the Parameters tab, click the Remove icon of a global parameter.
 A confirmation message displays.




Refresh Global Parameters




Searching for Global Parameters

To search for a particular global parameter, enter it in the Search box. All of the instances are displayed.



You can also enter one or more characters into the *Search* box and the suggested list of global parameters that matched the entries will be displayed.




[8] ACCESSING WORKBOOKS AND CONTEXT MENU OPTIONS


ACCESSING WORKBOOKS


The Workbooks page lists available folders and uploaded or published workbooks in Grid View.

- ☐ The Folders include their names and the number of available workbooks.
- □ The *Workbooks* include their titles, thumbnail images, and when they were last updated. Refer to <u>Workbooks and Folders Summary Layout</u> for more information.



Clicking on the workbook thumbnail opens it on the Open Workbook in View Mode:






Opened workbooks are then displayed on the Quick Access pane.

SEARCHING FOR WORKBOOKS

Search for particular workbooks that may be located in different folders and perform other operations like merge, copy, download, or remove.

Steps:


- On the Workbooks and Folders Summary layout, click on a workbook folder then enter a workbook name or dashboard name in the Search Workbook box.
- 2. Click →



The following information are displayed for each workbook:

- Folder where the workbook is located.
- What the search match was based on: workbook or dashboard name.
- Date/Time when the workbook was last viewed
- Date/Time when the workbook was last modified


You can also enter one or more characters into the *Search Workbook* box then click **Enter**. The list of workbooks that matched the entries will be displayed.




Click on a workbook thumbnail to open and display it on the Open Workbook in View Mode.


To go back to the Workbooks and Folders Summary layout, click $\stackrel{\longleftarrow}{}$.


You may opt to right-click on a workbook or select several workbooks to display the context menu.





To display the workbook in its location, click **Show in Folder** on the context menu.






The other context menu options are discussed in the sections below.

WORKBOOKS TOOLBAR AND CONTEXT MENU

Moving, copying, merging, and removing workbooks can either be done using:

□ Context menu



□ Toolbar



The Workbooks toolbar options include:

Toolbar Option	Description
Sort By / Sort Order	Allows sorting workbooks by Name or what was Last Viewed.
<u>Display View</u>	Display workbooks either by List View or Grid View.
Copy	Copy a workbook to another folder or subfolder the user has permission to.
Move	Move a workbook to another folder or subfolder the user has permission to.
Merge	Import or merge workbooks.
Remove	Remove workbooks or folders.

The Context Menu options include:

Toolbar Option	Description
Сору	Copy a workbook to another folder or subfolder the user has permission to.
Move	Move a workbook to another folder or subfolder the user has permission to.
Merge	Import or merge workbooks.
Remove	Remove workbooks or folders.

Sorting Workbooks


Sorting workbooks can be done by Name, Last Modified/Last Published, or Last Viewed by Me.

Sorting Option/Column	Default Sort Order
Name	Ascending
Last Modifed	Descending
Last Viewed By Me	Descending
Last Published	Descending

Steps:

On the Folders and Workbooks Summary layout, either:


click the **Sort By** option on the *Toolbar* of the *Grid View* By default, the sorting is by **Name** in ascending order.



• Ascending



□ click on the Name, Last Viewed By Me, or Last Published column header of the List View



Then click the Sort Order.

- Ascending
- Descending


Copying Workbooks

Users with a Designer role are allowed to copy workbooks to another folder or subfolder that they have permission.


Steps:

- 1. On the List or Grid view, select one or several workbooks then:
 - · right-click and select Copy on the context menu, or
 - click the **Copy** icon on the toolbar.

The Copy Workbook dialog displays with the folder or subfolders the user is allowed to copy the workbooks to.




2. Select the folder or subfolder.



3. Click Copy

The workbooks are copied to the selected folder.




Moving Workbooks

Users with a Designer role are allowed to move workbooks to another folder or subfolder that they have permission.


Steps:

- 1. On the *List* or *Grid* view, select one or several workbooks then:
 - right-click and select Move on the context menu, or
 - click the **Move** icon on the toolbar.


The Move Workbook dialog displays with the folder or subfolders that the user is allowed to move the workbook.



2. Select the folder or subfolder.



3. Click Move



The workbook is moved to the selected folder.

Deleting Workbooks or Folders

Users with a Designer role have the ability to remove workbooks or folders.


NOTE

- Folders and subfolders can be deleted as long as they do not contain workbooks.
- Removing folders and workbooks cannot be done simultaneously.

Steps:

- 1. On the *List* or *Grid* view, check the box of workbooks or folders then:
 - right-click and select Remove on the context menu, or
 - click the **Remove** icon on the toolbar.
- 2. Click on the toolbar.

A notification message displays.



Merging or Importing Workbooks

Existing workbooks can be imported into another open workbook, merging their dashboards together.

For example, the *How to Actions* workbook has eight dashboards, while *How to Drill* has two dashboards. Follow the steps below to import the eight dashboards and the associated data tables of *How to Actions* to *How to Drill*.

Steps:

- 1. On the List or Grid view, check the boxes of multiple workbooks then:
 - right-click and select Merge on the context menu, or
 - click the Merge icon on the toolbar.

The Select Merge Target dialog displays.




Select the target workbook (i.e., **How to Drill**) where the dashboards will be imported.



3.

The dashboards and data tables from How to Actions are now added to the How to Drill workbook.




NOTE

Dashboard parts and actions, that reference a data table that needs a new Id/name, will update the data table reference to point to the correct one.

WORKBOOK AND FOLDER CONTEXT MENU

The Workbooks page provides context menu in each folder or subfolder and the workbooks.



Workbook Folder or Subfolder Context Menu

Workbook Context Menu

The Workbooks page context menu options include:

Menu Option	Description
Rename	Rename the workbook or subfolder.
History	View workbook history and republish.
Move	Move a workbook to another folder or subfolder the user has permission to.
Сору	Copy a workbook to another folder or subfolder the user has permission to.
Download	Download a copy of the workbook.
Export Bundle	Export a bundle of the workbook including the data files.
Remove	Delete the workbook or folder.

Additional context menu options are available for the workbook or subfolder:

Menu Option	Description
New Folder	Create a new workbook folder and assign the allowed or denied groups and users.
New Workbook	Create a <u>new workbook</u> .
<u>Upload Workbook</u>	Upload workbooks.
Permissions	Define the <u>allowed</u> or <u>denied</u> subfolder or personal folder permissions.
Import Bundle	Import the folder or subfolder bundle.


Renaming Workbooks or Folders

A user with Designer role can rename workbooks and folders.



Steps:


1. Right-click on a workbook or folder then select **Rename** on the context menu.



Workbook Folder or Subfolder Context Menu

Workbook Context Menu

The Rename Workbook or Rename Folder dialog displays, respectively.




2. Enter a new name then click




Creating Folders

A user with a Designer role can create folders.



Steps:

1. On the **Workbooks** tab, right-click on the personal folder, and select **New Folder**.




The Create Folder dialog displays.



NOTE

- The Designer user is available under the Allowed section by default with Read, Write, and Modify permissions.
- Removing the Designer user will mean they will not have access to this folder and its subfolders.
- 2. Enter a Folder Name.
- 3. Proceed to defining the authorization to <u>Allowed</u> or <u>Denied</u> groups and users.
- 4. Click Create

The new folder is displayed on the expanded Folder hierarchy list and on the Folders/Workbooks list.



NOTE


- Folders and subfolders can be deleted as long as they do not contain published workbooks.
- The folders and subfolders on the *Workbooks* page will also be available on the *Data Library, Webhooks*, and *Themes* pages.

Adding Groups and Users with Allowed Authorization


A user with a Designer role can grant permissions for users or groups to a workbook folder or subfolder.

Steps:

1. Right-click on a folder and select **Permissions** on the context menu.



The Permissions dialog displays.



2. Under the *Allowed* section, click the **Add** icon.

A new User/Group Allowed section is displayed.



3. Select **User** or **Group** to be given permission in the drop-down list.



- 4. Enter the user or group Name.
- 5. Select the permission level that will be granted to the user or group:
 - READ

Permission to read the folder.

READ + WRITE

Permission to write to the folder and read.

MODIFY + WRITE + READ

Permission to read, modify, and write to the folder as well as create subfolders.



6. Click . The user or group is added under the *Allowed* list.



7. You can either:

• check the Apply Permissions to Subfolders box



This means the permissions that will be used on all of the subfolders will be fetched from the parent folder.



- leave the Apply Permissions to Subfolders box unchecked and modify the permission properties of the subfolders
- 8. Click Update to save the changes.


 A user with a Designer role is allowed not to grant himself permission to have access on folders or subfolders. This can be done either by granting permission to users or groups that they are not included or adding himself to the list of <u>denied users or groups</u>.

> You can copy the user names in the *Permissions* dialog by highlighting the text then right-clicking, and selecting **Copy** in the context menu.

Adding Groups and Users with Denied Access

Steps:

1. Right-click on a folder and select **Permissions** on the context menu.



The Permissions dialog displays.



2. Under the *Denied* section, click the **Add** icon.

A new User/Group Denied section is displayed.



- 3. Select **User** or **Group** that will be given denied permission in the drop-down list.
- 4. Enter the user or group Name.
- 5. Select the denied permission level that will be grated to the user or group:
 - MODIFY


Prevent user or group to modify and create subfolders.

WRITE + MODIFY

Prevent user or group to modify and write to the folder.

READ + WRITE + MODIFY

Prevent user or group to modify and create subfolders, modify and write to the folder, as well as read the folder.



6. Click . The user or group is added under the *Denied* list.








Repeat until all of the users with denied access are added.

7. Click to save the changes.


Creating Subfolders

Steps:

- 1. To create subfolders, you can either click a folder:
 - on the expanded Folder hierarchy list




on the workbooks/folders list




The Folders page displays.

2. Right-click on the folder and select New Folder.




Refer to <u>Creating Folders</u> for the steps in creating the subfolders. Also, <u>Adding Groups and Users with Allowed Authorization</u> and <u>Adding Groups and Users with Denied Access</u> for more information on adding Users and Groups with allowed or denied authorization.

The subfolder is added.



3. You can also opt to delete a subfolder by right-clicking on the folder and selecting **Remove** on the context menu as long as it does not contain published workbooks.




A confirmation message displays.




Updating Folder or Subfolder Properties


Steps:

1. To update folder properties, click a folder or a subfolder.






2. Right-click on the folder or subfolder and select **Permissions**.



The corresponding Permissions dialog displays.




- 3. Make the necessary changes such as new folder name, add or delete users and groups.
- 4. You can either:

• check the Apply Permissions to Subfolders box



This means the permissions that will be used on all of the subfolders will be fetched from the parent folder.

 leave the Apply Permissions to Subfolders box unchecked and modify the permission properties of the subfolders




Uploading Workbooks


Users with a Designer role can upload and publish workbooks to the currently selected folder in the Workbooks page.

Steps:

1. On the Workbooks page, click on a folder or subfolder and select Upload Workbook.




The *Upload Workbook* dialog displays.




- 2. To upload a workbook, you can either:
 - drag it from your desktop and drop on the dialog, or
 - click Choose Workbook and select one on the Open dialog that displays.

The name of the workbook is displayed on the uploaded workbook area and in the *Name* box.



- 3. You can opt to rename the workbook.
- 4. To replace an existing workbook, check the **Replace existing workbook** box.
- 5. Click Upload

You will be notified once the workbook is uploaded.



The workbook is added and displayed.

NOTE

- An error message is displayed if the data source schema of the uploaded workbook has not been updated or missing.
- The uploaded workbook will not include the data source. However, if Panopticon Real Time can reach the same folder of the data source, or the workbook has been designed in the same machine, then the data can be viewed.


Viewing Workbook History and Republishing

Aside from opening workbooks, a user with Designer role can also perform the following:

- view the change history of workbooks
- republish an archived workbook to the recent version of Panopticon Real Time
- rename an archived workbook

Steps:

1. On the Workbooks page, right-click on a workbook and select History on the context menu.




The *History of Workbook <Name>* dialog is displayed with the current version of the workbook indicated.



Sort the archival list either through the *Date Modified* or *Modified By* by clicking on the or button.

Also, move to the other pages of the list by clicking on a page or clicking the or button.

2. Click on an archived workbook in the list.



Then click Republish . A notification message displays.

Are you sure you want to republish the earlier version of 'How To Actions'?

Yes

No

3. Click Yes


A notification message displays.

The earlier version of the workbook was successfully republished.

OK



The republished workbook version is added in the history list.




5. You may also opt to rename an archived workbook by entering a new one in the *New Name* box and follow steps 2 to 4 to republish it.

Moving a Workbook


Users with a Designer role are allowed to move a workbook to another folder or subfolder they have permission to.

Steps:


1. Right-click on a workbook and select **Move** on the context menu.



The Move Workbook dialog displays with the folder or subfolders that the user is allowed to move the workbook.



2. Select the folder or subfolder.



3. Click Move


The workbook is moved and displayed on the selected folder.

Copying a Workbook


Users with a Designer role are allowed to copy a workbook to another folder or subfolder they have permission to.

Steps:


1. Right-click on a workbook and select **Copy** on the context menu.



The Copy Workbook dialog displays with the folder or subfolders the user is allowed to copy the workbook to.



2. Select the folder or subfolder.



3. Click Copy

The workbook is copied and displayed on the selected folder.


Deleting a Workbook or Folder

Users with a Designer role have the ability to remove workbooks or folders.



Steps:


1. Right-click on a workbook or folder and select **Remove** on the context menu.



Workbook Folder or Subfolder Context Menu

Workbook Context Menu


A notification message displays.



Downloading a Workbook

A user with a Designer role with READ + WRITE <u>permission</u> to the folder is allowed to download a copy of a workbook available in it.

Right-click on a workbook and select **Download** on the context menu.



A copy of the workbook is downloaded.

Exporting a Workbook or Folder Bundle


Users with a Designer role have the ability to download workbooks or folders and the associated data files.

NOTE


- Data files associated with workbooks will only be included in the download if they are available inside the repository.
- Users will only be able to download workbooks from folders where they have WRITE permission.

Steps:

3. Right-click on a workbook or folder and select **Export Bundle** on the context menu.








Workbook Context Menu

A notification message displays.



The **Include Data Files** box is checked by default. This means the associated workbook data files will be included in the download.

4. Click . A copy of the workbook or folder bundle is downloaded.

Importing Workbook Bundle


Users with a Designer role have the ability to import workbook bundles (*.exz).

NOTE

- Users will only be able to import a bundle to folders where they have WRITE permission.
- Existing workbooks with the same name as the uploaded workbooks will be archived, only if the new workbook differs from the current one.
 Consequently, the uploaded version will be the current one.
- The bundle must not exceed the value set in the property file.upload.size.max.bytes in the Panopticon.properties.
- The exported folder structure is maintained when uploading the bundle. If the folders do not exist on the server, they will be created.
- After importing, if there are duplicate workbook titles, their folder name will prefix the title.

Steps:

5. Right-click on a folder and select **Import Bundle** on the context menu.




The Import Bundle dialog displays.



- 6. To import a bundle, you can either:
 - · drag it from your desktop and drop on the dialog, or
 - click Choose Bundle to Import and select one on the Open dialog that displays.

The name of the selected bundle is displayed on the dialog box.



- 7. To replace existing workbooks, check the **Replace existing workbook** box.
- 8. Click Import

Panopticon Workbook Examples

The AltairPanopticonVisualizationServerWAR_<version number>.zip file includes the bundle of the workbook examples and their associated data files (Examples.exz) that you can import.

These workbooks cover:

- Visualization Guide
- □ Example Use Cases and Sample Dashboard
- Capabilities and How to Guides

Visualization Guide

The example workbook **VizGuide** includes demonstration of all snapshot and time series visualizations with usage guidelines.

Example Use Cases and Sample Dashboards

This section of example workbooks includes:

Sample Workbook	Description
Bond Maturity Screening	Bond universe selection and screening.
Displaying Spreads	Spread calculation on selected instruments.
Equity Analysis	Equity portfolio selection and screening.

Equity Universe Screening	Equity universe selection and screening.
GDP Per Capita	Data displayed as a hierarchy (Treemap), Map with scatter points and Choropleth, with each visual emphasizing different aspects of the dataset.
Nano Executions	Nanosecond accuracy executions.
Olympics	Olympic medals by country, across time.
Order Book	Equity order book imbalance across the S&P 500.
Portfolio Performance	Equity portfolio performance across time, including the playback of performance at each time slice across the 15-month time window.
Shopping Basket Analysis	The display of shopping baskets, constituent products, and the correlation of product purchases based on these baskets. The co-occurrence of products in a basket is demonstrated through use of a self-inner join in the underlying data table.
Supermarket Sales Summary	Supermarket sales and revenues against the target.
US Border Crossings	Periodicity in US border crossings by crossing point.
US Treasury Yield Curves	Demonstrates the manual axis tick marks, time series calculations, Scatter Plot reference lines based off a time series, and the time surface across the last two years.

Capabilities and How to Guides

This section of example workbooks includes:

Sample Workbook	Description
BP Oil Spill Timeline	Use of text time series to display market events, such as news headlines and overlay them on time series displays correlating the event to performance and money flow.
Cross Tab	Display of cross tabbing / trellising into rows and columns across different visuals. Cross tabbing produces a series of trellised smaller visuals which each correspond to a portion of the total dataset as defined by the row and column cross reference.
Financial Time Series	Display of typical financial time series displays such as the Line, OHLC and Candle Stick and Needle graphs for price and volume distributions. Additionally, the time axis of these displays is configured to show either a calendar axis, a working week axis where Saturdays and Sundays are removed, and a working hour axis, where only a defined time range (Monday to Friday) are displayed.
How to Actions	Examples of how to use Navigation action, URL action, and Script action. Using Action Control parts to set values to parameters that are involved in data connections. How to pick up current time window parameter values from time series visualizations, and how to pick up current axes span parameter values from visualizations.
How to Auto Parameterize	Use of parameters and auto-parameterization to pass context automatically between visualizations on the same dashboard. Parameters are passed through right-click or double-click mouse events and cause a new data request behind the target visualization. Unlike filtering, the data request can be pre-defined with parameters reflecting variable components of the pre-defined query, function or stored procedure.

How to Color	Use of the different color settings and properties:
	sequential or diverging numeric color palettes
	categorical text color palettes
	#RGB color source for text columns
	Opacity value for the level of color transparency/opacity
	colored shapes through the Shape Legend and Color Legend
	 Line shades based on the Opacity value adjustment in the numeric action slider
	 Configured Custom Single color for visual members in the Time Combination graph which are retrieved in the Timeseries Legend
	color background of text columns in the visualization table
	 Special examples including mixing of colors using the Action Dropdown or #RGB color source in the Bar Graph. In addition, setting the color gradient or quadrants on the background image, and color codes that are added to the data by using join.
How to Conflate	Use of fixed or auto conflation for time series data sets.
How to Drill	Automatic and manual drill configuration, demonstrating the use of double-clicking to drill through the levels of hierarchy orgranularity of a visualization, and the use of restricted "Level of Details" display, where only a certain number of hierarchy levels can be displayed at a single time, and drilling transverses these levels.
How to Filter	Using filter boxes with Numeric, Text, and Time Series columns. Demonstrating both categorical text filters for specified dimensions, with either selection or wild card entry, and numeric filters for measures, which either demonstrate the range (min to max) and distribution or focus on the distribution with a percentile scale. In addition, visualizations can be used as filters by selecting items and either including or excluding them.
How to Maps	Showing features of the map plot visualization as well as an example of how to use the SVG shapes visualization to create a choropleth map.
How to Non Additive	Working with non-additive numbers, where the aggregates must be provided externally, rather than calculated in the product. This example demonstrates single hierarchies, and multiple hierarchies around a defined leaf column. In each case, the data table is configured to specify the leaf column, and the value to check for aggregate presence, while the visuals are set to use external aggregates.
How to OrderBook Transform	The transform settings allow for orders to be reconstructed into an Order Book and standardized by conflating into an appropriate granularity for the output display. This allows playback through its values for compliance customers.
	To reconstruct the Order Book from the orders, the data must include:
	Order ID (Unique per Order)
	Order State/Event Type
	Update Time
	Side (Buy/Sell)
	• Price
	Balance/Remaining Quantity

How to Panel Layout	Shows how to use panels for creating compartments within a dashboard which allow dashboard parts to maximize in a limited way, confined to the space within their panel. Includes dashboards with or without layout panels.
How to PDF	Uses the configured Paper Size and DPI resolution. Setting the resolution of the workbook to match the output resolution from the PDF settings through the Workbook Style, ensures that what is displayed in the web client matches that output in the PDF.
How to Pivot & Unpivot	Pivoting of data for optimum use by dividing them into Dimensions (Text fields), and Measures (Numeric fields). This example shows how key values are displayed when pivoted, or when data is already pivoted, or when an already pivoted data is unpivoted. They are transformed to provide maximum flexibility.
How to Python	Demonstrates the use of Python as a data source and as data transform. Also, the use of Pyro for Python connectivity. With Python, a list of dictionaries is passed.
	This workbook additionally demonstrates enhancing the build in capabilities through Python with the addition of the Numpy and Scipy modules, specifically demonstrating:
	K Means Clustering
	Curve Fitting
	Chi Square Testing
	Of course, the full data manipulation capabilities of Python are made available, rather than that just demonstrated in the example dashboards.
How to R	Includes examples and instructions in using Rserve with Panopticon:
	R environment to use
	Sample data sets from R (i.e., Seatbelts, Volcano)
	Univariate Timeseries Forecasting (ARIMA modelling)
	 Unsupervised Machine Learning in the form of K-means cluster analysis on a synthetic, randomized data set
	Continuous Unsupervised Machine Learning
	Logistic Regression (machine learning classification)
	Multiple Linear Regression (Supervised Machine Learning)
	Anscombe's Quartet of 'Identical' Simple Linear Regressions
	Geographic binning (Interactive transform)
How to Reference Lines	Use of Reference Lines in time series visualizations, both from source columns, and from time series calculations.
How to Retrieve Text and XML	Retrieving Text and XML, together with appropriate parsing from external URLs. This example by design requires a valid direct Internet link, as it retrieves data from external web sites. Delimited text is retrieved based on a parameterized URL and displayed in a time series graph. RSS is retrieved, parsed through the XML connector, and displayed in a table, and RFD is also retrieved through the XML connector making use of XML name spaces in the XPath definitions to extract data from the source XML.
How to Time Window	Example of how to use Time Axis Minimum Range and Time Axis Increment Step with streaming data.

	In addition, time series calculations, based on selected time windows, including time relative calculations such as simple moving averages, time window calculations such as the % Change across the time window, and finally re-baselining of performance values based on a selected time slice (Snapshot).
How to Use JS Dashboard Part	Demonstrates how to include bespoke JS code inside a dashboard such as: how to add a listener for parameter value changes how to update the parameter values data loading This dashboard part also supports loading data from Panopticon Real Time, inside the same data loading framework as the rest of the dashboard.
How to Use Timeseries Data Formats	Time series retrieval, interpolation and display. This example shows how line graphs are drawn between known data points, and how gaps are displayed where there is a time slice, but an unknown value (null). It also demonstrates the use of interpolation to fill the data gap. Finally, the example shows sparse time data similar to that from multiple sensors. As the data is not aligned to a standard set of time slices, the gap displays rules take over the visualization, removing most trends lines. This output is then adjusted to standardize time slices producing appropriate output, where there are values for each series at each given time.
Order Book History	Displays Order Book across time and playback.


[9] WEBHOOKS

A webhook is a special URL that makes it possible to send a message from other systems into the system that issued the webhook. Webhook URLs should be treated with care and not shared publicly, since anyone with knowledge about the webhook URL will be able to use it.

Collaboration platforms such as Microsoft Teams, Slack, and many others, all have support for creating incoming webhooks. In Panopticon, outgoing webhooks can be added (based on incoming webhook URLs from other systems) and used as a channel for sending messages about triggered alerts, like how such messages can also be sent by email. Webhooks added to Panopticon are stored in the server folder structure and are subject to the same permissions model as workbooks.

An outgoing webhook in Panopticon can be used as the message channel for multiple different alerts in multiple different workbooks, due to the parameterization of the webhook request body. The exact structure and content that you should create in the request body of a webhook will be specified in the documentation of the system that issued the webhook.

NOTE Do not expect that the example <u>request body</u> shown below, will work as is.



Property	Description
Search Webhooks	Entering text will filter the webhooks.
Toolbar	Allows copying, moving, and removing of webhooks. Also, to display the webhooks list either on <u>List View or Grid View</u> .
Create Webhooks	Allows creating new webhooks.


Webhooks Context Menu

Allows <u>renaming</u>, <u>moving</u>, <u>copying</u>, <u>deleting</u>, and enabling of the trigger of webhooks.


Folders and Webhooks Display View

Webhooks can be displayed either on a List or Grid View.

On the *Toolbar*, click **Grid View** . The folders and webhooks are displayed as thumbnails.




Or click **List View** , the webhooks are displayed in a standard listing.




On either display view style, clicking on a webhooks title or thumbnail displays the Webhooks page.

Searching for Webhooks

On the Webhooks tab, to search for a particular webhook, enter it in the Search Webhooks box.



You can also enter one or more characters into the *Search Webhooks* box then click **Enter**. The suggested list of webhooks that matched the entries will be displayed.



Click on a webhook to open the settings page.

To clear the filter, delete the text entry in the Search Webhooks box.

CREATING WEBHOOKS

This section discusses the instructions and guidelines to create webhooks.


Steps:

On the Webhooks tab, click on a folder then
 The New Webhook dialog displays.



2. Enter the name of the webhook then click

The new webhook is displayed on the Webhook page.



Create

3. Enter or select the following webhook properties:

Property	Description
Description	Description of the webhook.
URL	URL of the webhook. This property is required.
Headers	A comma separated list of name=value pairs representing HTTP headers.
HTTP Method	Select the appropriate HTTP method for the request from the following options:
	GET ▼
	GET
	POST
	PUT
	DELETE
	GET – retrieve data
	POST – add new data
	PUT – replace existing data
	DELETE – remove existing data
Timeout	Timeout (in ms) for reading a response from the URL.
Content Type	The content type of the request body. Default is application/json.
Request Body	The request body to be supplied to the HTTP call. For example: {
	<pre>'Alert title': '{_alert_title}', 'Alert dashboard URL': '{_alert_dashboard_url}', 'Alert description': '{_alert_description}', 'Alert reason': '{_alert_reason}', 'Triggering items': '{_alert_triggering_items}', 'Timestamp': '{_current_time}', 'Folder': '{_workbook_folder}', 'Workbook': '{_workbook_name}', 'Dashboard': '{_dashboard_name}'</pre>

NOTE

URL, *Headers*, and *Request Body* fields can be parameterized (i.e., <u>special server parameters</u>, <u>alert parameters</u>, and <u>global parameters</u>).



4. Click to save the new webhook.

You may opt to click to trigger the webhook. Any parameter in the request body will be replaced by its value when triggering the webhook request.


For example:

6. Click to go back to the Folders and Webhooks list. The new webhook is added on the list.


WEBHOOKS TOOLBAR AND CONTEXT MENU

Moving, copying, and removing webhooks can either be done using:

Context menu



Webhook Context Menu



Webhooks Folder Context Menu

□ Toolbar













The Webhooks toolbar options include:

Toolbar Option	Description
Sort By / Sort Order	Allows sorting webhooks by Name, Last Modified, or Last Modified By.
<u>Display View</u>	Display webhooks either by List View or Grid View.
Сору	Copy webhooks to another folder or subfolder where the user has permission.
Move	Move webhooks to another folder or subfolder where the user has permission.
Remove	Remove webhooks.

The Context Menu options include:

Toolbar Option	Description
Rename	Rename the webhook.
Move	Move webhooks to another folder or subfolder where the user has permission.
Сору	Copy webhooks to another folder or subfolder where the user has permission.
Remove	Remove webhooks.
Trigger	Trigger the webhook.

Sorting Webhooks


Sorting webhooks can be done by Name, Last Modified, or Last Modified By.

Steps:

On the Webhooks tab, either:

□ click the **Sort By** option on the *Toolbar* of the *Grid View*.

By default, the sorting is by Name.




Last Modified

Then click the Sort Order.



□ click on the Name, Last Modified, or Last Modified By column header of the List View.




Then click the Sort Order.

- Ascending
- Descending

Renaming a Webhook

Steps:

1. Right-click on a webhook then select **Rename** on the context menu.



The Rename Webhook dialog displays.



Rename

2. Enter a new name then click


Moving Webhooks

Users with a Designer role are allowed to move webhooks to another folder or subfolder where they have permission.

Steps:

- 1. On the *List* or *Grid* view, select one or several webhooks then:
 - right-click and select Move on the context menu, or
 - click the **Move** icon on the toolbar.

The *Move Webhook* dialog displays with the folder or subfolders that the user is allowed to move the webhooks. Select the folder or subfolder.



2. Click Move


The webhooks are moved and displayed on the selected folder.

Copying Webhooks

Users with a Designer role are allowed to copy webhooks to another folder or subfolder where they have permission.


Steps:

- 1. On the List or Grid view, select one or several webhooks then:
 - right-click and select Copy on the context menu, or



• click the **Copy** icon on the toolbar.

The *Copy Webhook* dialog displays with the folder or subfolders the user is allowed to copy the webhooks to. Select the folder or subfolder.



2. Click Copy


The webhooks are copied and displayed on the selected folder.

Deleting Webhooks

Users with a Designer role have the ability to remove webhooks.


Steps:

- 1. On the *List* or *Grid* view, select one or several webhooks then:
 - right-click and select Remove on the context menu, or



• click the **Remove** icon on the toolbar.


A notification message displays.



2. Click Yes to remove.

Triggering Webhooks

To trigger a webhook, right-click on it and select **Trigger** on the context menu.



Any parameter in the request body will be replaced by its value when triggering the webhook request.


For example:

{_current_time} - 2021-07-01T12:34:56Z

[10] MANAGING WORKBOOK THEMES

Workbook themes are set of configurable settings that affect all colors and fonts of dashboards and visualizations in a workbook. This configuration also includes setting which among the <u>color palettes</u> will be available for the <u>Color variable</u> or shape palettes for the <u>Shape</u> variable in the visualizations. Furthermore, the general colors to be used in visualizations such as axis, background, border, and focus colors can be defined.

Theme files are independent of workbooks and can be stored externally (e.g., Themes folder in the AppData).




Property	Description
Search Theme	Entering text will filter the themes.
Toolbar	Allows copying, moving, and removing of themes. Also, to display the themes list either on <u>List View</u> or <u>Grid View</u> .
<u>Create Theme</u>	Allows creating new themes.
Theme Context Menu	Allows <u>uploading</u> , <u>renaming</u> , <u>moving</u> , <u>copying</u> , <u>downloading</u> , and <u>deleting</u> themes.


FOLDERS AND THEMES DISPLAY VIEW

Themes can be displayed either on a List or Grid View.

On the *Toolbar*, click **Grid View** . The folders and themes are displayed as thumbnails.




Or click **List View** , the themes are displayed in a standard listing.




On either display view style, clicking on a themes title or thumbnail displays the *Theme* page.

SEARCHING FOR THEMES

On the *Themes* tab, to search for a particular theme, enter it in the *Search Theme* box.



You can also enter one or more characters into the *Search Theme* box then click **Enter**. The suggested list of themes that matched the entries will be displayed.



Click on a theme to open the settings page.

To clear the filter, delete the text entry in the Search Theme box.

CREATING A NEW THEME

Creating a new theme allows setting the colors, fonts, color palettes, general colors, and shape palettes to be used in workbooks and visualizations.

Steps:

1. On the **Themes** tab, click


The New Theme dialog displays.



Create

2. Enter the name of the theme then click

The new theme is displayed on the *Theme* page.



- 3. When creating a new theme, you may specify the following properties:
 - <u>Default Styles</u> Define the default style settings of the workbook, part, visualizations, filter box, action part title, legend title, and actions.
 - <u>Custom Styles</u> Define the settings of the custom styles.


- Color Palettes Manage, import, or export Text, Sequential, and Diverging color palettes.
- General Colors Define or create duplicate general color.
- <u>Editor</u> Define the editor style settings.
- <u>Shape Palettes</u> Define the settings of shape palettes and add, upload, download, duplicate, or remove them.
- <u>Dashboard Templates</u> Update or delete default and new dashboard templates.

Define the Default Style Settings of a Theme

When you define the default settings of a theme, you specify the colors and fonts of the workbook, parts, visualizations, filter box, action part title, legend title, and action form.

Steps:

To define the default styles of the workbook, click Workbook on the Default Styles tab. The Workbook Settings
are displayed.




You may opt to modify the colors of the following properties:

Property	Description
Foreground	Foreground color of the workbook.
Background	Background color of the workbook.
Primary	Primary color of the workbook.
Secondary	Secondary color of the workbook.
On Primary	Foreground color within the primary color.


1.1. You can either:

• click the corresponding *Color* box to display the *Color* dialog to:




- o select the color, or
- o click to enter the values


for RGB



for HSL



for the Hex color code




or enter the Hex color code



1.2. Select the Font.



- 1.3. Specify the Font Size.
- 1.4. Specify whether **Bold** and **Italic**.
- 2. To define the default styles of the parts, click **Part** on the *Default Styles* pane. The *Part Settings* are displayed.



You may opt to modify the colors of the following properties:

Property	Description
Foreground	Foreground color of the parts.
Background	Background color of the parts.
Border	Border color of the parts.

- 2.1. Follow step 1.1 to define the visualization, title, and border colors.
- 2.2. Select the part's Font.
- 2.3. Specify the part's Font Size.
- 2.4. Specify whether **Bold** and **Italic**.
- 2.5. Specify the Padding of the parts.
 - 2.5.1. To modify the *Top*, *Right*, *Left*, and *Bottom* padding values, click

The page updates to display the following fields:




- 2.5.2. Set the desired padding values. If the values are not the same, **Mixed** is displayed in the *Padding* field.
- 2.6. Specify the *Border Radius*. When set to **0px**, the border is displayed as a sharp corner. Setting to higher values makes the border more rounded.
- 2.7. Specify the Margin of the parts.

2.7.1. To define the *Top*, *Right*, *Left*, and *Bottom* margin values, click




- Set the desired margin values. If the values are not the same, Mixed is displayed in the Margin field.
- 3. To define the default styles of the visualizations, click **Visualization** on the *Default Styles* pane. The *Visualizations Settings* are displayed.



You may opt to modify the colors of the following properties:

Property	Description
Foreground	Foreground color of the visualizations and title.
Background	Background color of the visualizations and title.
Border	Border color of the visualizations.

- 3.1. Follow step 1.1 to define the visualization, title, and border colors.
- 3.2. Select the visualization and title's Font.
- 3.3. Specify the visualization and title's Font Size.
- 3.4. Specify whether **Bold** and **Italic**.




- 3.5. Specify the *Border Size* of the visualizations.
- 3.6. Select the visualization title Alignment, Left, Center, or Right.
- 3.7. Specify the *Padding* of the visualizations.
 - 3.7.1. To modify the *Top*, *Right*, *Left*, and *Bottom* padding values, click


The page updates to display the following fields:



- 3.7.2. Set the desired padding values. If the values are not the same, **Mixed** is displayed in the *Padding* field.
- 3.8. Specify the *Border Radius*. When set to **0px**, the border is displayed as a sharp corner. Setting to higher values makes the border more rounded.
- 3.9. Specify the *Margin* of the visualizations.
 - 3.9.1. To define the Top, Right, Left, and Bottom margin values, click




- 3.9.2. Set the desired margin values. If the values are not the same, **Mixed** is displayed in the *Margin* field.
- 3.10. You can opt to define the settings of the *Title Rows*.



By default, there are three title rows. You can do one of the following:


- Click Remove Style to delete, or
 Click Add Title Row Style to add more title rows and define their settings.
- 4. To define the default styles of the filter box, click **Filter Box** on the *Default Styles* pane. The *Filter Box Settings* are displayed.



You may opt to modify the colors of the following properties:

Property	Description
Foreground	Foreground color of the filter box.
Background	Background color of the filter box.

- 4.1. Follow step 1.1 to define the colors of the filter box.
- 4.2. Select the filter box title's Font.
- 4.3. Specify the filter box title's Font Size.
- 4.4. Specify whether **Bold** and **Italic**.




- 4.5. Select the filter box title *Alignment*: **Left**, **Center**, or **Right**.
- 5. To define the default styles of the action part title, click **Action Part Title** on the *Default Styles* pane. The *Action Part Title Settings* are displayed.




- 5.1. Select the action part title's Font.
- 5.2. Specify the action part title's Font Size.
- 5.3. Specify whether **Bold** and **Italic**.

NOTE For the action part title, **Bold** is selected by default.

6. To define the default styles of the legend title, click **Legend Title** on the *Default Styles* pane. The *Legend Title* Settings are displayed.




- 6.1. Select the legend title's Font.
- 6.2. Specify the legend title's Font Size.
- 6.3. Specify whether **Bold** and **Italic**.



7. To define the default styles of the different actions (i.e., Action Form, Action Date Picker, Action Button, Action Dropdown, Action Text Box, Numeric Action Slider), click one and on the *Default Styles* pane to display their corresponding settings.


Most of these actions share the same settings as below:



You may opt to modify the colors of the following properties:

Property	Description
Foreground	Foreground color of the action, button, or slider.
Background	Background color of the action, button, or slider.

- 7.1. Follow step 1.1 to define the colors of the actions.
- 7.2. Select the action and button's Font.
- 7.3. Specify the action and button's Font Size.
- 7.4. Specify whether **Bold** and **Italic**.



- 7.5. Specify the action's border color and size.
- 7.6. Specify the Padding of the actions.
 - 7.6.1. To modify the *Top*, *Right*, *Left*, and *Bottom* padding values, click

 The page updates to display the following fields:



- 7.6.2. Set the desired padding values. If the values are not the same, **Mixed** is displayed in the *Padding* field.
- 7.7. Specify the *Border Radius*. When set to **0px**, the border is displayed as a sharp corner. Setting to higher values makes the border more rounded.
- 7.8. Specify the Margin of the actions.
 - 7.8.1. To define the *Top, Right, Left*, and *Bottom* margin values, click .




- 7.8.2. Set the desired margin values. If the values are not the same, **Mixed** is displayed in the *Margin* field.
- 8. Proceed to the **Custom Styles** tab to specify the <u>custom styles</u> of the theme.

Define the Custom Style Settings of a Theme

Published custom style configuration of a part can be modified in the **Custom Styles** tab and can be applied to other parts.

Steps:

- 1. Click Custom Styles tab. The available published custom styles and properties are displayed.
 - ← StocksTheme




- 2. See <u>Define Default Styles</u> to specify the settings depending on the custom style part.
- 3. Proceed to the **Color Palettes** tab to define the <u>color palettes</u> of the theme.

Define the Color Palettes Settings of a Theme

When you define the settings of the color palettes, you can manage, import, or export Single, Sign, Text, Sequential, and Diverging color palettes.

Steps:

- To select the Diverging, Sequential, Text, Sign and Single color palettes to use within the workbooks, click the Color Palettes tab.
 - ← StocksTheme




NOTE

For more information on how to create, <u>modify</u>, <u>duplicate</u>, or <u>delete</u> Single, Sign, Text, Sequential, or Diverging Palettes, see to the sections below.

- 2. Check the boxes of the provided color palettes that will be included for each category.
- 3. Click the radio button of the preferred *Default* color palette for each category.
- 4. To upload color palettes, click



. The Upload Color Palette dialog displays.



- 5. To upload a color palette, either:
 - drag the file from your desktop and drop on the dialog, or
 - click Choose color palettes file to upload and then browse and select one on the Open dialog that displays


The name of the color palette is displayed on the uploaded color palette area and in the Name box.

You can opt to rename the uploaded color palette.

6. To replace the color palettes, check the Replace Color Palettes box.



A notification displays once the color palettes file is uploaded.



- 8. To export color palettes, click to the desired location.

 Export Palettes


 The .excp file is exported. You can now move this file
- 9. Proceed to the **General Colors** tab to specify the <u>general colors</u> of the theme.

Define the General Color Settings of a Theme


You can specify new general colors or duplicate or remove them.

Steps:


To set the general colors to be used for visualizations, click the General Colors tab.
 By the default, the new General Colors is named GeneralColorsLight.




2. Click **Duplicate** \Box to make a duplicate copy of the new general colors.



- 3. You can enter a new name and click . Set Default is turned off and the Remove icon is now available.
- 4. Tap the **Set Default** slider to turn it on and the **Remove** icon is no longer available.



5. Click any of the color boxes to display the Color dialog.



Select or specify the new general colors: AxisColor, BackColor, BorderColor, FocusColor, ForeColor, MajorGridColor, MinorGridColor, MissingColor, SelectionColor. SnapshotColor,ZebraStripeColor.

Or enter the corresponding Hex color code.

6. Repeat steps 2 to 5 to add more general colors.

Once the new theme is saved and selected in the opened workbook, all of the defined *General Colors* will be added as options in the *General Colors* drop-down list of a *Color* variable in a visualization.


- 7. Select any of the general colors and tap the Set Default slider to make it the default.
- 8. Select any of the general colors that is not set as the default and click **Delete** to remove
- 9. Proceed to the **Editor** tab to specify the editor style of the **Dark** theme.

Define the Editor Style Settings of a Theme

You can define the editor style settings of a dark theme.

Steps:

- 1. To set the Foreground, Background, Primary, On Primary, and Secondary colors for the editor style of the **Dark** theme, click the **Editor** tab.
 - ← StocksTheme




- 2. Click on any of the color boxes to display the *Color* dialog and select or enter the preferred color.
- 3. Proceed to the **Shape Palettes** tab to specify the shape palettes of the theme.

Define the Shape Palettes of a Theme

When you define the shape palettes of a theme, you specify the settings of shape palettes and add, upload, download, duplicate, or remove them.

Steps:

1. To set the shape palettes that can be used with the workbook theme, click the **Shape Palettes** tab.




2. Proceed to the **Dashboard Templates** tab to specify the <u>dashboard templates</u> of the theme.

Define the Dashboard Templates of a Theme


Default dashboard templates are provided in Panopticon. You can modify the name or delete default and new dashboard templates.

Steps:

 To modify the dashboard templates that can be used with the workbook theme, click the Dashboard Templates tab.



- 3. Click on a dashboard template, then you can either:
 - Modify the Title, or
 - Click to delete.
- 4. Click **Save** to save the new theme.
- 5. Clicking the displays the **Themes** tab page with the new theme added in the list.




NOTE

Unlike the default **Dark, Dark 2023, Light,** and **Light2023** themes, new themes can be deleted.

THEMES TOOLBAR AND CONTEXT MENU

Moving, copying, and removing themes can either be done using:

Context menu



The toolbar options include:

Toolbar Option	Description
Sort By / Sort Order	Allows sorting of themes by Name, Last Modified, or Last Modified By.
<u>Display View</u>	Display themes either by List View or Grid View.
Сору	Copy themes to another folder or subfolder where the user has permission.
Move	Move themes to another folder or subfolder where the user has permission.
Remove	Remove themes.

The context menu options include:

Toolbar Option	Description
<u>Upload Theme</u>	Upload theme.
Rename	Rename the theme.
Move	Move themes to another folder or subfolder where the user has permission.
Сору	Copy themes to another folder or subfolder where the user has permission.

Remove	Remove themes.
Reset to Default	Reset to default Dark or Light theme settings.

Sorting Themes


Sorting themes can be done by Name, Last Modified, or Last Modified By.

Steps:

On the Themes tab, either:

□ click the **Sort By** option on the *Toolbar* of the *Grid View*.

By default, the sorting is by Name.




- Name
- Last Modified

Then click the Sort Order.



□ click on the **Name**, **Last Modified**, or **Last Modified By** column header of the *List View*.




Then click the Sort Order.

- Ascending
- Descending


Renaming a Theme

Steps:

1. Right-click on a theme then select **Rename** on the context menu.



The Rename Theme dialog displays.



2. Enter a new name then click


Moving Themes

Users with a Designer role are allowed to move themes to another folder or subfolder where they have permission.

Steps:

- 1. On the *List* or *Grid* view, select one or several themes then:
 - right-click and select Move on the context menu, or
 - click the **Move** icon on the toolbar.

The *Move Theme* dialog displays with the folder or subfolders that the user is allowed to move the themes. Select the folder or subfolder.



2. Click Move

The themes are moved and displayed on the selected folder.


Copying Themes

Users with a Designer role are allowed to copy themes to another folder or subfolder where they have permission.

Steps:

- 1. On the *List* or *Grid* view, select one or several themes then:
 - right-click and select Copy on the context menu, or
 - click the **Copy** icon on the toolbar.

The *Copy Theme* dialog displays with the folder or subfolders the user is allowed to copy the themes to. Select the folder or subfolder.




2. Click Copy

The themes are copied and displayed on the selected folder.

Downloading Themes

On the List or Grid view, right-click on a theme and selected **Download** on the context menu to download a copy.




You can copy this file to the desired location.

Uploading Themes

Users can upload their own workbook themes and also replace existing ones.

Steps:

1. Click on a folder of subfolder where the user has permission to upload a theme then select **Upload Theme** on the context menu.




The *Upload Theme* dialog displays.



- 2. To upload a workbook theme, either:
 - drag the file from your desktop and drop on the dialog, or
 - click Choose theme to upload and then browse and select one on the Open dialog that displays

The name of the workbook theme is displayed on the uploaded workbook palette area and in the Name box.




You can opt to rename the uploaded workbook theme.

3. To replace the workbook theme, check the *Replace Theme* box.



A notification displays once the file is uploaded.




The uploaded theme is added in the *Theme* list.

Deleting Themes

The default themes (Dark, Dark2023, Light, and Light2023) cannot be removed.


Steps:

- 1. Right-click on one or two themes then either:
 - select **Remove** on the context menu, or



• click the **Remove** icon on the toolbar.


A notification message displays.




2. Click Yes

COLOR PALETTES

<u>Single, sign, text, sequential,</u> and <u>diverging</u> color palettes that are used in text or numeric color variables in visualizations can be created, <u>imported</u>, <u>exported</u>, <u>modified</u>, <u>duplicated</u>, or <u>deleted</u> in the **Color Palettes** tab of a *Theme* page.



Text					+
Include	Name				
~	Coffee Bean	0	A. Marie	4	
~	Fourteen Colors	0	, de	4	
~	Panopticon BI	0	A. Marie	4	
~	Seven Light Colors	0	A PART	4	
~	Seven Standard Colors	0	, de	Ф	
~	Spectral	0	, de la	4	
~	Sunshine	0	, de	4	
~	Twenty Eight Colors		, de	Ф	
	Twenty Eight Colors Print	0	A MARK	4	
~	Vintage	0	, di	4	i
Seguenti					_
Sequenti Include	al				+
	al	0	1	6	+
Include	al Name	0	1	8	
Include	al Name Gray	0			
Include	al Name Gray Purple-Orange	0	, e.	<u></u>	
Include	Al Name Gray Purple-Orange White-Blue	0	en.	- - - - - - - - - - -	
Include	Al Name Gray Purple-Orange White-Blue White-Blue-Print	0	1	- B B	
Include V	Name Gray Purple-Orange White-Blue White-Blue-Print White-Green	0	1	- - - - - - - - - - - - - - - - - - -	
Include V	Al Name Gray Purple-Orange White-Blue White-Blue-Print White-Green White-Orange	0	1	- 8 8 8 8 8 8 8 8	



NOTE

Creating, modifying, duplicating, or deleting color palettes can also be done inside a workbook in the Web Authoring. However, these changes will only be associated with the inline theme of the workbook and will not be reflected in the Color Palettes tab of the Themes page in Panopticon Real Time.

Importing a Color Palette


Users can upload their own color palettes.

Steps:

Import Palettes

1. On the Color Palettes pane, click

The Upload Color Palette dialog displays.



- 2. To upload a color palette, either:
 - · drag the file from your desktop and drop on the dialog, or
 - click Choose color palettes file to upload and then browse and select one on the Open dialog that displays

The name of the color palette is displayed on the uploaded color palette area.


- 3. To replace the color palettes, check the Replace Color Palettes box.
- 4. Click Upload

A notification displays once the color palettes file is uploaded.

Click Cancel to close the dialog. The uploaded color palette is added in the list.

Exporting a Color Palette

You can download a copy of any of the color palettes.



Creating a New Single Color Palette

These are the single colors that will be shared in a workbook for:

- records in Table and Record visualizations for the background, text, or shape
- visual members in Combination visualizations for the background or text

Light and medium single color palettes are provided in Panopticon Real Time, but you can also add new ones.


Steps:

On the Single section, click the Add Palette + icon.
 The New Single Palette dialog displays.



- 2. Enter the Title then click 🗸 .
- 3. Click the **Color** box to display the *Color* dialog and set the palette color or enter the Hex color code.
- 4. Click Ok

The new single color palette is added in the list (e.g., **Medium Yellow**). Note that it is already included and can be <u>modified</u>, <u>duplicated</u>, and <u>deleted</u>.




Creating a New Sign Color Palette

The Sign color palette is used to signify the positive or negative values in numeric visual members.

Steps:

1. On the Sign section, click the Add Palette + icon.


The New Sign Palette dialog displays.



- 2. Enter the *Title* then click .
- 3. To set the *Positive Color* (default is **Gray**) and the *Negative Color* (default is **Red**), click the **Color** box to display the *Color* dialog and select the palette color or enter the Hex color code.



The new Sign color palette is added in the list (e.g., **Red-Green**). Note that it is already included and can be modified, duplicated, and deleted.



Creating a New Text Color Palette

The configuration pane for the Color variable changes depending on the column data type.


When a text column is added to the *Color* variable, the configuration pane displays the color associated with each categorical item, as specified with a default color palette (e.g., **Twenty Eight Colors**).

Steps:

On the Text section, click the Add Palette + icon.
 The Next Text Palette dialog displays.




- 2. Enter the Title then click .
- Select the *Number of Colors* in the drop-down list. Default is 28 colors.
 The *Other* list is updated accordingly.
- 4. To set the colors:
 - click the corresponding *Color* box to display the *Color* dialog to:




- select the color, or
- click to enter the values


for RGB



for HSL



for the Hex color code




• or enter the Hex color code



5. Click Ok

The new text color palette is added in the list (e.g., **Sixteen Colors**). Note that it can be <u>deleted</u>.



Creating a Sequential or Diverging Numeric Color Palette

Panopticon visualizations support two types of Numeric Color Palettes: Sequential and Diverging.

Sequential Color Palettes

Sequential palettes use a two-color gradient between a minimum and a maximum value. Numeric column containing only positive values default to a Sequential Palette using the **White-Blue** color palette.

In this case the range *Mid* point is disabled, and the *Min* and *Max* points are populated with defaults from the data set.


Diverging Color Palettes

Diverging Palettes use a three-color gradient between a minimum, middle and a maximum value. Numeric columns containing both positive and negative values default to the Diverging Palette with the **Red White Blue** color palette selected.

Diverging Palettes use the **Range Midpoint**. The *Min*, *Mid* and *Max* points are populated with defaults from the data set.

To create a new sequential numeric color palette:

On the Sequential section, click the Add Palette icon.
 The New Sequential Palette dialog displays.




- 2. Enter the Title and click '.
- 3. Select the Number of Colors in the drop-down list. Default is 4 colors.

The number of colors from *Min* to *Max* is updated accordingly.

4. Set the *Outliers*, *Min*, and *Max* colors. Refer to step 4 of <u>Creating a New Text Color Palette</u> for more information.




The new sequential numeric color palette is added in the list and can be <u>deleted</u> (e.g., **Green-Red**).



To create a new diverging numeric color palette:

On the *Diverging* section, click the **Add Palette** + icon.
 The *New Diverging Palette* dialog displays.




2. Enter the *Title* and click ...

- 3. Select the *Number of Colors* in the drop-down list. Default is **7** colors.
 - The number of colors from Min, Mid, to Max is updated accordingly.
- 4. Set the *Outliers*, *Min*, *Mid*, and *Max* colors. Refer to step 4 of <u>Creating a New Text Color Palette</u> for more information.



The new diverging numeric color palette is added in the list and can be <u>deleted</u> (e.g., **Yellow-White-Red**).



Modifying Color Palettes


Any of the included or checked color palettes can be modified.

NOTE

- For the selected default color palette, only the Number of Colors and assigned colors can be modified.
- Color palettes that are not selected cannot be modified.

Steps:


Click the Edit icon of an included or checked color palette.
 The corresponding dialog box displays.



- 2. Modify the *Title*, *Number of Colors*, and assigned colors.
- 3. Click to commit the changes or to revert to the original settings.

Creating a Duplicate of a Color Palette

Click the **Duplicate** icon of a color palette. A copy of the color palette is added in the list (e.g., **Seven Light Colors 1**).




You can opt to modify the settings.

Deleting Color Palettes

New or duplicate color palettes can be deleted. Click the **Delete** icon to remove the color palette in the list.

SHAPE PALETTES


Shape palettes that can be used with the workbook theme can be <u>created</u>, <u>uploaded</u>, <u>downloaded</u>, <u>modified</u>, <u>duplicated</u>, <u>rearranged</u>, or <u>deleted</u> on the <u>Shape Palettes</u> page.



Creating a New Shape Palette


Steps:

Click Add Palette .
 A new shape palette displays (i.e., ShapePalette.0).



2. Click ShapePalette.<Number>.

The page changes to allow the definition of the new shape palette.



- 3. Enter the shape palette *Title* and click ...
- 4. To make this shape palette the default for the workbook theme, tap the **Default Palette** slider to turn it on.




5. To add the shapes, click +



You can either:

- click on a shape.
- Add SVG . Select one or more SVG files in the Open dialog box that displays. click

The added shapes are displayed.



To delete a shape, click it's corresponding Delete

- Select the Default Shape in the drop-down list.
- ☐ Save Click the Save
- - Saved! When saved, the notification is displayed.


The new shape palette is available in the Shape Palette drop-down list in the Shape variable when the workbook theme, where it is added, is used (i.e., Light).

Uploading a Shape Palette

Users can upload their own shape palettes.


Steps:

1. On the Shape Palettes pane, click The Upload Shape Palette dialog displays.



- 2. To upload a shape palette, either:
 - · drag the file from your desktop and drop on the dialog, or
 - click Choose shape palette file to upload and then browse and select one on the Open dialog that displays.


The name of the shape palette is displayed on the uploaded shape palette area and in the Name box.



You can opt to rename the uploaded shape palette.

3. Click Upload

A notification displays once the file is uploaded.



Click Close the dialog. The uploaded shape palette is added in the list.

Downloading a Shape Palette

You can download a copy of any of the shape palettes.


Click the **Download** icon of a shape palette.

Modifying Shape Palettes

Any of the shape palettes can be modified.

Steps:


1. Click on a shape palette to display its settings.



- 2. You can modify the following properties:
 - Title
 - Default Palette. Tap to enable or disable.
 - Add or delete shapes
 - Default Shape
- 3. Click the **Save** icon to save the changes.

Creating a Duplicate of a Shape Palette

Click the **Duplicate** icon of a shape palette. A copy of the shape palette is added in the list (e.g., **Default Shape Palette 1**).



You can opt to modify the settings.

Rearranging Shape Palettes


The order of the shape palettes can be rearranged.

Steps:


1. Click on a shape palette you want to move.

2. Drag and drop the shape palette to the desired position.





← Dark




3. Click the **Save** icon to save the changes.

Deleting Shape Palettes

Any shape palette can be deleted except the default. Click the **Delete** icon to remove the shape palette in the list.

[11] PANOPTICON RESOURCES

Clicking the user icon on the top right section of the toolbar displays the other Panopticon online resources that users with a Designer role can access.



Select the Language on the drop-down list: English or Japanese.



Resource	Description		
Visualization Guide	Guide to the supported Panopticon visualizations.		
Web Authoring Quick Start Guide	Panopticon Web Authoring Quick Start Guide. Available upon installation.		
Web Authoring Guide	Panopticon Web Authoring Guide which consists of: creating and managing of data tables. building and viewing of workbooks. creating and managing global parameters and alerts. Available upon installation.		
Analyst Client User Guide	Panopticon Real Time documentation for users with a Viewer role which consists of: • viewing and analysing of workbooks • creating, monitoring, and deleting of alerts Available upon installation.		
User Community	Link to the Panopticon User Community page.		
Data Analytics Documentation	Link to the Altair Data Analytics Documentation page.		

[APPENDIX]

SUPPORTED ROLES IN PANOPTICON REAL TIME

Depending on the authentication or user management mechanism used, the role that a user should have been specified and then mapped to a group set in Panopticon.properties.

Property	Description	Default Value
access.administrator.groups	The role that is mapped to the administrator group.	admin
access.default.roles	The default roles applied to all users of the server. For example, if access.default.roles=DESIGNER,ADMINISTRATOR and a user with a VIEWER role logs on to the server, then the user will simultaneously have a VIEWER, DESIGNER, and ADMINISTRATOR roles. A blank value for access.default.roles is equivalent to ANONYMOUS. A blank value or the value ANONYMOUS will NOT block users from authenticating. NOTE: The roles that can be assigned in this property can only be ADMINISTRATOR, VIEWER, ANONYMOUS, and/or DESIGNER. This property is case sensitive.	VIEWER
access.designer.groups	The role that is mapped to the designer group.	designer
access.viewer.groups	The role that is assigned to the viewer group.	

NOTE

- Group sets can be added for a role, separated by a comma.
- To be able to use all of the features of Panopticon Real Time, a user is required to have Designer and Administrator roles.
- When using <u>Altair Units</u> licensing, different user roles will check out different numbers of Altair Units.

Role	Altair Units Draw
Viewer	2
Designer	2 10 when designing workbooks
Administrator	2

SYSTEM REQUIREMENTS

Panop	ticon I	Real Ti	me is supported on these operating systems:
		Linux	
		Windo	ows 10 (64-bit) – For Development Environments Only
		Windo	ows Server 2012 (64-bit)
		Windo	ows Server 2016 (64-bit)
Panop	ticon I	Real Ti	me also requires:
			e Java SE 8, Oracle Java SE 11, Open JDK 8, and Open JDK 11 are supported after installing the indency files that are distributed with Panopticon Real Time.
	NO	TE	Unzip the contents of the dependency package file provided by Panopticon into the <code>TOMCAT_HOME/lib</code> folder to be able to run Altair Panopticon software on JRE 8 and Open JDK 8.
_		-	ne Tomcat 9.0.x
			me is supported for deployment on the following cloud providers:
			Services (AWS)
		oft Azur	
	•		Platform
□ O	racle (Cloud	
C	ontain	erized	deployment with Docker Linux containers is also supported.
Suppo	rted b	rowser	s include the latest version of:
□ G	oogle	Chrom	e
□ Sa	afari		

04.2023

ARO		NIO	DTI	\sim	N N I

For more information on Panopticon and other resources, go to https://www.altair.com/panopticon .