



Altair Panopticon™ v2025.0

STREAMS SERVER INSTALLATION AND REFERENCE GUIDE

### **TABLE OF CONTENTS**

[1] INTRODU	UCTION	1
Acronyms		1
Terminology		
Overview		1
Pan	nopticon Streams Applications	2
Pan	nopticon Streams Operators	3
1	Panopticon Streams Inputs	3
	Panopticon Streams Outputs	4
System Requ	uirements	4
Sys	stem Hardware Requirements	5
ļ	Development / Test	5
;	Small Scale Deployment	5
1	Medium Scale Deployment	5
1	Large Scale Deployment	5
[2] GETTING	S STARTED	6
Setting Up C	Confluent Kafka Enterprise on a Local Machine Using Docker	6
Setting Up Z	ooKeeper, Kafka, and Schema Registry	7
	ditional Notes on Setting Up the Schema Registry	
Setting Up P	anopticon Streams	9
Imp	oorting the Bundle of Example Applications	13
Cor	nfiguration of the Client Properties	13
Licensing		16
Usir	ng Altair Units License in Altair's License Server	16
Usir	ng Managed Altair Units License via Altair One	17
Migration to	Streams Server 2025 from an Older version	20
1.	Copy All Content	21
2.	Delete Old Content	21
3.	One-time Conversion	21
4.	Applications, Data Sources, and Data files	22
5.	Do Not Make Changes on Both Servers	22
6.	Post-migration Cleanup	22
Upgrade		23
[3] AUTHEN	ITICATION	24
Introduction .		24
Mar	pping Users to Roles	24
Tok	(en	26
Tomcat Real	lm	26
Ton	neat Llear Page	27



	Tomcat Memory Configuration for Windows	20
	Tomcat Memory Configuration for Linux	
	Encrypting Passwords in tomcat-users.xml	
	LDAP	
	Active Directory	
SAMI	Active Directory	
	2.0	
O tatili	Example	
Filter	2.00 po	
	Creating a Custom Filter	
Header	,	
[4] PCL	LI: COMMAND UTILITIES FOR PANOPTICON	37
Export	Data Sources	
	Parameters	_
	Example 1: Export data sources from a workbook	
	Example 2: Export data sources from all workbooks example	37
[5] USI	NG ALTAIR PANOPTICON STREAMS	38
Connec	cting to or Disconnecting from the CEP Engine	38
	Connecting to the CEP Engine	40
	Disconnecting from the CEP Engine	40
[6] MAI	NAGING THE STREAMS SYSTEM	41
Viewin	g and Managing Kafka Properties	43
Reload	ing Configurations	44
Loggin	g/Monitoring	44
	View Logs	44
	Setting the Logging Level	47
	Setting the Server Metrics Publisher	47
Schedu	ıling Task to Clear Topic Data	
	Modify a Scheduled Task	50
[7] AU	THORIZATION	51
Sacura	Access	51
Journe	Creating Folders	
	Creating Folders on the Applications Tab	
	Creating Folders on the Data Sources Tab	
	-	
	Adding Groups and Users with Allowed Authorization	55
	-	55 58

[8] MANAGING APPLICATIONS	65
Uploading Applications	66
Folders and Applications Display View	70
Importing an Application Bundle	72
Exporting an Application or Folder Bundle	
Sorting the List of Applications	77
Searching for Applications	78
Renaming Applications or Folders	79
Viewing Application History and Republishing	80
Viewing and Managing Application Topic Usages	82
Clearing the Data In an Application Topic	83
Clearing the Schema in an Application Topic	84
Sorting Application Topics	84
Viewing the Application Data Sources Usage	85
Moving Applications	86
Copying Applications	87
Downloading an Application	88
Deleting an Application	89
Deleting Applications Using the Toolbar	89
Deleting Applications Using the Context Menu	89
Creating a New Application	90
Adding an Operator	92
Adding an Input Operator	93
Example	96
Adding An Aggregation Operator	
Example	101
Building the Expression	
Using the Expression Builder	102
Supported Aggregation Functions	
Converting Timestamp to/from Integer	
Adding a Branch Operator	
Example	107
Example 2	
Adding a Calculation Operator	
Supported Operators and Calculation Functions	
Supported Operators	
Supported Calculation Functions	
Example	
Adding a Conflate Operator	
Example	
Adding an External Input	
Adding a Filter Operator	
Example	
Adding a Join Operator	
Example	
Fixing Broken Joins	
Adding a Metronome Input Operator	137

Example	139
Adding a Python Transform Operator	139
Example	143
Additional Best Practice Recommendations in Using Python with Panopticon	143
Adding a Rank Operator	144
Example	148
Adding a Rekey Operator	148
Example	150
Adding a REST Transform Operator	150
Adding an R Transform Operator	155
Additional Best Practice Recommendations in Using R with Panopticon	158
Adding a Scatter Operator	158
Example	160
Adding a Table to Stream Operator	160
Example	162
Adding a Union Operator	163
Adding an Output Operator	164
Adding Application-specific Properties	166
Example	167
Saving an Application	168
Editing an Application	169
Validating and Fixing Application Issues	170
Starting an Application	171
Starting an Application on the Applications Tab	172
Starting an Application on the Application Page	174
Stopping an Application	178
Stopping an Application on the Applications Tab	178
Stopping an Application on the Application Page	179
IOI MANACINO DATA COURCES	404
[9] MANAGING DATA SOURCES	101
Uploading Data Sources	182
Folders and Data Sources Display View	
Sorting the List of Data Sources	
Searching for Data Sources	
Renaming Data Sources or Folders	
Viewing Application Usages	
Moving Data Sources	
Copying Data Sources	
Downloading a Data Source	
Deleting Data SourceS	
Creating a Data Source	
Common Data Source Settings	
Selecting and Defining the Data Connector File Source	
Defining the Message Type in Data Sources	
Defining the Nessage Type in Data Sources	
Saving or Loading Column Definitions in the Data Sources	
Defining Real-time Settings	
Donling Real-time Octaings	∠ ۱∠

Using the Data Source Toolbar	213
Date/Time Key Elements	214
Creating Email Output Connector	216
Creating InfluxDB 1.x Output Connector	217
Creating JDBC Legacy Output Connector	218
Creating Apache Kafka Output Connector	219
Creating Kx kdb+ Output Connector	220
Creating a MQTT Output Connector	221
Creating a REST Output Connector	222
Creating Text Output Connector	225
Creating ActiveMQ Input Data Source	226
Creating Altair Al Hub Input Data Source	229
Creating Azure Input Data Source	230
Creating AMPS Input Data Source	232
Creating Cassandra Input Data Source	235
Creating DolphinDB Input Data Source	237
Creating DolphinDB – Streaming Input Data Source	237
Creating Google Analytics Input Data Source	239
Creating Google Cloud Input Data Source	241
Creating Google Cloud Pub/Sub Input Data Source	243
Creating an InfluxDB 1.x Input Data Source	247
Creating JDBC Legacy Input Data Source	248
Creating JDBC Input Data Source	252
Creating a JSON Input Data Source	257
Creating Apache Kafka Input Data Source	259
Creating Kx kdb+ Input Data Source	264
Kx kdb+ - Deferred Sync Query	268
Creating Kx kdb+Tick Input Data Source	268
Creating ksqlDB Input Data Source	272
Creating ksqlDB - Streaming Input Data Source	274
Creating MongoDB Input Data Source	275
Row-Wise Array Expansion	279
Column-Wise Array Expansion	280
Bson-Wise Array Expansion	280
Creating MQTT Input Data Source	280
Creating MQTT Publisher Input Data Source	283
Creating MS Excel Input Data Source	284
Creating OneTick Input Data Source	286
Creating OneTick CEP Input Data Source	288
Creating Python Input Data Source	290
Creating RabbitMQ Input Data Source	291
Creating Amazon S3 Input Data Source	294
Creating Rserve Input Data Source	295
Creating Solace Input Data Source	297
Creating Stream Simulator Input Data Source	299
Creating StreamBase Input Data Source	303
Creating StreamBase LiveView Input Data Source	304
Creating Text Input Data Source	306

Creating WebSocket Input Data Source	308
Creating Web Data Input Data Source	310
Creating XML Input Data Source	316
Modifying Data Sources	317
[10] MANAGING DATA PRODUCERS	319
Refresh Data Producers	320
Starting or Stopping Data Producers	320
[11] MONITORING ENGINE METRICS AND APPLICATION TOPICS	321
Managing Topics	323
Filter Topics	324
Sorting the List of Topics	324
Moving to Other Topics List Pages	324
[12] MANAGING PARAMETERS	325
Adding Parameters	325
Modifying Parameters	326
Deleting Parameters	327
Refresh Parameters	327
Sorting the List of Parameters	327
[13] EXAMPLE APPLICATIONS	328
[14] PANOPTICON RESOURCES	330
[APPENDIX]	331
Properties: Streams	331

# [1] INTRODUCTION

Fundamental to understanding Panopticon Streams are these acronyms and terminologies:

# **ACRONYMS**

Component	Description
CEP	Complex Event Processing
PCLI	Panopticon Command-line Interface

# **TERMINOLOGY**

Component	Description
Apache Kafka or Kafka	Used for building the real-time data pipelines and streaming applications. It is horizontally scalable, fault-tolerant, fast and runs in production in thousands of companies.
Apache ZooKeeper or ZooKeeper	A centralized service for maintaining configuration information, naming, providing both distributed synchronization and group services.
Confluent	The free, open-source streaming platform based on Apache Kafka. The Confluent Platform is the complete streaming platform for large-scale distributed environments. Unlike a traditional messaging system or streaming processing API, Confluent Enterprise enables your interfaces to be connected to anywhere in the world and help make decisions with all your internal systems in real-time.
Schema registry	Part of the Confluent distribution package. Stores a versioned history of all schemas and allows the evolution of schemas according to the configured compatibility settings. Also provides a plug-in to clients that handles schema storage and retrieval for messages that are sent in Avro format.
Panopticon Streams	The name of the Panopticon CEP platform.

# **OVERVIEW**

Event processing is a method of tracking and analyzing streams of information of an event, and eventually deriving a conclusion from what transpired. CEP is an event processing method which combines data from multiple sources to infer events or patterns that may demonstrate unusual activities or anomalies, consequently requiring immediate action.

The CEP engine provided by Panopticon is named **Panopticon Streams** and it is built to work with different CEP engines. However, for this version, it will only support Kafka.

Kafka is a distributed streaming platform that lets you publish and subscribe to streams of records. Each record consists of a **key**, a **value**, and a **timestamp** and stores streams of records in categories called **topics**. Kafka is mainly used for two reasons:

- Building real-time streaming data pipelines that reliably get data between systems or applications
- □ Building real-time streaming applications that transform or react to the streams of the data Refer to <a href="https://kafka.apache.org/intro.html">https://kafka.apache.org/intro.html</a> for more information.

Panopticon Streams enables you to create streaming data pipelines which both transforms and reacts to streaming data. Aside from Kafka, it is also using ZooKeeper and Schema Registry that are provided by Confluent. ZooKeeper is a key component when using Kafka since it allows the configuration and management of clusters in the Kafka servers. The Schema Registry stores a versioned history of all schemas used by Kafka and provides a RESTful interface for storing and retrieving Avro schemas.

### **Panopticon Streams Applications**

The main task of Panopticon Streams is to execute and manage streams **applications**. An application describes how data should be piped, transformed, and processed. Applications consist of a set of **inputs**, **operators**, and **outputs** and are described or constructed in an XML file.

It can be viewed as a directed graph with a set of nodes (or operators) and a set of edges (or streams) that are interconnected with each other.

Component	Description
ID	The ID of the application config. It should be the same with the filename when loading an application config from the system.
operators	A list of operators (actions and functions).
Streams	A list of streams that describe the connection and the flow between operators.
properties	Application-specific defined properties.




Figure 1-1. Panopticon Streams Framework

An application can either use **Kafka topics** or **data producers**, which generate data from a data source. The data producer also demonstrates to be the connection between the Panopticon Streams framework and the Panopticon core.

The Panopticon core has data connectors such as Kx kdb+, OneTick, and MS Excel that serve as data sources. Just like the application, the data source is also constructed or described in an XML file.

An application refers to a data source through its ID (or filename). There are several ways to create a data source of an application:

Export data source with the PCLI tool

The PCLI tool extracts the already defined data sources in workbooks and saves them as CEP data sources.

Using Panopticon Streams

### **Panopticon Streams Operators**

An **operator** is a single task responsible for processing the data and publishing it as an output. Currently, Panopticon Streams supports the following operators:

<u>Aggregation</u>
<u>Branch</u>
Calculation
<u>Conflate</u>
External Input
<u>Filter</u>
<u>Input</u>
<u>Join</u>
<u>Metronome</u>
Rank
Rekey
<u>Scatter</u>
To_stream
<u>Output</u>
<u>Union</u>
Python Transform
REST Transform

R Transform

Each operator produces one or more output streams that can be connected and defined as input streams for other operators.

### **Panopticon Streams Inputs**

Panopticon Streams engine allows the combination of multiple data sources and their definition as input channels. The data sources are referred to within Panopticon Streams as **inputs**. The data produced by each input can be processed by one or more operators.

### **Panopticon Streams Outputs**

**Email** 

InfluxDB 1.x

JDBC Legacy

An **output** produces and publishes streams towards a Kafka topic or a **data consumer**. A data consumer is the opposite of a data producer. It consumes the data produced from an output in Panopticon Streams and publishes the data to a data source.

The most common approach is to publish the data to a Kafka topic which eventually can be consumed or used by Panopticon Real Time or other platforms that support Kafka.

Currently, Panopticon Streams supports publishing of the output data to the following data sources:

	Apache Kafka
	Kx kdb+
	Rest
	<u>Text</u>
<u> </u>	VOTEM DECLUDEMENTO
<b>5</b>	YSTEM REQUIREMENTS
•ar	nopticon Real Time is supported on these operating systems:
_in	ux which includes the following distributions and versions:
	Red Hat Linux (RHEL) 9.4
	Debian 11
	Ubuntu 22.04 LTS
	Fedora 40
Nir	ndows operating systems – For Evaluation, Development, and Testing Environments Only
_	Windows 10 or higher (64-bit)
_	Windows Server 2012 or higher (64-bit)
	Williams Colver 2012 of Higher (O4 bit)
Par	nopticon Streams Server also requires:
	Oracle Java SE 17 and Open JDK 17
	Apache Tomcat 10
_	
ar	nopticon Streams Server is supported for deployment on the following cloud providers:
	Amazon Web Services (AWS)
	Microsoft Azure
	Google Cloud Platform
	Oracle Cloud
Sup	oported browsers include the latest version of:
	Google Chrome

□ Safari

# **System Hardware Requirements**

De	velopment / Test
	1 x Dual Core CPU (Hyper Threaded to 4 Cores/Threads)
	8GB RAM
	4GB Disk (Available)
	In Memory Caching limited to available Server RAM
Sm	nall Scale Deployment
	1 x Quad Core CPU Or Equivalent (Hyper Threaded to 8 Cores/Threads)
_	16GB RAM
	4GB Disk (Available)
	In Memory Caching limited to available Server RAM
Иe	dium Scale Deployment
	4 x Quad Core CPU Or Equivalent (Hyper Threaded to 32 Cores/Threads)
	32GB RAM
	32GB RAM 4GB Disk (Available)
	4GB Disk (Available)
	4GB Disk (Available) In Memory Caching limited to available Server RAM
a Laı	4GB Disk (Available) In Memory Caching limited to available Server RAM  rge Scale Deployment
a La	4GB Disk (Available) In Memory Caching limited to available Server RAM  rge Scale Deployment  8 x Quad Core CPU Or Equivalent (Hyper Threaded to 64 Cores/Threads)

# [2] GETTING STARTED

Running Panopticon Streams can either be done with:

- □ a <u>Dockerized Kafka</u> (Confluent Kafka Enterprise platform)
- a local cluster that includes **Zookeeper**, Kafka, and Schema Registry

Follow the steps below corresponding to the platform you are using.

# SETTING UP CONFLUENT KAFKA ENTERPRISE ON A LOCAL MACHINE USING DOCKER

### Steps:

1. Install Docker.

If you install on a Windows machine, you can use Docker Desktop for Windows, see:

https://docs.docker.com/desktop/windows/install/



If you run Docker on Windows, we recommend that you use the WSL 2 backend. If you choose to use Hyper-V instead, make sure that you select Linux containers, and increase the available memory to at least 8 GB.

2. Download the Docker Compose script from Confluent:

https://github.com/confluentinc/cp-all-in-one/raw/v6.0.1/cp-all-in-one/docker-compose.yml

Save this in a convenient location, such as next to the Panopticon Streams directory.

3. Start the Confluent platform from a command prompt in the same directory as the YML file:

```
docker compose up -d
```

This script defines a number of services that together make up the full Confluent platform. Panopticon Streams really only needs zookeeper, broker, and schema-registry.

4. To verify that everything is working, run docker compose ps, and make sure that all services are listed with status running.

Once the Confluent services are up, start Tomcat and Panopticon Streams to build, deploy, and execute your applications.

# SETTING UP ZOOKEEPER, KAFKA, AND SCHEMA REGISTRY

### NOTE

Windows is currently not a supported platform for running Confluent Kafka, ensure that your OS is on the list of supported operating systems:

https://docs.confluent.io/4.0.0/installation/installing\_cp.
html#system-requirements

Before proceeding, you must install and setup the following prerequisites:

- Java JDK 64-bit, version 1.7 or later
- System Environment variable JAVA\_HOME set to the Java JDK 64-bit

### Steps:

- 1. Download one of the Confluent Kafka archives from  $\underline{\text{http://confluent.io/download}}$ .
- 2. Extract the contents of the archive to a new location.
- 3. Below are the top-level folders of the archive:

```
confluent-3.1.1/bin/ # Driver scripts for starting/stopping services
confluent-3.1.1/etc/ # Configuration files
confluent-3.1.1/share/java/ # Jars
```

- 4. Start the ZooKeeper, Kafka and Schema Registry processes in the correct order. Make sure the previous process has been started before continuing to the next one.
  - Start ZooKeeper
    - \$ ./bin/zookeeper-server-start ./etc/kafka/zookeeper.properties
  - Start the Kafka broker
    - \$ ./bin/kafka-server-start ./etc/kafka/server.properties
  - Start Schema Registry

```
$ ./bin/schema-registry-start ./etc/schema-registry/schema-
registry.properties
```

When these three processes have been started, you can now connect Panopticon Streams to your local Kafka cluster to execute and deploy your applications.

For more details, refer to the Confluent Kafka Installation-and Quick Start guides:

- https://docs.confluent.io/3.1.1/installation.html
- https://docs.confluent.io/3.1.1/quickstart.html

When connecting to a Kafka broker on a separate machine, exposing different IP addresses internally and externally, you need to configure KAFKA\_ADVERTISED\_LISTENERS. This is typically the case when running Kafka in a Docker container.

The symptoms of the missing configuration are:

- Panopticon Streams can connect to ZooKeeper and the Kafka Broker
- No data is written to topics

In [Kafka]/etc/kafka/server.properties, uncomment advertised.listeners and replace "your.host.name" with the externally exposed host name or IP address.

```
# Hostname and port the broker will advertise to producers and
consumers. If not set,
# it uses the value for "listeners" if configured. Otherwise,
it will use the value
# returned from java.net.InetAddress.getCanonicalHostName().
advertised.listeners=PLAINTEXT://your.host.name:9092
```

When using the Confluent Docker image, you can pass the KAFKA ADVERTISED LISTENERS as a parameter:

```
docker run -d --restart=always \
--net=confluent \
--name=kafka \
-p 9092:9092 \
-e KAFKA_ZOOKEEPER_CONNECT=zookeeper:2181 \
-e KAFKA_ADVERTISED_LISTENERS=PLAINTEXT://your.host.name:9092 \
-e KAFKA_OFFSETS_TOPIC_REPLICATION_FACTOR=1 \
confluentinc/cp-kafka:5.1.0
```

### Additional Notes on Setting Up the Schema Registry

It is recommended to turn off the compatibility checking in schema registry when used with Panopticon Streams.

To do this, set the Avro compatibility level to **NONE** (as mentioned below) in the schema-registry.properties file.

Then there are three cases depending on how Kafka is deployed:

- On Windows from the ZIP file from Panopticon. Already turned off by default.
- On Linux manually deployed ("bare metal"). Add the following line to ...etc/schema-registry/schema-registry.properties

```
Avro.compatibility.level=NONE
```

■ With Docker Compose using the Confluent images

Add the following line to the environment section of the schema-registry service in docker-compose.yml

```
SCHEMA_REGISTRY_AVRO_COMPATIBILITY_LEVEL: 'NONE'
```

## SETTING UP PANOPTICON STREAMS

Follow the steps and guidelines below to install Panopticon Streams on Windows.

**NOTE** 

If you need to upgrade your previously installed Panopticon Streams, proceed to the <u>Upgrade</u> section.

### Steps:

1. Extract the contents of PanopticonStreamsWAR <version>.zip file to a new location.

This zip file will contain the following files and folder:

- streams.war
- streams.xml
- Examples.apz
- CustomMessageParserExample.zip
- CustomTransformExample.zip
- OpenJDK11Dependencies.zip
- OpenJDK11Dependencies\_README.txt
- User License.rtf
- Panopticon Streams Reference Guide
- examples folder with sample data files and CEP applications and data sources
- 2. Create the AppData folder (i.e., **streamsserverdata**) and ensure that the user account **Local Service** running Tomcat has read/write and execute permissions to this folder.

Example: c:\streamsserverdata

3. Copy the extracted streams.xml file into the Tomcat config folder (\Apache Software Foundation\Tomcat 10.0\conf\Catalina\localhost). This file contains the following information:

Instead of setting the path of the environment variable
 PanopticonAppData on the streams.xml file, you can do so on
 the System Environment Variables. For example:

Variable	New Value
PanopticonAppData	c:\panopticonstreamsdata

- If the directory path is set in both an environment variable and in the streams.xml file, the value set in the XML file will take precedence.
- 4. Copy the streams.war file into the Tomcat webapps folder (\Apache Software Foundation\Tomcat 10.0\webapps).
- 5. Edit the existing tomcat-users.xml file which is available in the Tomcat config folder (\Apache Software Foundation\Tomcat 10.0\conf) and add the entry:

```
<role rolename="user"/>
<role rolename="designer"/>
<role rolename="admin"/>
<user username="viewer" password="viewer" roles="user" />
<user username="designer" password="designer" roles="designer" />
<user username="admin" password="admin" roles="admin" />
```

For more complex authentication and user directory options, see section [3] Authentication.


### **IMPORTANT**

- Before proceeding to step 7, ensure the Tomcat temp folder (e.g., (\Apache Software Foundation\Tomcat 10.0\temp) is available.
- You can opt to choose a different temp folder with the CATALINA\_TMPDIR environment variable. For example:

Variable	Value
CATALINA_TMPDIR	C:\tomcat\dev\temp

6. Start Tomcat to deploy the .war file.

The streams folder is extracted in the Tomcat webapps folder:




The server initializes the AppData directory with an empty content repository and empty subdirectories for other types of data. The Streams.properties file is created with the default server properties.

- 7. Specify the <u>license type</u> that will be used. Use any of the following license types:
  - Volume License file (PanopticonLicense.xml) that must be copied to the designated AppData folder.
  - Altair Units license. Refer to <u>Using Altair Units License in Altair's License Server</u> for more information.
  - Managed Altair Units license. Refer to <u>Using Managed Altair Units via Altair One</u> for more information.
- 8. You should now be able to log on to Panopticon Streams using the following URL:


[Host Name]:[Port]/[Name of your application]

### For example:


http://localhost:8080/streams




Panopticon Streams Server <u>supports different user roles</u>. By default, all users are assigned the VIEWER role. For example, logging on using the viewer user added in step 6, Panopticon Streams Server will only display:



To have full access to all the services, the user is required to have an ADMINISTRATOR role.



A user with a DESIGNER role can create or upload applications and data sources:




### Importing the Bundle of Example Applications

The AltairPanopticonStreamsWAR\_<version number>.zip file includes the bundle file (Examples.apz) of the example applications and their associated data sources and data files.

Follow the instructions in Importing an Application Bundle to import this bundle to Panopticon Streams Server.

### **Configuration of the Client Properties**

Starting with version 2020.1, Panopticon Streams Server generates a streams.json configuration file in the JavaScriptConfiguration directory of the AppData folder (i.e., c:\streamsserverdata).



The default content of the streams.json file has the following objects/names:

```
"baseUrl" : ".",
   "hideAuthenticationButton" : false,
}
```

In the streams.json file, you can control the configuration of the following objects/names:

Object/Name	baseUrl
Description	Location of Panopticon Streams Server.
Default Value	"."
Required	Yes
Object/Name	automaticReconnectOnServerDisconnect
Description	If set to <b>true</b> , then the real time connection (WebSocket or long polling) to the Panopticon server will be automatically reconnected if it is disconnected.
Default Value	false
Required	No
Object/Name	dataLoading.transport
Description	Controls the which transport should be used when viewing log from the server. Valid values are "websocket" and "long-polling". If configured to "websocket", but the WebSocket connection fails, then the web client will automatically fall back to "long-polling".
Default Value	"websocket"
Required	No
Object/Name	maxClipboardLength
Description	Maximum length of text that will be attempted to be put into the system clipboard (copy). If too much text is attempted, then the browser might become unresponsive.
Default Value	500000
Required	No
Object/Name	hideAuthenticationButton
Description	Boolean. Hides the login and logout buttons.
Default Value	false
Required	No
Object/Name	localization.useBrowserLocale

Description	Boolean. If set to true, then the browser navigator.language, navigator.userLanguage on IE11, controls the localization of the UI. Not all languages are supported.
Default Value	true
Required	No
Object/Name	localization.defaultLocale
Description	Locale used if the browser locale is not supported, or if useBrowserLocale is set to false.
Default Value	"en-US"
Required	No
Object/Name	localization.fallbackLocale
Description	Locale used if a resource string is missing from the locale in use. Should be specified if localization.defaultLocale is specified.
Default Value	value of localization.defaultLocale
Required	No
Object/Name	localizationOverride
Description	Nested object with resource strings per language. Used to customize resource strings.
Default Value	
Required	No
Object/Name	logLevel
Description	Controls which types of logs Panopticon will write to the browser dev console. Valid values are: "trace", "debug", "info", "warn", "error" and "silent".
Default Value	"info"
Required	No
Object/Name	showFileUploadUI
Description	Controls the visibility of UI that is used to upload a file to the server.
Default Value	true
Required	No
Object/Name	showLinkToFileUI
Description	Controls the visibility of UI that is used to specify a data file on the server local file system as a data source. Per default, this flag is automatically inserted into the client configuration at runtime.
Default Value	true
Required	No

If there are no config files available on the server, default ones will be created and saved. After that, you can alter them in any way you would like and keep the configuration even if the server is restarted.

## **LICENSING**

#### NOTE

In the Panopticon documentation, HyperWorks Units (HWU) and Hosted HyperWorks Units (HHWU) are now named Altair Units.

In the Panopticon product, these license types are still named HyperWorks Units and Hosted HyperWorks Units.

For more information on Altair Units, visit <a href="https://www.altair.com/altair-units/">https://www.altair.com/altair-units/</a>.

Licensing within Panopticon Streams supports three license types:

- a volume-based XML file (named **PanopticonLicense.xml**), that is used to store all license information for a specific customer, must be copied to the designated AppData folder (i.e., **c:\streamsserverdata**)
- Altair Units license which is available in the Altair's License Server you are connected to (local or over the network)
- Managed Altair Units license via Altair One

The license file type you will use is delivered separately from the installation packages.

### Using Altair Units License in Altair's License Server

If your license source is Altair's License server, it is required to configure certain properties in the Streams.properties file located in the AppData folder or c:\streamsserverdata:

Property	Service authentication level
Attribute	authentication.required
Description	The property that will make the authentication required. It will force the user to login in order to use any of the services provided by the server. Must be set to <b>true</b> .
Default Value	true
Property	Licensing
Attribute	license.hwu.uri
Description	The path where the License Server is running e.g., 6200@191.255.255.0 where the syntax is PORTNUMBER@HOST. If multiple servers are specified, use the ';' semicolon separator sign for Windows and the ':' colon separator sign for Linux.

	NOTE:  If value is not set in the Streams.properties, the environment variable ALTAIR_LICENSE_PATH serves as the backup path and will be used.
Example	For Windows: license.hwu.uri=6200@192.168.5.51;6200@192.168.5.52 For Linux: license.hwu.uri=6200@192.168.5.51:6200@192.168.5.52
Default Value	
Property	Licensing
Attribute	license.mode
Description	The license mode. Possible values are: FILE or HWU. Must be set to <b>HWU</b> .
Default Value	FILE

### For example:

```
authentication.required=true
license.hwu.uri=6200@192.168.5.51;6200@192.168.5.52
license.mode=HWU
```

### **NOTE**

 Panopticon Streams Server supports different user roles which check out different numbers of Altair Units.

Role	Altair Units License Draw	
Designer	10	
Administrator	2	

- Logging in to both Panopticon Real Time and Panopticon Streams Server with the same username levels the unit draw. A total of 10 units are drawn even if the user logs in to both servers.
- Running applications are leveled towards the user who started the application.

### Using Managed Altair Units License via Altair One

Using the managed Altair Units licensing will support simplifying the license management by removing all manual aspects of emailing license files, extending evaluation periods, among others.

In addition, managed Altair Units licensing will help small to medium deployment customers who do not want to host on-premise license server.

Before using Altair Units, it is required to configure certain properties in the  $\underline{\texttt{Streams.properties}}$  file located in the  $\underline{\texttt{AppData}}$  folder or c:\streamsserverdata:

Property	Licensing
Attribute	license.hwu.hosted
Description	Boolean stating if you wish to use Managed or Local Altair Units licensing. Set to <b>true</b> if you wish to use managed licensing.
Default Value	false
Property	Licensing
Attribute	license.hwu.hosted.authorization.username
Description	Username to the Altair One account.
Default Value	
Property	Licensing
Attribute	license.hwu.hosted.authorization.password
Description	Password to the Altair One account.
Default Value	
Property	Licensing
Attribute	license.hwu.hosted.authorization.token
Description	An authorization token generated through the Altair One admin portal. Used to authorize a machine to the managed Altair Units system.
Default Value	

To use the managed Altair Units licensing, set the following properties:

license.hwu.hosted=true
license.mode=HWU
authentication.required=true


• Add the Panopticon application to your Altair One account.

To authorize the machine against the managed Altair Units system, you have two options.

### Option 1


Use an authorization code generated through Altair One:

Log on to Altair One (<a href="https://admin.altairone.com">https://admin.altairone.com</a>) then navigate to User Profile and select Authorized Machines.



# 2. Click Generate Auth Code

The page displays the auth code and a timer indicating the code's expiration.



Click **Copy to Clipboard** to copy the generated auth code.

- 3. Paste the generated code into the license.hwu.hosted.authorization.token property in the Streams.properties file.
- 4. Start the server.

### Option 2

Directly use your Altair One credentials in Streams.properties:

- 1. Enter your Altair One credentials into the license.hwu.hosted.authorization.username and license.hwu.hosted.authorization.password properties in the Streams.properties file.
- 2. Start the server.

#### **NOTE**

- If a token is entered, this will be tried first. If the token was invalid or not present, and credentials are present, the credentials will be used to authorize the machine towards the managed Altair Units system.
- In Option 1, the generated auth code is only valid for 15 minutes and you should restart your server within that timeframe to properly get access to your licenses.
- In Option 2, Altair One credentials are only required at first restart of the server to generate the auth token and should be removed from the Streams.properties file going forward to avoid exposing these credentials.
- A working Internet connection is required to use Altair Units licensing.
- If your company uses proxy, you might need to add exception in your proxy to allow access to the Managed Altair Licenses.

Please refer to this link for more information: <a href="https://community.altair.com/kb\_view.do?sys\_kb\_id=bb9bf3fc97205590e3b0361e6253af03">https://community.altair.com/kb\_view.do?sys\_kb\_id=bb9bf3fc97205590e3b0361e6253af03</a>

If you don't have an Altair One account, you can sign up for a free trial that will allow you to test
the product for 14 days.

# MIGRATION TO STREAMS SERVER 2025 FROM AN OLDER VERSION

These instructions assume that you:

- □ Have an existing 2024.1 or older server installed and want to migrate the content to a new installation of the 2025.0 server.
- Want to keep running the old server while you make sure that the migration was successful, and that the new server is running as it should.

All of the server content is stored in its application data <appdata> folder, the path of which is set in the PanopticonAppData context environment property. For example, in Tomcat this would be in <tomcat home>/conf/catalina/localhost/streams.xml or similar.

NOTE

Two Panopticon web applications should never share the same <appdata> folder, ensure that the new server is pointed at its own initially empty folder.

Some of the content can simply be copied from the old server to the new one, while some is now stored in a new format and needs to be converted. The applications and data sources themselves can be migrated any number of times, essentially resetting the applications on the new server.

### **Summary of steps:**

- 1. Copy all content.
- 2. Delete old content.
- 3. One-time conversion
- 4. Applications, data sources, and data files
- 5. Do not make changes on both servers.
- 6. Post-migration cleanup

### 1. Copy All Content

Start by copying all files from <old\_appdata> to <new\_appdata>. You can selectively copy some files again later to keep the old and new server in sync (e.g., copy over scheduled tasks after they are modified on the old server). This completes the **migration** of the following:

- License file The server will not start without a valid <appdata>/PanopticonLicense.xml. Starting in 2020, you also have the option to use Altair units licensing instead of the XML file.
- Properties file The set of properties in <appdata>/Streams.properties that the server understands changes between releases. The first time you start it, it will add a new one and remove old properties.
- □ Scheduled tasks All scheduled tasks are in SCH files in <appdata>/Schedule/.

### 2. Delete Old Content

On the new server, delete the <new\_appdata>/Tokens/ folder. This holds authentication tokens for logged in users, and they are server specific.

### 3. One-time Conversion

**NOTE** 

Converting applications and data sources is covered in the next section.

On servers older than version 2020.0, parameters were stored in

<old\_appdata>/DefaultParameters.xml. They were global and applied to all content (applications and
data sources). Starting in 2021.0 you can now organize content in folders, and you can also define parameters that
only apply to content in a particular folder. The new server stores them all in
<new appdata>/Parameters.json.

If <appdata>/Parameters.json doesn't exist when the new server starts, it will create it, and if it finds <appdata>/DefaultParameters.xml it will import these into the new file. To repeat the conversion, e.g., if you want to re-import changed parameters from the old server, delete Parameters.json and restart the server.

### 4. Applications, Data Sources, and Data files

Applications and their change history, and data sources, are stored in a very different format in a repository inside the <appdata>/.streams-repository/ folder. This is preparation for better versioning, content synchronization in a cluster and other things.

On servers older than version 2020.2, all applications were stored as individual APP files in <appdata>/CEP/Applications. Every time an application was updated, a backup was placed in <appdata>/CEP/Archive. Data sources were stored as DSM files in <appdata>/CEP/Datasources.

If the new server starts and the <appdata>/.streams-repository/ folder doesn't exist, it will create one, and then look in the <appdata>/CEP/ folder. Any applications and data source files it finds in there, it will import into the newly created repository. After the import, the <appdata>/CEP/ folder is no longer used.

Optionally, you can also import all application backups from <appdata>/CEP/Archive/. If you do, they will be recorded as application edits in the new repository. While the web UI currently doesn't expose the change history, it may very well do so in the future.

NOTE

To opt out, set repository.import.archived.applications to false in Streams.properties.

You can repeat this migration as many times as you like: stop the new server, delete the entire <new\_appdata>/.streams-repository/ folder, then start the new server. This provides a convenient way to keep the new server in sync with changes on the old server, assuming the old server is still in use. Please note that this process will lose all changes made on the new server only, as they are stored in the repository.

Data sources that use data files (e.g., CSV, JSON, XML) with relative paths expect the path to be relative to the <appdata>/Data/ folder. You can simply copy the entire <old\_appdata>/Data/ folder to <new appdata>.

### 5. Do Not Make Changes on Both Servers

After the initial migration you can keep the new server up to date when content changes on the old server by repeating any of the steps above. It is much harder to move content the other way, from the new server to the old one. Therefore, avoid making changes (that you want to keep) on the new server until you've completely migrated and retired the old server.

### 6. Post-migration Cleanup

When you are satisfied that the new server is running as it should, that all content has been migrated, switched users over to the new server, and are no longer using the old server, you can remove files from <new\_appdata> that are no longer needed.

- $\hfill \Box$  <appdata>/DefaultParameters.xml These are now in the JSON file.
- <appdata>/CEP/Applications/ Applications are now stored in the repository.
- <appdata>/CEP/Archive/ If you migrated the change history, this is also in the repository now.
  Otherwise, you can keep it if you want to go back to an earlier application version.
- □ <appdata>/CEP/Datasources/ Data sources are now also in the repository.

# **UPGRADE**

A previously installed Panopticon Streams can be upgraded through the following process:

- 1. Stop Tomcat.
- 2. Delete the existing webapps\streams.war file.
- 3. Delete the deployed application: webapps\streams.
- 4. Delete the cache from the working folder (for example):

```
work\Catalina\localhost\streams
```

- 5. Deploy the new streams. war file by copying it to the Tomcat webapps folder.
- 6. Restart Tomcat.

# [3] AUTHENTICATION

# INTRODUCTION

Panopticon Streams provides multiple approaches to authentication. It can easily be configured to use different authentication mechanisms depending on the environment and the setup. The server only supports authentication and authorization and does not have any support for user management or administration of users.

There are mainly two properties that manage the authentication on the server. These properties are listed and described in the table below. Please note that more properties might need to be configured depending on the authentication mechanism you are using.

Property	Description	Default Value
authentication.role	The required role or group that the user needs to be identified as a Panopticon user. The property can be left blank if no role or group is required.	
authentication.required	This property will make the authentication required. It will force the user to login in order to use any of the services provided by the server.	true
authentication.type	The type of authentication that should be used when authenticating the user. The property allows the following values: BASIC, FILTER, HEADER, OAUTH2, SAML.	BASIC

### **Mapping Users to Roles**

Depending on the authentication or user management mechanism used, the role that a user should have is specified and then mapped to a group set in <a href="Streams.properties">Streams.properties</a>.

Property	Description	Default Value
access.administrator.groups	The role that is mapped to the administrator group.  Allowed to perform the following:	admin
	• <u>connect</u> to or <u>disconnect</u> from the CEP Engine.	
	<ul> <li>create, <u>rename</u>, remove <u>folders</u> and <u>subfolders</u>, upload <u>applications</u> or data sources, and manage users or groups that should be <u>granted</u> or <u>denied</u> access.</li> </ul>	
	import and export application bundles.	
	<ul> <li>rename, view topic or data source usage, move, copy, download, remove, and publish/republish applications to folders to which the user has permission.</li> </ul>	
	<ul> <li>rename, view application usage, move, copy, download, and remove data sources.</li> </ul>	
	Administer the server which includes:	
	o <u>refresh</u> , <u>start</u> , and <u>stop</u> data producers.	

Property	Description	Default Value
	<ul> <li>view engine metrics and retrieved messages.</li> <li>add, modify, refresh, and delete parameters.</li> <li>define file logging level or view, pause, resume logging, copy, and clear all logs</li> <li>view Kafka properties.</li> <li>reload configuration.</li> <li>create, modify, and delete clear topic data tasks.</li> </ul>	
access.default.roles	The default roles applied to all users of the server.  For example, If  access.default.roles=DESIGNER,ADMINISTRATOR  and a user with a VIEWER role logs on to the server, then the user will simultaneously have a VIEWER, DESIGNER, and ADMINISTRATOR roles.  However, if no default roles are wanted, then leave the property blank.  NOTE: The roles that can be assigned in this property can only be ADMINISTRATOR, VIEWER, ANONYMOUS, and/or DESIGNER. This property is case sensitive.	VIEWER
access.designer.groups	The role that is mapped to the designer group.  Allowed to perform the following:  create, rename, remove folders and subfolders, upload applications or data sources, and manage users or groups that should be granted or denied access.  create, rename, view topic or data source usage, move, copy, download, remove, and publish/republish applications to folders to which the user has permission  create, rename, view application usage, move, copy, download, and remove data sources.  import and export application bundles.	designer
access.viewer.groups	The role that is assigned to the viewer group.  Allowed to view the engine status.	viewer

Group sets can be added for a role, by default separated by a comma.

Normally, you should use role mapping to control user access. This way you can manage access in the same place that you manage your users without having to reconfigure the server.

In some scenarios, it may be impossible to set up appropriate roles for Panopticon in your external system, or you may want to make one-off exceptions for specific users. As a workaround for these cases, you can also explicitly list individual users and their access in the server configuration with the <a href="mailto:access.you can also explicitly list individual users and their access in the server configuration with the access.administrator.users">access.designer.users</a>, and <a href="mailto:access.viewer.users">access.designer.users</a>, and <a href="mailto:access.viewer.users">access.viewer.users</a> properties.

### **Token**

A web token is used when the user has successfully logged into Panopticon Streams when using one of the following authentication types: BASIC or SAML. The token is used to identify the user and represent the user's ongoing session. This is done to prevent user credentials being sent between the user and server more than necessary.

The token is returned from Panopticon Streams in the form of a cookie when the user has been authenticated. The cookie will be stored in the browser as a HttpOnly cookie.

The token can be configured differently to suit your needs and requirement. The token can be configured to be valid at a certain amount of time, if it can refresh itself and/or if it should be persistent or if it should only last for a user session (While the browser is still open). All this can be configured in the <a href="Streams.properties">Streams.properties</a>. The table below lists all available token properties.

Property	Description	Default Value
authentication.token.persistence	This property is used to determine if the token should persist if the browser is closed or if it should only last while the browser is open. There are two possible values:  PERSISTENT and SESSION. PERSISTENT will persist the token in the browser even if the browser has been closed and reopened. SESSION will remove the token from the browser if it is shutdown.  IMPORTANT:  After modifying the property value to SESSION, ensure to clear the AppData/Token folder before starting the server.	PERSISTENT
authentication.token.refreshable	This property determines if the token can refresh itself. The web client can identify if the token is about to expire and then request a new token with the existing token. A token is refreshable if the property is set to <b>true</b> . The token will expire and invalidate the user session if the property is set to <b>false</b> .	true
authentication.token.secret	The secret is used to sign the token. The secret will be auto-generated when the server starts for the first time.  NOTE: This value should be kept a secret.	Auto-generated
authentication.token.validity.seconds	The number of seconds that the token should be valid.	604800

# **TOMCAT REALM**

Panopticon Streams can be configured to use the Tomcat Realm when performing authentication. The Tomcat Realm is configured in the server.xml file in the Tomcat conf folder. The Tomcat Realm itself can be configured to authenticate towards a variety of different types of authentication source, such as Tomcat user base and LDAP. The sub chapters in this chapter will give examples on how to configure the Tomcat Realm.

Panopticon Streams needs to be configured to use the BASIC type in order to do the authentication towards the Tomcat Realm. To enable Tomcat Realm authentication, set this property in the Streams.properties file:

authentication.type=BASIC

It is a common approach to wrap your Tomcat Realm with the LockOutRealm. This is used to prevent brute-force attacks.

```
<Realm className="org.apache.catalina.realm.LockOutRealm">
     <!-Insert your own Tomcat Realm here +
     </Realm>
```

### **Tomcat User Base**

The Tomcat User Base Realm is using a JNDI resource to store user information. By default, the JNDI resource is configured in an XML file. The default file is tomcat-users.xml in the Apache Tomcat conf folder.

We strongly recommend using this authentication approach for your test or local environment. It is easy to setup and configure. However, it is not designed to be used for large-scale production or when you have a large number of users.

The following Realm has to be added in the server.xml file in the Apache Tomcat conf folder:

<Realm className="org.apache.catalina.realm.UserDatabaseRealm"
resourceName="UserDatabase"/>

#### NOTE

The Tomcat User Database Realm is used as the default. No configurations are required in the server.xml file to be able to use the Tomcat Database Realm.

The users and roles are managed in the tomcat-users.xml file in the Apache Tomcat conf folder. In this file, you can add users and roles as well as assign roles to users.

Add the following role and user to your tomcat-users.xml file:

```
<role rolename="admin"/>
<user username="John" password="john" roles="admin"/>
```

By adding these two lines you have achieved the following:

- □ Created a new role named admin
- Created a new user with username John and password john
- Assigned the newly created user the role admin

### **NOTE**

Authentication towards a Tomcat Realm (i.e., Tomcat users, LDAP, AD) in Tomcat 8.5.28 is not supported. This has been supported in all the previous and the succeeding versions.

### **Tomcat Memory Configuration for Windows**

**NOTE** 

It is recommended to increase the Java heap size of Tomcat to avoid the initiation of garbage collection when memory usage hits the set threshold.

The steps may vary depending on how Tomcat was deployed.

### Steps:

- 1. Stop Tomcat.
- 2. Create a file named setenv.bat.
- 3. Place the file in the Tomcat bin folder.
- 4. Set the minimum and maximum heap size with the JVM -Xms and -Xmx parameters. A minimum of 1 GB is recommended. For example:

 $\verb|set JAVA_OPTS={JAVA_OPTS}| - \texttt{Dfile.encoding} = \texttt{UTF-8} - \texttt{server} - \texttt{Xms} \\ 512\texttt{m} - \texttt{Xmx} \\ 2\texttt{g} - \texttt{Xmx} \\ 2\texttt{g$ 

NOTE

Setting the maximum value should be dependent on your system. Ensure that the heap size is not larger than the available free RAM on your system. It is recommended to use 80% of the available RAM not taken by the operating system or other processes of your JVM.

- Save the file.
- 6. Restart Tomcat to apply the increase in the heap.

### **Tomcat Memory Configuration for Linux**

**NOTE** 

It is recommended to increase the Java heap size of Tomcat to avoid the initiation of garbage collection when memory usage hits the set threshold.

The steps may vary depending on how Tomcat was deployed.

### Steps:

- 1. Stop Tomcat.
- 2. Create a file named setenv.sh.
- 3. Place the file in the Tomcat bin folder.
- 4. Set the minimum and maximum heap size with the JVM -Xms and -Xmx parameters. A minimum of 1 GB is recommended. For example:

JAVA OPTS="\$JAVA OPTS -Dfile.encoding=UTF-8 -server -Xms512m -Xmx2g"

Setting the maximum value should be dependent on your system. Ensure that the heap size is not larger than the available free RAM on your system. It is recommended to use 80% of the available RAM not taken by the operating system or other processes of your JVM.

- 5. Save the file.
- 6. Restart Tomcat to apply the increase in the heap.

### **Encrypting Passwords in tomcat-users.xml**

Tomcat supports encrypted user credentials via the Digested Passwords feature:

https://tomcat.apache.org/tomcat-9.0-doc/realm-howto.html#Digested Passwords

To secure passwords saved in tomcat-users.xml, do the following:

- 1. Stop Tomcat.
- Open [tomcat\_home]/conf/server.xml.
- 3. In server.xml, find the Engine XML element.

Nested inside the Engine element, there is a Realm element named LockOutRealm. Nested inside the LockOutRealm is another Realm element named UserDatabaseRealm that looks like this:

```
<Realm className="org.apache.catalina.realm.UserDatabaseRealm"
    resourceName="UserDatabase"/>
```

4. Edit the UserDatabaseRealm element into the following:

NOTE

You must add the closing element "</Realm>" for the UserDatabaseRealm, and edit out the closing forward slash "/" at the end of the original Realm element.

5. Generate hash from plain text passwords using the command below:

### Linux example:

```
[tomcat_home]/bin/digest.sh -a SHA-256 -h
org.apache.catalina.realm.MessageDigestCredentialHandler [password]
```

#### Windows example:

```
[tomcat_home]/bin/digest.bat -a SHA-256 -h
org.apache.catalina.realm.MessageDigestCredentialHandler [password]
```

NOTE

If your Apache Tomcat installation has the <code>JAVA\_HOME</code> environment variable set only in the file <code>catalina.sh</code> (Linux) or <code>catalina.bat</code> (Windows) and not generally on the system, you will also need to set the <code>JAVA\_HOME</code> variable before running the digest command.

#### Linux example:

export JAVA HOME=/path/to/JavaInstallation

Windows example:

set JAVA\_HOME=/path/to/JavaInstallation

The digest command will return the password supplied, followed by a colon, and then a hash of the password. Example, for a password **asd123**:

asd123:74807befd6bdc1c937dc931a3dfadf015da1df1b99b74cd8d91210788e0141a5\$1\$f21cb2dd667209d6 39f6be48cf83826a657730032bdacb04465262d221bfc509

- 6. Replace the plain text password in tomcat-users.xml with the generated password hash, and save the tomcat-users.xml file. NOTE: When you have defined a MessageDigestCredentialHandler in the UserDatabaseRealm, then ALL passwords stored in tomcat-users.xml are treated as hash values. You will no longer be able to log in using passwords that are saved as clear text.
- 7. Start Tomcat.

### **LDAP**

Panopticon Streams can be configured to authenticate towards a Lightweight Directory Access Protocol (LDAP) or source. By configuring the Apache Tomcat Realm, the server can authenticate users and extract their roles by querying the LDAP source.

The realm's connection to the directory is defined by the <code>connectionURL</code> attribute. Each user that can be authenticated must be represented in the directory with an individual entry that corresponds to an element in the initial <code>DirContext from the connectionURL</code>. This user entry must have an attribute containing the username that is presented for authentication.

You can add a dedicated user with <code>connectionName</code> and <code>connectionPassword</code> in a Realm to define a user with a Read access to the user database and roles. If for example the admin <code>cn</code> name is set as **admin** and the admin <code>password</code> is set as **admin**, then you need to add these properties as shown in the example below.

The userPattern attribute may be used to specify the DN, with " $\{0\}$ " marking where the username should be substituted.

The role is usually an LDAP group entry with one attribute containing the name of the role and another one whose values are distinguished names or usernames of the users in that role. The following attributes configure a directory search to find the names of roles associated with the authenticated user:

roleBase: The base entry for the role search. If not specified, the search base is the top-level directory context
roleSearch: The LDAP search filter for selecting role entries
roleName: The attribute in a role entry containing the name of that role
roleNested: Includes nested roles if set to true. This means every newly found roleName and distinguished Name will be recursively tried for a new role search. The default behavior is false.

The following is an example on how the Realm can be configured when using LDAP. Please note that the values should be replaced with details from your own LDAP source.

```
<Realm className="org.apache.catalina.realm.JNDIRealm"
    connectionURL="ldap://localhost:389"
    connectionName="cn=admin,dc=test,dc=com"
    connectionPassword="admin"
    userPattern="uid={0},ou=users,dc=test,dc=com"
    roleBase="ou=groups,dc=test,dc=com"
    roleName="cn"
    roleSearch="(uniqueMember={0})"
    rolenested="true"</pre>
```

Using this configuration, the realm determines the user's distinguished name by substituting the username into the userPattern, authenticates by binding to the directory with this DN and the password received from the user, and searches the directory to find the user's roles.

#### NOTE

If you opt not to have a dedicated user, remove <code>connectionName</code> and <code>connectionPassword</code>, and then have each user extract information about itself. You do this by adding <code>userSearchAsUser</code> and <code>roleSearchAsUser</code> in a Realm, and setting both values to <code>true</code>. The recommended usage, however, is to have a dedicated user. This allows you to always have the rights to query a LDAP, unlike using <code>userSearchAsUser</code> and <code>roleSearchAsUser</code> where there is no guarantee that each user is authorized to extract these details.

# **Active Directory**

Panopticon Streams can be configured to authenticate towards an Active Directory server. Panopticon Streams is using LDAP to interact and communicate with the Active Directory server. Therefore, the configuration is very similar to the LDAP configuration in the previous section.

The following is an example on how the Realm can be configured when using Active Directory. Please note that the values should be replaced with details from your own LDAP source.

```
<Realm className="org.apache.catalina.realm.JNDIRealm"</pre>
   connectionURL="ldap://ad.dwch.com:3268"
   alternateURL="ldap://ad.dwch.com:389"
   authentication="simple"
   referrals="follow"
   connectionName=admin@DWCH.com
   connectionPassword="admin"
   userBase="cn=Users,dc=DWCH,dc=com"
   userSearch="(sAMAccountName={0})"
   userSubtree="true"
   roleBase="cn=Users,dc=DWCH,dc=com"
   roleName="cn"
   roleSearch="(member={0})"
   roleSubtree="true"
   roleNested="true"
/>
```

## **NOTE**

Similar with LDAP, you can opt not to have a dedicated user by removing connectionName and connectionPassword and instead let each user extract information about itself by adding userSearchAsUser and roleSearchAsUser in a Realm. Set both values to true. As mentioned in the LDAP section, the recommended usage is to have a dedicated user since there is no guarantee that each user is authorized to extract these details.

# SAML

Panopticon Streams supports Security Assertion Markup Language, SAML2. Upon a login request, Panopticon Streams will redirect the user to an Identity provider (IdP). The IdP will authenticate the user and redirect the user back to Panopticon Streams. The response message will be controlled and validated. Username and roles will be extracted from the response message and used within Panopticon Streams.

Panopticon Streams will redirect the user back to the IdP upon a logout request. The IdP logout service should then invalidate the SAML token.

Property	Description
authentication.saml.assertion.roles	User attribute for roles configured in the IdP.
authentication.saml.assertion.username	User attribute for username configured in the IdP.
authentication.saml.assertionconsumerservice.url	The URL to the Panopticon assertion consumer service. URL: [Protocol]://[Host]:[Port]/[Context]/server/rest/auth/login
authentication.saml.certificate.name	The name of the certificate used to validate signature and/or sign outgoing SAML messages
authentication.saml.certificate.password	The password of the certificate used to validate signature and/or sign outgoing SAML messages
authentication.saml.identityprovider.logout.url	The URL to the IdP logout service.
authentication.saml.identityprovider.url	The URL to the IdP login service.
authentication.saml.keystore.file	The location of the Keystore file that contains the certificate.
authentication.saml.keystore.password	The password to the Keystore file.
authentication.saml.serviceprovider.id	The ID of the service provider configured in the IdP.
authentication.saml.identityprovider.certificate.file	Takes a file path to a certificate file that contains the IdP's public key.
authentication.saml.identityprovider.signature.validation.req uired	Specifies whether to require a valid IdP signature to be present on the SAML response. Default value is <b>false</b> .
authentication.saml.provider	The IdP provider. Possible values are <b>OPENSAML</b> , <b>OPENAM</b> . Default value is <b>OPENSAML</b> .

Property	Description
authentication.saml.keystore.type	The key store type. Possible values are <b>JKS</b> , <b>JCEKS</b> , <b>PKCS12</b> . Default value is <b>JKS</b> .
authentication.saml.openam.meta.alias	The meta alias for the IdP if you are using OpenAM.

# **OAUTH 2.0**

This section discusses how to configure Panopticon Streams to use the OAuth 2.0 for authorization. Upon a logon request, Panopticon Streams will redirect the user to the Login page provided by the OAuth 2.0.

Note that OAuth 2.0 does not normally provide support on how to authenticate the user, Panopticon Streams will only know if the user is authorized or not. To authenticate the user, Panopticon Streams can be configured to use a REST service to extract the user identity with an access token retrieved from the OAuth 2.0 provider. In addition to the standard OAuth 2.0 configurations, the server includes properties (i.e., authentication.oauth2.\*) that are specifically used to extract the user details.

authentication.type=OAUTH2

Property	Description
authentication.oauth2.client.id	The ID of the OAuth 2.0 client.
authentication.oauth2.client.secret	The secret used by the OAuth 2.0 client.
authentication.oauth2.identity.attribute.username	The attribute that will be extracted from the identity response and used as the username.
authentication.oauth2.identity.url	The URL to the REST service that provides details about the authenticated user.
authentication.oauth2.login.callback.url	The callback URL. The URL should be the same as one of the specified callback URLs used by the client. The URL should refer to Panopticon Streams
authentication.oauth2.login.response.type	The response type. The only response type that is currently supported is <b>CODE</b> . The value can also be left blank.
authentication.oauth2.login.scope	The requested scope. The field can be left blank.
authentication.oauth2.login.url	The URL to the OAuth 2.0 login resource.
authentication.oauth2.logout.url	The URL to the OAuth 2.0 logout resource. This field can be left blank.
authentication.oauth2.token.method	The method on how the token should be retrieved. Supported values are <b>QUERY</b> , <b>BODY</b> , and <b>HEADER</b> .
authentication.oauth2.token.url	The URL to the OAuth 2.0 token resource.

# **Example**

```
authentication.oauth2.client.id=ClientId
authentication.oauth2.client.secret=ClientSecret
authentication.oauth2.identity.attribute.username=name
```

```
authentication.oauth2.identity.url=https://oauth2/me
authentication.oauth2.login.callback.url=http://localhost:8080/panopticon/ser
ver/rest/auth/login
authentication.oauth2.login.response.type=CODE
authentication.oauth2.login.scope=
authentication.oauth2.login.url=https://oauth2/authorize
authentication.oauth2.logout.url=
authentication.oauth2.token.method=QUERY
authentication.oauth2.token.url=https://oauth2/access_token
authentication.type=OAUTH2
```

# **FILTER**

Custom authentication filters can be applied to the server and the application when the default authentication settings are not sufficient. This type of authentication is referred to as **Filter authentication**. When Panopticon Streams is configured to use filter authentication, it means that the incoming requests have already been authenticated and authorized before reaching the server. Follow the steps below to configure filter authentication:

- 1. Open the Streams.properties file in the AppData folder (c:\streamsserverdata).
- 2. Enable authentication.type=FILTER in Streams.properties.
- 3. Apply the following URL pattern to your own filter: /\*
- 4. Save the changes and restart the Tomcat.

# **Creating a Custom Filter**

The custom filter will be a basic authentication filter which will authenticate the user with hardcoded values. The Principal forwarded by the filter will be used to authenticate the user.

The filter will require the following dependencies:

- Javax Servlet
- Tomcat embed core

#### Steps:

1. Create a HTTP request wrapper.

The class will contain the following:

- the original incoming HTTP request
- the Principal which contains both the credentials and the roles for the authenticated user.

The HTTP wrapper will be forwarded to Panopticon Streams instead of the original incoming HTTP request.

```
import org.apache.catalina.realm.GenericPrincipal;
import org.apache.catalina.users.MemoryUser;
import javax.servlet.http.HttpServletRequest;
import javax.servlet.http.HttpServletRequestWrapper;
import javax.security.Principal;

public class FilterRequestWrapper extends HttpServletRequestWrapper {
    private final GenericPrincipal principal;
}
```

2. Create a custom filter. The filter will create a new Principal which includes both the credentials and the groups/roles for the user.

In this example, the class <code>GenericPrincipal</code> contains username, password, and groups. Panopticon Streams is only able to extract the groups from <code>GenericPrincipal</code> class or the <code>MemoryUser</code> class. Both the Principal and the original HTTP request will be wrapped in an instance of <code>FilterRequestWrapper</code>. The wrapper will then be forwarded towards Panopticon Streams.

```
import org.apache.catalina.realm.GenericPrincipal;
import org.apache.catalina.users.MemoryUser;
import javax.servlet.*;
import javax.servlet.http.HttpServletRequest;
import javax.servlet.http.HttpServletResponse;
import java.io.IOException;
import java.security.Principal;
import java.util.Arrays;
import java.util.List;
public class ExampleFilter implements Filter{
    @Override
    public void init(FilterConfig filterConfig) throws ServletException {}
    public void doFilter(final ServletRequest servletRequest, final
ServletResponse servletResponse, FilterChain filterChain) throws
IOException, ServletException {
        if (!(servletRequest instanceof HttpServletRequest ||
!(servletRequest instanceof HttpServletResponse))) {
            return;
        final HttpServletRequest request = (HttpServletRequest)
servletRequest;
        final HttpServletResponse response = (HttpServletResponse)
servletResponse;
        final String username = "username";
```

```
final String password = "password";
    final List<String> groups = Arrays.asList("Group1", "Group2");
    final GenericPrincipal principal = new GenericPrincipal(username,
password, groups);
    filterChain.doFilter(new FilterRequestWrapper(request, principal),
response);
}

@Override
    public void destroy() {}
}
```

- 3. When these classes have been created, you can compile them and package them in a jar file.
- 4. Copy the jar file to the WEB-INF/lib folder in the panopticon war file (or the extracted folder).
- 5. Enable the filter by adding the following code to the web.xml file in panopticon WEB-INF folder:

# **HEADER**

It is possible to use a web-facing Panopticon Streams behind a proxy server that will handle the authentication of users. The proxy server forwards the name of the user and roles to Panopticon Streams as HTTP headers for every request.

For requests where headers are blank or missing, they are treated like anonymous requests while requests where the user HTTP header is valid are treated like authenticated requests with that specific username.

Requests from the proxy server are fully trusted and checks are no longer performed at Panopticon Streams regarding the validity of the username. The authorization on workbooks and administration will work as usual.

To activate the Header authentication, add or update the following properties in the Streams.properties file:

```
authentication.type=HEADER
authentication.header.role.delimiter=,
authentication.header.roles={roles header, ie. X-Roles}
authentication.header.username=={userid header, ie. X-User}
```

# [4] PCLI: COMMAND UTILITIES FOR PANOPTICON

Panopticon Streams is supplied with a command line utility PCLI.jar.

# **EXPORT DATA SOURCES**

THE PCLI provides functionality to export data sources from one or all workbooks in a directory. The exported data sources can be uploaded and used directly by Panopticon Streams.

#### **Parameters**

Parameter	Description	Required
-w,workbook	The name of the workbook.	Yes (or -wd)
-od,output-directory	The output directory where the data source will be exported to.	No
-wd,workbook- directory	The directory of the workbooks folder.	Yes (or -w)
-dd,data-directory	The directory of the data folder.	Yes
-I,license-file	The path of the license file.	Yes

#### **Example 1: Export data sources from a workbook**

```
java -jar pcli.jar exportdatasource
-w "C:/vizserverdata/Workbooks/VizGuide.exw"
-l "C:/vizserverdata/PanopticonLicense.xml"
-dd "C:/vizserverdata/Data"
-od "C:/streamsserverdata/CEP/Datasources"
```

#### **Example 2: Export data sources from all workbooks example**

```
java -jar pcli.jar exportdatasource
-wd "C:/vizserverdata/Workbooks"
-l "C:/vizserverdata/PanopticonLicense.xml"
-dd "C:/vizserverdata/Data"
-od "C:/streamsserverdata/CEP/Datasources"
```

#### Where:

- □ C:\vizserverdata is the AppData folder of Panopticon Real Time
- ☐ C:\streamsserverdata is the AppData folder of the Streams server


# [5] USING ALTAIR PANOPTICON STREAMS

# CONNECTING TO OR DISCONNECTING FROM THE CEP ENGINE

## **NOTE**


Panopticon Streams Server will be connected to the CEP engine after start up if any of the following settings is true:

- The default setting of the localhost for the Kafka broker is available.
- The Kafka settings in the <a href="Streams.properties">Streams.properties</a> file are correct.




Click Kafka Connection Status to expand and display the Engine pane and view the settings.

# For Connected :



# For A Disconnected :



Property	Description
Status	Displays whether Panopticon Streams is connected to or disconnected from the CEP Engine (Kafka).
Туре	The CEP Engine that Panopticon Streams engine will work with (KAFKA).
ZooKeeper	The URL to the ZooKeeper servers. Default is localhost:2181.
Kafka	The URL of all the Kafka servers. Default is localhost: 9092.
Schema Registry	The URL to the Schema Registry. Default is <a href="http://localhost:8081">http://localhost:8081</a> .

# **Connecting to the CEP Engine**

Starting with version 2021.0, the "local" or "internal" Kafka connectivity is deprecated. To connect to the CEP engine, use the external setup.

### NOTE

Before connecting to the CEP engine, ensure the following are running:

- <u>Confluent Kafka Enterprises services</u> if you are using a Dockerized Kafka.
- ZooKeeper, Kafka, and Schema Registry batch files if you are using a local cluster.



to connect to the external Kafka.

# **Disconnecting from the CEP Engine**

Click not be generated.

. Consequently, the applications cannot be started and the input and output topics will


# [6] MANAGING THE STREAMS SYSTEM

The **System** tab displays the following sections where an administrator can:


View the active	ve license
-----------------	------------

- View the server properties
- View <u>Kafka properties</u>
- Reload configurations
- Schedule tasks

If the licensing used is the Altair Units license, the page will be displayed as:



If the licensing used is the volume-based XML file (named PanopticonLicense.xml), the page will be displayed as:



# VIEWING AND MANAGING KAFKA PROPERTIES

The user-defined Kafka.properties file contains properties for controlling the Kafka configurations in Panopticon Streams.

Below is a sample properties file:

```
# Broker endpoints where we will discover the cluster broker members.
If this
# is set here, any results from ZooKeeper are ignored.
# common producer and consumer settings
#bootstrap.servers=localhost:9092
bootstrap.servers=localhost:9093
security.protocol=SASL PLAINTEXT
sasl.mechanism=PLAIN
sasl.jaas.config=\
  org.apache.kafka.common.security.plain.PlainLoginModule required \
    username="dwchuser" \
   password="dwchpwd";
#Global properties applied on any topic created
topic.retention.ms=50000
topic.cleanup.policy=delete
aggregate.cachingEnabled=true
#Specific operator/node applicationId.operatorId.propertyname
AggregationExample.Input.retention.ms=60000
AggregationExample.Output.retention.ms=30000
AggregationExample.Aggregation.cachingEnabled=false
```

When Panopticon Streams is started, it checks the AppData folder for the kafka.properties file and loads the properties in the *Kafka Properties* box.

```
### Broker endpoints where we will discover the cluster broker members. If this ### is set here, any results from ZooKeeper are ignored.

# common producer and consumer settings #bootstrap.servers=localhost:9092 bootstrap.servers=localhost:9093 security.protocol=SASL PLAINTEXT sasl.mechanism=PLAIN sasl.mechanism=PLAIN sasl.jaas.config=\
org.apache.kafka.common.security.plain.PlainLoginModule required \
username="dwchuser" \
password="dwchpwd";

#Global properties applied on any topic created topic.retention.ms=50000 topic.cleanup.policy=delete
```

However, if the kafka.properties file is not available, the *Kafka Properties* box will display a blank *Kafka Properties* box:

CAFKA PROPERTIES		
		/

If you opt to copy the kafka.properties file to a different location, open the Streams.properties file and set the attribute cep.kafka.properties to the value of the file path along with the Kafka properties file name. For example:

cep.kafka.properties=c:\kafkafile\kafka.properties

#### NOTE

- The values in the *Kafka Properties* box is not editable on the **System** tab. Changes can be made in the actual kafka.properties file. To reload the properties on the **System** tab, click **Reload Configuration**.
- The kafka.properties file supports any Kafka configurations available on their documentation
- The configurations made in the kafka.properties will supersede any of the Kafka-related properties in the streams.properties file
- Some of the configurations in the kafka.properties file can be overridden by the settings made in Panopticon Streams applications

# **RELOADING CONFIGURATIONS**

3 Reload configuration

On the *System Settings* page under the **System** tab, click . This will stop and restart applications, reload data sources, and Kafka properties along with the administrators and parameters from the file system.

# LOGGING/MONITORING

# **View Logs**


View the latest 300 rows of a Logging Level on the Logs page:

- □ FINEST (lowest level)
- FINER

- □ FINE
- CONFIG
- □ INFO (default level)
- WARNING
- □ SEVERE (highest level)


#### Steps:


1. Under the **System** tab, click **Logs**. Initially, the default level (**INFO**) logs are displayed.



2. Select another Logging Level in the drop-down.

For example: FINEST





The latest 300 rows of the selected log level or higher are fetched.

3. You can also click any of the following buttons:



- to resume the logging
- to copy log to clipboard
- to clear the logs

# **Setting the Logging Level**

Changes to the logging level can be made by altering the value of <code>logger.level.file</code> in the <code>Streams.properties</code> file. The server will not log messages with a lower/finer level than this value. The separate logging configuration still applies to route whatever messages that the server does log. This means that if you have set the file handler's level to <code>INFO</code> in the configuration, setting the property to <code>FINE</code> has no effect.

The default value of the property is set to **INFO**. At this level, most information needed for troubleshooting is logged, including many data queries, timing, and parameters. With a lower/finer level performance will be affected due to the amount of information logged.

# **Setting the Server Metrics Publisher**

The server performance metrics can be used to report, monitor, and configure the server's health and limits. The collected metrics may include the following information:

- Long polling, WebSocket, and total number of connections
- CPU loading percentage
- Maximum, size, and used Heap Bytes
- Subscription alerts, users, and total
- Number of parallel data loading and live threads
- Average data load time or refresh rate

You can configure the following properties in the  $\underline{\text{Streams.properties}}$  in the  $\underline{\text{AppData}}$  folder or C:\streamsserverdata:

Property	Server Metrics
Attribute	metrics.authorization.level
Description	Specifies the required authorization level to get server metrics. Available values are ANONYMOUS, VIEWER, DESIGNER, ADMINISTRATOR.  NOTE: This property is case sensitive.
Default Value	ADMINISTRATOR
Property	Server Metrics
Attribute	metrics.collection.rate
Description	Specifies the rate at which metrics are collected in milliseconds.
Default Value	1000


Property	Server Metrics
Attribute	metrics.file.flush.rate
Description	Specifies how often metrics should be saved to disk in milliseconds. Only used if the metrics.publisher.type is set to FILE.
Default Value	10000
Property	Server Metrics
Attribute	metrics.memory.queue.size
Description	Specifies how many metric entries are stored in memory. When the number of metrics goes above the specified value, the oldest value is removed to make room for the newest one (FIFO). Only used if the metrics.publisher.type is set to <b>MEMORY</b> .
Default Value	100
Property	Server Metrics
Attribute	metrics.publisher.configuration
Description	Specifies the id for which metric publisher configuration to use.
Default Value	
Property	Server Metrics
Attribute	metrics.publisher.type
Description	Specifies the current metric publisher that is used. Available values are <b>NONE</b> , <b>MEMORY</b> , <b>FILE</b> , <b>EMAIL</b> , <b>INFLUX_DB</b> , <b>JDBC</b> , <b>KAFKA</b> , <b>KDB</b> , <b>MQTT</b> , <b>REST</b> , <b>TEXT</b> .
Default Value	MEMORY

# **SCHEDULING TASK TO CLEAR TOPIC DATA**

Panopticon Streams supports scheduling of tasks such as daily deletion of application topics.


#### Steps:

1. Under the **System** page, click **Scheduler**.



2. Cilck New Task


. The New Task pane displays.



3. Enter the Name of the task. Ensure the name is unique.

+ New Task

- 4. Tap the Activated slider to turn it on.
- 5. Select the Trigger. You can either select:
  - Period then enter the Interval (in seconds), or



• **CRON** then enter a *CRON Expression* on the format:

sec mins hours dayofmonth month dayofweek (e.g., 09 02 18 ? \* MON-FRI)




- 6. Select the task *Type*: Clear Topic Data.
- 7. Enter the Description of the task.
- 8. Select the *Application* in the drop-down list. These are the applications available on the **Applications** tab.



Once saved, you can opt to click

Run to manually run the task.

• Click to go back to the Tasks pane. The new task is added in the list.



A task displays the following columns: Name, Activated, Type, Trigger, Last Updated By, Created, Last Run, and Last Run Result.

Modify the sorting of the list by clicking the  $^{\downarrow}$  or  $^{\uparrow}$  button of any of these columns. The icon beside the column that was used for the sorting will indicate if it was in an ascending or descending order.

#### Tasks can also be:

- manually started
  - Instead of waiting for the set Period interval or CRON Expression, you can manually execute the task by clicking .

The Last Run and Last Run Result (Success or Failed) are displayed. For failed results, you can hover on the tooltip to view the error.

- modified
- deleted



# Modify a Scheduled Task

#### Steps:

- 1. On the Scheduler page under the **System** tab, click the link of a task to modify.
  - The properties of the task are displayed.
- Apply the desired changes.
- 3. Click

# [7] AUTHORIZATION

#### **NOTE**

Starting with version 2020.0, mapping of administrators through Administrators.txt and AdministratorGroups.txt is no longer supported. The property access.administrator.groups should be used instead.

If the customer's authentication method relied to the use of the <code>Administrators.txt</code> or <code>AdministratorGroups.txt</code> file, they can still do so by additionally using the <code>tomcat-users.xml</code> to replicate the usage of these administrator text files.

For example, in the tomcat-users.xml, they can assign groups from the administrator text files to specific users like this:

```
<user username="admin" password="admin" roles="role1,otherRole"/>
<user username="admin2" password="admin2" roles="role2"/>
```

Then in the <u>Streams.properties</u> file, use the access.administrator.groups property to map the admins (i.e., admin and admin2) to the administrator groups by adding their roles:

access.administrator.groups=role1, role2

# SECURE ACCESS

Panopticon <u>applications</u> and <u>data sources</u> published to the folders or subfolders in Panopticon Streams Server can be secured by granting allowed or denied permissions.

# **Creating Folders**

A user with an Administrator or Designer role can create folders.

#### NOTE

Users that log on with a Designer role will have their own personal folder created and displayed on the Applications and Data Sources tabs (e.g., ~designer).


The personal folders:

- are displayed and can be accessed for users with an Administrator or Designer role.
- are where Designers can create applications and data sources. For more information, see <u>Creating a New Application</u> or <u>Creating a Data Source</u> sections.


### **Creating Folders on the Applications Tab**

#### Steps:

1. On the **Applications** tab, right-click on the topmost folder (**Organization**) or the *Applications* pane and select **New Folder**.




The Create Folder dialog displays.






- Everyone is available in the Allowed section by default.
- Removing the Everyone group will mean that the folder and its subfolders will not be available for public access.
- 2. Enter a Folder Name.
- 3. Proceed to defining the Authorization to <u>Allowed</u> or <u>Denied</u> groups and users.
- 4. Click Create

The new folder is displayed on the expanded Folder hierarchy list and on the Root Folder list.






## **Creating Folders on the Data Sources Tab**

## Steps:

1. On the **Data Sources** tab, right-click on the topmost folder or the *Data Sources* pane and select **New Folder**.




The Create Folder dialog displays.



NOTE

- Everyone is available in the Allowed section by default.
- Removing the Everyone group will mean that the folder and its subfolders will not be available for public access.
- 4. Enter a Folder Name.
- 5. Proceed to defining the Authorization to <u>Allowed</u> or <u>Denied</u> groups and users.
- 6. Click Create

The new folder is displayed on the expanded *Folder* hierarchy list and on the *Root Folder* list.




# **Adding Groups and Users with Allowed Authorization**


A user with an Administrator or Designer role can grant permission for users or groups access to application or data source folder or subfolder.

#### Steps:


1. Right-click on a folder (except the root folder) and select **Permissions** in the context menu.



The Permissions dialog displays.



Under the Allowed section, click the Add icon.
 A new User/Group Allowed section is displayed.



3. Select User or Group to be given permission in the drop-down list.




- 4. Enter the user or group *Name*.
- 5. Select the permission level that will be granted to the user or group:
  - READ
     Permission to read the folder.
  - READ + WRITE

Permission to write to the folder and read.


MODIFY + WRITE + READ

Permission to read, modify, and write to the folder as well as create subfolders.



#### 7. You can either:

select the Apply Permissions to Subfolders check box



This means the permissions that will be used on all of the subfolders will be fetched from the root folder.



leave the **Apply Permissions to Subfolders** box unchecked and modify the permission properties of the subfolders


8. Click Update to save the changes.

**NOTE**You can copy the user names in the *Permissions* dialog by highlighting the text then right-clicking, and selecting **Copy** in the context menu.

# **Adding Groups and Users with Denied Access**

#### Steps:

1. Right-click on a folder and select **Permissions** in the context menu.



The Permissions dialog displays.



2. Under the *Denied* section, click the **Add** icon.

A new User/Group Denied section is displayed.



- 3. Select **User** or **Group** that will be given denied permission in the drop-down list.
- 4. Enter the user or group Name.
- 5. Select the denied permission level that will be granted to the user or group:
  - MODIFY

Prevent user or group to modify and create subfolders.

WRITE + MODIFY

Prevent user or group to modify and write to the folder.

READ + WRITE + MODIFY

Prevent user or group to modify and create subfolders, modify and write to the folder, as well as read the folder.

# Denied



6. Click . The user or group is added under the *Denied* list.

### Denied +



Repeat until all of the users with denied access are added.

- 7. You can either:
  - select the Apply Permissions to Subfolders check box, or



This means the permissions that will be used on all of the subfolders will be fetched from the root folder.




- leave the Apply Permissions to Subfolders box unchecked and modify the permission properties of the subfolders.
- 8. Click Update to save the changes.


# **Creating Subfolders**

### Steps:

- 1. To create subfolders, you can either click a folder:
  - on the expanded Folder hierarchy list, or





on the Root folders list.



The Folders page is displayed.


2. Right-click on the folder or on the *Applications* pane or *Data Sources* pane and select **New Folder**.






Refer to <u>Creating Folders</u> for the steps in creating the subfolders. Also, <u>Adding Groups and Users with Allowed Authorization</u> and <u>Adding Groups and Users with Denied Access</u> for more information on adding users and groups with allowed or denied authorization.


The subfolder is added.



3. You can also opt to delete a subfolder by right-clicking on the folder and selecting **Remove** in the context menu as long as it does not contain applications or data sources.




# A confirmation message displays.




# **Updating Folder or Subfolder Properties**

### Steps:

- 1. To update folder properties, click a folder or a subfolder.
- 2. Right-click on the folder or subfolder and select **Permissions**.



The corresponding Permissions dialog displays.



- 4. Make the necessary changes such as new folder name, add or delete users and groups.
- 5. You can either:
  - select the Apply Permissions to Subfolders check box
     This means the permissions that will be used on all of the subfolders will be fetched from the root folder.
  - leave the Apply Permissions to Subfolders box unchecked and modify the permission properties of the subfolders




6. Click to save the changes.


# [8] MANAGING APPLICATIONS

On the **Applications** tab, users with Administrator or Designer role can:

- import and export application bundles
- □ <u>upload</u> applications
- □ <u>rename</u> applications
- view topic or data source usage
- move or copy applications to folders or subfolders to which the user has permission
- download applications
- remove applications
- publish/<u>republish</u> applications to folders to which the user has permission



To create a new application, a user must have a Designer role.




# **UPLOADING APPLICATIONS**


Users with Administrator or Designer role can upload applications to folder or subfolders that they have permission.

### Steps:


- 1. To upload applications, you can either right-click a folder or subfolder then select **Upload Application**:
  - on the expanded Folder hierarchy list



on the Root folders list




The Upload Application dialog displays.




- 2. To upload an application, you can either:
  - · drag it from your desktop and drop in the dialog, or
  - click **Choose Application** and select one in the *Open* dialog that displays.

The name of the application is displayed on the uploaded application area and in the *Name* box.




3. You can opt to rename the application.




4. To replace an existing application, select the **Replace existing application** check box.




You will be notified when the application has been uploaded.




The application is added and displayed on the **Applications** tab.






## **Folders and Applications Display View**


Folders and applications can be displayed either on a *List* or *Grid View*. By default, the applications are displayed in a *List View*.



Click **Grid View** . The folders and applications are displayed as thumbnails.




Click **List View** to return to the standard listing.



On either display view style:

- clicking on an application title or thumbnail displays the application
- right-clicking on an application displays the context menu




# **IMPORTING AN APPLICATION BUNDLE**

Follow the instructions below to import an application bundle to Panopticon Streams.

### Steps:

1. On the Applications tab, right-click on a folder and select Import Bundle in the context menu.



The Import Bundle dialog displays.




- 2. To import the bundle, you can either:
  - drag it from your desktop and drop in the dialog, or
  - click **Choose Bundle to Import** and select one on the *Open* dialog that displays.

The name of the selected bundle is displayed in the dialog box.




- 3. Select the **Keep Folder Structure** check box if you opt to maintain the exported folder structure when uploading the bundle. If the folders do not exist on the server, they will be created.
- 4. To replace an existing data source, select the **Replace existing data source** check box.
- 5. To replace an existing application, select the Replace existing application check box.
- 6. Click Import

The applications and data sources that you can view and explore are imported.



Clicking the **Data Sources** tab displays the associated <u>data sources</u> of the sample applications.




# **EXPORTING AN APPLICATION OR FOLDER BUNDLE**

Users with an Administrator or Designer role have the ability to export application or folder bundle and the associated data files.

#### Steps:


1. Right-click on a application or folder and select **Export Bundle** in the context menu.



**Application Folder or Subfolder Context Menu** 

**Application Context Menu** 

The corresponding notification message displays.



The **Include datasources and Include data files** check boxes are selected by default. This means the associated application data sources and data files will be included in the download.

# **SORTING THE LIST OF APPLICATIONS**


Sorting applications can be done by Name, Last Modified, or Status Updated.

Sort By	Default Sort Order		
Name Ascending			
Last Modified	Descending		
Status Updated	Descending		

## Steps:

On the Folders and Applications Summary layout, either:

click the **Sort By** option on the *Toolbar* of the *Grid View* By default, the sorting is by **Name**.




- Name
- Last Modified
- Status Updated

Then click the Sort Order.



□ click on the Name, Last Modified, or Status Updated column header of the List View




Then click the Sort Order.


- Ascending
- Descending

# **SEARCHING FOR APPLICATIONS**

To search for a particular application, enter it in the Search Application box.



You can also enter one of more characters into the *Search Application* box then click **Enter**. The list of applications that matched the entries will be displayed.




# **RENAMING APPLICATIONS OR FOLDERS**

A user with an Administrator or Designer role can rename applications and folders.

#### Steps:


1. Right-click on an application or folder then select **Rename** in the context menu.



Folder or Subfolder Context Menu

**Application Context Menu** 

The Rename Application or Rename Folder dialog displays.



2. Enter a new name then click

# VIEWING APPLICATION HISTORY AND REPUBLISHING


A user with either an Administrator or Designer role can also perform the following:

- □ View the change history of applications
- □ Republish an archived application to the recent version of Panopticon Streams Server


Rename an archived application

#### Steps:

1. On the Applications tab, right-click on an application and select History in the context menu.




The <Application Name> - History dialog displays:



Sort the archival list either through the *Date Archived* or *Archived By* by clicking on the or button.

Also, move to the other pages of the list by clicking on a page or clicking the or button.

- 2. You may opt to rename an archived application by entering a new one in the New Name box.
- 3. Click on an archived application in the list.




# VIEWING AND MANAGING APPLICATION TOPIC USAGES


On the **Applications** tab, you can view the input and output topic usages of an application.

## Steps:

1. On the **Applications** tab, right-click on an application and select **Topic Usage** in the context menu.



The <Application Name> Topics dialog displays.



If the application has been executed, the #Messages column will display the number of retrieved messages, while the Messages/sec column will display the number of retrieved messages per second.

If the application is not yet executed, both the #Messages and Messages/sec columns will display 0 values.

- 2. You can then opt to:
  - clear data
  - clear schemas
  - sort topics
- Click Close.

## **Clearing the Data In an Application Topic**

You can recycle an application by:

- stopping the application
- deleting data in the topics
- restarting the application

Follow the steps below to clear the data in an application topic.

#### Steps:

- 1. You can either:
  - Click to delete the data in a topic, or
  - Click
     Click
     Click to delete the data in all of the topics in an application
- 2. Click Close

## Clearing the Schema in an Application Topic

Schema registry can be cleared in any application topic.

### Steps:

- 1. You can either:
  - click to delete the schema in a topic, or
  - click Clear Schemas
    to delete the schema in all of the topics in an application
- 2. Click Close

## **Sorting Application Topics**

By default, the list of topics is sorted by Name in an ascending order.




Modify the sorting of the list by clicking the or button of the *Name*, *Type*, #Messages or Messages/sec columns. The icon beside the column that was used for the sorting will indicate if it was in an ascending or descending order.

# VIEWING THE APPLICATION DATA SOURCES USAGE


On the **Applications** tab, you can view the data sources that are currently used by an application.

#### Steps:

1. On the Applications tab, right-click on an application and select Data Source Usage in the context menu.



The list of data sources that is currently used by the application displays.



2. Click Close

## **MOVING APPLICATIONS**


Users with Administrator or Designer role are allowed to move an application to another folder or subfolder to which they have permission.

Moving applications can be done either through the toolbar or context menu.


#### Steps:

- 1. Select the check the box of one or multiple applications either on the Grid View or List View.
- 2. Then select either:
  - the **Move** icon on the toolbar
  - Move in the content menu


The *Move Application* dialog displays with the folder or subfolders to which the user is allowed to move the application.



3. Select the folder or subfolder.



4. Click Move



The application is moved and displayed on the selected folder.

# **COPYING APPLICATIONS**


Users with Administrator or Designer role are allowed to copy an application to another folder or subfolder to which they have permission.

Copying applications can be done either through the toolbar or context menu.


#### Steps:

- 1. Select the check box of one or multiple applications either on the Grid View or List View.
- 2. Then select either:
  - the **Copy** icon on the toolbar
  - Copy in the content menu


The Copy Application dialog displays with the folder or subfolders the user is allowed to copy the applications to.



3. Select the folder or subfolder.




4. Click Copy



The applications are copied and displayed on the selected folder.

# **DOWNLOADING AN APPLICATION**

Users with an Administrator or Designer role are allowed to download a copy of an application by right-clicking on an application and selecting **Download** in the context menu.



The application is downloaded.

## **DELETING AN APPLICATION**


Users with Administrator or Designer role are allowed to delete an application which can be done either through the toolbar or context menu.

## **Deleting Applications Using the Toolbar**

#### Steps:

- 1. Select the check box of applications either on the Grid View or List View.
- 2. Click on the toolbar.

A notification message displays.




3. Click Yes to remove.


## **Deleting Applications Using the Context Menu**

## Steps:

1. Right-click on an application and select **Remove** in the context menu.



A confirmation message displays.



# **CREATING A NEW APPLICATION**


A user with a Designer role can create new applications to folders or subfolders to which they have permission.

#### Steps:


1. On the **Applications** tab:



• right-click on a folder or subfolder and select **New Application**.




The New Application dialog displays.



2. Enter the Name of the application and click

Create

The Application page displays with the following sections. Initially, the Operator Settings pane is displayed.



Section/Pane	Description	
Application Name	Name of the application. Click the button to go back to the Applications listing page.	
Expand Graph	Expands the <i>Graph</i> pane.	
Error Validation	After <u>saving</u> the changes in the application, this allows <u>error validation</u> . If there are definition issues (red node) or if there is no traffic on the topic (yellow node), you can click to help fix the errors.  If there are no issues, is no longer displayed in the <i>Application</i> page.	
Add Operator	When enabled , displays the <i>Add Operator</i> pane and allows operators to be added in the application. Click to close the <i>Add Operator</i> pane.	
Delete Operator	Deletes the selected operator.	


Runs or executes an application.
Saves the changes made in the Application page.
Allows saving of changes made in the application or saving another copy. The application properties are also displayed and allows adding new ones.
Display the nodes and edges of the application model. It allows single node selection.
Available operators that can be added in the application.
When an operator has been added or a node is selected in the application graph, the corresponding operator settings are displayed in the <i>Operator Settings</i> pane to allow editing.  When the application is running, the operator settings are displayed but
are not editable.
Expands the Operator Settings pane.
Displays the preview of the data.

Refer to the sections below to proceed in creating an application.

## **ADDING AN OPERATOR**

Operators can be added in any order. The sequence or direction of the graph will be based on the inputs or outputs that will connect the nodes.


When adding an operator, its node will be displayed in the *Graph* pane.



**NOTE** 

- The edges (inbound and/or outbound) will depend on the operator.
- For best practice, start by adding Input operators (i.e., Input, External Input, or Metronome) and end with the Output operator.

Also, the corresponding Operator Properties and Schema are displayed on the Application page.




## **Adding an Input Operator**


Used to define the input data for the application model.

input1

### Steps:



The **Input** node icon displays in the *Graph* pane, as well as the properties to be defined in the *Operator Settings* pane, and the preview of the data in the *Schema* pane.



This operator serves as the initial source of the data in the application. The right (outbound) edge allows you to connect to other operators.

2. In the Operator Settings pane, define or select the following properties:


Property	Description	
Node ID	The ID of the input operator.	
Topic	The stream of records or input you will be subscribed to.  Select the Use Node ID check box to use the value entered in the Input ID. Otherwise, uncheck the box and enter a new Topic ID.  When adding Topic IDs, ensure they:  must be unique across an application  must be specified  must start with a letter (a to Z) or an underscore. Also, it can only contain letters (a to Z), numbers (0 to 9), and underscores	
Partition Count	Enter the number of partitions for the Kafka topics that will be created for the Input operator.  Partitions allow you to parallelize a topic by splitting the data in a particular topic across multiple brokers wherein, each partition can be placed on a separate machine to allow for multiple consumers to read from a topic in parallel.	
Input Type	Select the input type: <b>STREAM</b> , <b>TABLE</b> , or <b>GLOBAL_TABLE</b> .	

	STREAM will treat incoming data as a stream of records while TABLE creates a "materialized view" or snapshot table, representing the latest state of received key/value pairs. GLOBAL_TABLE can be seen as a materialized view that is distributed across all partitions. This is useful for keeping small, relatively static, data sets that needs to be joined with streaming data.
Priority	<ul> <li>Select the priority of the node's startup:</li> <li>APPLICATION – running and successful completion of the node is critical in the application startup.</li> <li>HIGHEST – highest priority but not critical.</li> <li>HIGH (Default) – high priority but not critical.</li> <li>STANDARD – standard priority.</li> <li>LOW – low priority.</li> </ul>
Data Source	<ul> <li>Select the data source.</li> <li>NOTES:</li> <li>It is recommended to upload the data source first so they will be available for selection.</li> <li>Selecting a non-streaming data source displays the Refresh Period (ms) property. Enter the refresh period for the data. This value determines when to periodically reload the data (from the beginning).</li> <li>Setting the Refresh Period to any value less than or equal to zero will disable automatic data reload.</li> <li>The preview of the data (OUTPUT) is displayed in the Schema pane.</li> </ul>
Key Columns	In Kafka, all messages are processed in a key/value fashion where the value represents the actual data payload or record. The key is used to determine how the key/value pairs are distributed across available partitions. If the key is null a round-robin approach is used to determine partition.  For the TABLE and GLOBAL_TABLE input type, key is also essential for defining how records are segregated (keyed) in the table. Not providing a key will result in a single-row table.  Post input, keying of records can be changed by using either the Rekey or Aggregation operators.

NOTE

Node ID, Topic, Input Type, and Data Source properties are required.

3. In the *Key Columns* section, click <sup>+</sup> to add a key column from the data source schema. Repeat to add more.



You can also delete a key column in the list by clicking X.

4. Save the changes.

### **Example**

## **Adding An Aggregation Operator**

The aggregation operator aggregates the data based on a grouping key and a set of aggregated fields.


Steps:



1. On the Application page, click and select Aggregation Aggregati... in the Add Operator pane.

aggregation1

The **Aggregation** node icon displays in the *Graph* pane, as well as the properties to be defined in the *Operator Settings* pane, and the preview of the data in the *Schema* pane.



This operator has left (inbound) and right (outbound) edges that allow connection to other operators in the application.

2. In the Operator Settings pane, define or select the following required properties:


Property	Description		
Node ID	The ID of the aggregation operator.		
Inputs	Automatically connects to the currently selected operator.  You can select another ID of the operator that will be the source of the data in the <i>Inputs</i> drop-down list.  The preview of the data (INPUT) is displayed in the <i>Schema</i> pane.		
Window Type	Select either:  Tumbling (default)  A series of fixed-sized, non-overlapping, and adjoining time intervals.		

	This window type is a moving window whose window size ( <i>Time Window</i> ) is equal to its advance interval. Since tumbling windows never overlap, a data record will belong to only one window.
	Hopping
	This window type models fixed-sized, scheduled overlapping windows.
	Defined by the window's size ( <i>Time Window</i> ) and advance interval ( <i>Advance Period</i> ).
Time Window	The window's size (in milliseconds).
Advance Period	The advance interval for the <i>Hopping Window</i> (in milliseconds). Specifies by how much a window moves forward relative to the previous one.
Enable Cache	Specifies whether to start or stop caching tables. When caching is stopped, it gets every event input into the table to produce an output event. This is necessary for delta/prev aggregates.
Group By	The name/IDs of the columns that the data will be grouped by. (Proceed to step 3.)
Fields List	A set of aggregated fields (with actions and expressions). (Proceed to step 5.)


- 3. In the *Group By* section, click <sup>+</sup> . A column is added in the list. Click the drop-down list to select another column.
- 4. Select a column that will be used to group the data.

The INPUT and OUTPUT schema are displayed.

Schema	INPUT OUTPUT		
Field Name	Туре		
Region	string (key, null)		
Country	string (null)		
Exchange	string (null)		
Name	string (null)		
Forex	string (null)		
Symbol	string (null)		
ISIN	string (null)		
SEDOL	string (null)		
Close_local	double (null)		
Mcap_local	double (null)		
Mcap_USD	double (key, null)		
Industry	string (key, null)		



Repeat steps 3 and 4 to add more.



You can also delete a column in the *Group By* list by selecting its check box and clicking .

5. Under the *Field List* section, click \* . A new field entry displays.



6. Enter the Field Name and the <u>Expression</u> that will be evaluated for each incoming record.

Example:

Field Name: Count Expression: count()

7. Repeat steps 5 and 6 to add more aggregated fields.

Actio	n	Field Name	Expression	A .	+ -
Add	~	Count	count()		fx
Add	~	Samples	samples(Mcap_USD)		fx
Add	~	Sum_Mcap_USD	sum(Mcap_USD)		fx
Add	~	First_Close_local	first(Close_local)		fx
Add	~	Last_Close_local	last(Close_local)		fx
Add	~	Min_One_Day_Change	min(One_Day_Change)		fx
Add	~	Max_One_Day_Change	max(One_Day_Change)		fx
Add	~	Avg_One_Day_Change	avg(One_Day_Change)		fx
Add	~	Varp_One_Day_Change	varp(One_Day_Change)		fx
Add	~	Vars_One_Day_Change	vars(One_Day_Change)		fx

#### You can also:

- check the topmost box to select all of the fields
- change the order of the fields by checking a field's box and clicking either the or button
- delete a field entry in the Field List by checking its box and clicking

The OUTPUT schema is updated based on the added aggregations.

Schema	INPUT OUTPUT	
Field Name	Туре	
Industry	string (key, null)	
Count	long (not null)	
Sum_Mcap_USD	double (not null)	
First_Close_local	double (null)	
Last_Close_local	double (null)	
Min_One_Day_Change	double (null)	
Max_One_Day_Change	double (null)	
Samples	long (not null)	
Avg_One_Day_Change	double (null)	
Varp_One_Day_Change	double (null)	
Vars_One_Day_Change	double (null)	
Sdevp_One_Day_Change	double (null)	
Sdevs_One_Day_Change	double (null)	

8. Save the changes.

## **Example**

## **Building the Expression**

To build the expression, you can either:


□ manually enter into *Expression* text box

Take note that the column name is case sensitive.

A validation error displays with a suggestion to help build the expression.

Examples:

		Add	~	Samples	samples(MCAP_USD)				
		Col 8: Ur	nable	to find column MCAP_USD , did yo	ou mean Mcap_USD				
	Click	the link (	(e.g., [	Mcap(USD)] to apply the correct e	ntry.				
		Add	~	Samples	samples(				
	col.8: Something missing? Got <nothing> expected or ')'</nothing>								
	Com	plete the	expre	ssion as necessary.					
	use t	he <u>Expre</u>	ssion	<u>Builder</u>					
Us	ing th	ne Expre	essio	n Builder					
		ew fields and oper			input operator and supported <u>aggregation</u> or	<u>calcu</u>	lation	1	
Ste	eps:								
1.	On th	ne <i>Field</i> s	List se	ection, click + to add a new field	instance.				
		Action	1	Field Name	Expression	•	•	+	_
		Add	~						fx
	Field Name is required								
2.	Ente	r the <i>Fiel</i>	d Nam	ne.					
3.	Click	the <b>New</b>	Expr	ession $f_X$ icon.					
	The	Expressio	on <fi< th=""><th>eld Name&gt; dialog displays.</th><th></th><th></th><th></th><th></th><th></th></fi<>	eld Name> dialog displays.					



4. Build an expression by double-clicking in the list of Functions, Fields, and Columns.

You can also click on a function and operator then

To search for a particular column or function, enter it in the Search Fields/Search Functions box.

Add



Or enter one or more characters/alphabets into the *Search Fields* box and the suggested list of columns that matched the entries will be displayed.

For example, after entering **One**, the list will be displayed such as below:







#### **Supported Aggregation Functions**

This section lists the aggregation functions that are only supported in aggregation operator expressions.

NOTE	Panopticon Streams also supports nullability where:
	a field may or may not allow null/empty/missing/NA values.
	<ul> <li>functions or operators may or may not allow null arguments (e.g., you can't divide seven by null).</li> </ul>

Aggregation Function	Description	Example	Nullability
avg(X)	Average of a field across records.	avg(numericField)	<b>~</b>
collect(X)	Returns last n values of a field across records.  collect(fieldName,valuesCount)  Parameters:  fieldName – Field name whose last n values should be retained.  valuesCount – Number of values to be retained.	collect(symbol,3)	•
count(X)	Counts the number of records.	count()	

Aggregation Function	Description	Example	Nullability
delta(X) Returns the difference of the last and second last value of the integer field.		delta(numericField)	<b>~</b>
first(X)	First value of a field.	first(fieldName)	~
firstNonNull(X)	First non-null value of a field.	firstNonNull(fieldName)	~
last(X)	Last value of a field.	last(fieldName)	•
lastNonNull(X)	Last non-null value of a field.	lastNonNull(fieldName)	~
max(X)	Maximum of an integer field across records.	max(fieldName)	~
min(X)	Minimum of an integer field across records.	min(fieldName)	~
prev(X)	Previous values of a field record.	prev(fieldName)	<b>✓</b>
samples(X)	Count of non-null values of field records.	samples(fieldName)	~
sdevp(X)	Returns the standard deviation of an entire population.	sdevp(numericField)	~
sdevs(X)	Estimates standard deviation based on a sample.	sdevs(numericField)	~
sum(X)	Sums a field across records.	sum(numericField)	~
varp(X)	Returns the variance in an entire population.	varp(numericField)	~
vars(X)	Returns the variance based on a sample.	vars(numericField)	~
wavg(X)	Weighted average of a field across records.  wavg(score,weight)  Parameters:  score – Numeric field for score.  weight – Numeric field for weightage.	wavg(marks,weight)	•

NOTE

The following aggregates work with a time window (can subtract): count, samples, sum, sdev, var, and avg

## **Converting Timestamp to/from Integer**

Allows you to convert Tim	estamp values to/from I	Integer which includ	de the followin	g examples:

- from posix to timestamp
- □ from posixmillis to timestamp
- □ from timestamp to posix
- from timestamp to posixmillis

The conversion uses the expression: to ([typename], [expression], [format]

#### Examples:

□ to(int, timefieldname, 'POSIX')

to(time, intfieldname, 'POSIX')

## **Adding a Branch Operator**

The branch operator will split a stream into one or more branches. The path for a stream is determined by a configured predicate within the branch operator.

The predicate expression will be evaluated for each incoming record. A record will be routed to the first branch with a matching predicate.


#### Steps:



1. On the *Application* page, click and select **Branch** in the *Add Operator* pane.

branch1

The **Branch** node icon displays in the *Graph* pane, as well as the properties to be defined in the



The left (inbound) edge allows you connect to an input data or operator. The right (outbound) edges allow you to add more streams.

2. In the Operator Settings pane, define or select the following required properties:

Property	Description
Node ID	The ID of the branch operator.
Inputs	Automatically connects to the currently-selected operator.  You can select another ID of the operator that will be the source of the data in the <i>Inputs</i> drop-down list.  The preview of the data (INPUT/OUTPUT) is displayed in the <i>Schema</i> pane.
Predicate	A list of predicates. Each predicate contains an <u>expression</u> that will be evaluated for each record.

3. To add more predicates, click - . A new predicate entry displays.

Enter at least two expressions.

Predicate	+	-
One_Day_Change < 0		
One_Day_Change >= 0		

You can also:

- select the topmost check box to select all of the fields
- delete a field entry in the Field List by selecting its check box and clicking
- 4. Save the changes.

#### **Example**

## Example 2

```
<streams>
    <stream>
        <source>Input</source>
            <operator>Branch</operator>
        </sink>
    </stream>
       <source>Branch</source>
       <port>1</port>
       <sink>
            <operator>Output1</operator>
       </sink>
    </stream>
    <stream>
        <source>Branch</source>
        <port>2</port>
        <sink>
           <operator>Output2</operator>
        </sink>
    </stream>
</streams>
```

# **Adding a Calculation Operator**


The calculation operation will calculate a field and add the result as an additional field. Usually, input fields pass through an operation, but calculations can also be set to replace existing fields or simply remove them.


Steps:



1. On the *Application* page, click <sup>†</sup> and select **Calculation** Calculation in the *Add Operator* pane.

calculation1





This operator has left (inbound) and right (outbound) edges that allow connection to other operators in the application.

2. In the Operator Settings pane, define or select the following required properties:


Property	Description
Node ID	The ID of the calculation operator.
Inputs	Automatically connects to the currently-selected operator.  You can select another ID of the operator that will be the source of the data in the <i>Inputs</i> drop-down list.  The preview of the data (INPUT and OUTPUT) are displayed in the <i>Schema</i> pane.
Fields List	Set of fields (with actions and expressions). Enter at least one calculated field. Proceed to step 3.

3. Enter the Field Name and the Expression that will be evaluated for each incoming record.

To use the expression builder, click the **New Expression** 



The Expression <Field Name> dialog displays.



Build an expression by double-clicking in the list of Functions, Fields, and Columns.

You can also click on a function and operator then




To search for a particular column or function, enter it in the Search Fields/Search Functions box.



Or enter one or more characters/alphabets into the Search Fields box and the suggested list of columns that matched the entries will be displayed.

For example, after entering Numeric, the list will be displayed such as below:

# Fields Q Numeric Numeric1 double



5. Click  $^{+}$  to add a new field entry and repeat steps 3 and 4.

The OUTPUT schema is updated based on the added calculations.

Schema	INPUT OUTPUT
Field Name	Туре
KeyField	string (key, null)
Text1	string (null)
Text2	string (null)
Numeric1	double (null)
Numeric2	double (null)
Integer1	double (null)
DateTime1	datetime (null)
Bool1	string (null)
DateTime2	datetime (null)
Calc_Diff	double (not null)
Calc_Mod	double (not null)

#### You can also:

- select the topmost check box to select all of the fields
- change the order of the fields by selecting a field's check box and clicking either the or button
- delete a field entry in the Field List by selecting its check box and clicking
- 6. Save the changes.

## **Supported Operators and Calculation Functions**

This section lists the supported operators and calculation functions in Panopticon Streams.

#### NOTE

Panopticon Streams supports nullability where:

- a field may or may not allow null/empty/missing/NA values
- functions or operators may or may not allow null arguments (e.g., you can't divide seven by null)

## **Supported Operators**

These are typically the operators that are used to create aggregation operator and calculation operator expressions.

Operator	Name	Description	Example	Nullability
!	Logical NOT	<ul> <li>! boolean</li> <li>Reverse arguments or results.</li> <li>Parameter:</li> <li>boolean – A value of logical expression that can be evaluated as TRUE or FALSE.</li> </ul>		
!=	Not Equal To	Tests if one value is not equals to another.	12.3 != 47.11 = true	~
%	Modulo	number % divisor  Gets the remainder from division.  Parameters:  • number – The Number to be divided.  • divisor – The number to divide with.	17 % 5 = 2	
&&	Logical AND	Returns true only if both the conditions return true.	(7 > 5)&&(3 < 8) = true	
*	Multiplication	Multiply	9 * 5 = 45	
+	Addition	Adds two numbers or joins two or more text strings to produce a single piece of text.	47.11 + 9.7 = 56.81	
-	Subtraction	Subsctracts two numbers.	47 – 11 = 36	
1	Division	number / divisor Parameters:  number – The number to be divided. divisor – The number to divide with.	11 / 5 = 2	
<	Less than	Tests if one value is less (smaller) than another.	4 < 7 = true	
<=	Less Than or Equal To	Tests if one value is less than or equal to another.	7 <= 4 = false	
==	Equal To	Tests if one value is equals to another.	9 == 5 = false	~
>	Greater Than	Tests if one value is greater (larger) than another.	7 > 4 = true	
>=	Greater Than or Equal To	Tests if one value is greater or equal to another.	7 >= 4 = true	
?:	Ternary IF	Provides branching capability. If condition is true, then it returns exprlfTrue, else returns exprlfFalse.  condition ? exprlfTrue : exprlfFalse  Parameters:  condition – A value or logical expression that can be evaluated as true or false.  exprlfTrue – The value to return when condition evaluates to true.		•

Operator	Name	Description	Example	Nullability
		exprlfFalse - The value to return when condition evaluates to false.		
٨	Exponentiation	Get the exponential value of the number.	(2.0) ^ 7.0 = 128.0	
like	Like	Tests if the pattern exists in the text.	'olle' like pattern('.ll.') = true	
II	Logical OR	Returns true if any of the conditions return true.	(7 > 5)    (3 > 8) = true	
-	Negation	Negation of the number.	-(1 + 2 ) = -3	
+	Positivity	Positivity of the number.		
()	Cast Operator	Explicit data type conversion.  Valid casts are:  'int'  'real'  'text'  'time'  'bool'	(int)sqr(Numeric1)	

# **Supported Calculation Functions**

Operator	Name	Description	Example	Nullability
abs	Absolute Value	<ul> <li>abs(number)</li> <li>Find the absolute value of a number.</li> <li>Parameter:</li> <li>number – The number to get the absolute number of.</li> </ul>	abs(-47.11) = 47.11	
array	Array	<ul> <li>array(size,value)</li> <li>Create an array of specified size and initialize with the given value.</li> <li>Parameters:</li> <li>size – Size of the array.</li> <li>value – Array elements.</li> </ul>	array(5, 1.1)	•
atan	Arc Tangent	<ul> <li>atan(ordinate, abscissa)</li> <li>Get the inverse tangent of a number.</li> <li>Parameters:</li> <li>ordinate – The ordinate coordinate.</li> <li>abscissa – The abscissa coordinate (optional).</li> </ul>	atan(1.0) = 0.785398	
ceil	Ceiling	ceil(number)  Returns the smallest double value that is greater than or equal to the argument and is equal to a mathematical integer.	ceil(4.7) = 5.0	

Operator	Name	Description	Example	Nullability
		Parameter:  number – The number to get the ceiling value of.		
clock	Clock	Returns the current system Date/Time value.	clock()	
concat	Concatenate	concat(text1,text2) Joins two text values. Parameters:  text1 – First text to join.  text2 – Second text to join.	concat('olle','pelle') = 'olle pelle'	
cos	Cosine	<ul> <li>cos(number)</li> <li>The natural logarithm (base e) of a real value.</li> <li>Parameter:</li> <li>number – A number to take the natural logarithm of .</li> </ul>	cos(0.0) = 1.0	
cosh	Hyperbolic Cosine	cosh(number) Get the hyperbolic cosine of the number. Parameter:  number – The number to get the hyperbolic cosine of.	cosh(0.0) = 1.0	
cot	Cotangent	<ul> <li>cot(number)</li> <li>Get the cotangent of the number.</li> <li>Parameter:</li> <li>number – The number to get the cotangent of.</li> </ul>		
dateDiff	Date Difference	dateDiff(startDatetime,endDatetime,unit)  Calculates the difference in whole units between two time values, the return value is positive if endDatetime comes after startDatetime, and is negative if endDatetime comes before startDatetime.  Valid units are 'DAYS', 'HOURS', 'MINUTES', 'SECONDS, 'MILLISECONDS', 'MICROSECONDS', AND 'NANOSECONDS'.  Parameters:  • startDatetime – The first (later) Date/Time value.  • endDatetime – The second (earlier) Date/Time value.  • unit – The time unit to use.	dateDiff(#2019-06- 17#,#2019-06- 14#,'DAYS') = 3	
dateDiff2	Date Difference	Calculates the difference in fraction units between two time values, the return vallue is positive if endDatetime comes after startDatetime, and is negative if endDatetime comes before startDatetime.	dateDiff2(#2019-06- 17T12:00:00#,#2019- 06- 14T00:00:00#,'DAYS' ) = 3.5	

Operator	Name	Description	Example	Nullability
		Valid units are 'DAYS', 'HOURS', 'MINUTES', 'SECONDS, ''MILLISECONDS', 'MICROSECONDS', AND 'NANOSECONDS'. Parameters:  • startDatetime – The first (later) time value.  • endDatetime – The second (earlier) time value.  • unit – The time unit to use.		
datePart	Date Part	Returns a specified part of a time value, the result is an integer value.  Valid units are 'DAYS', 'HOURS', 'MINUTES', 'SECONDS, 'MILLISECONDS', 'MICROSECONDS', AND 'NANOSECONDS'.  Parameters:  datetime – The Date/Time value.  part – The time part to get.	datePart(#1973-07- 23#,'YEARS') = 1973	
dateTrunc	Date Truncate	dateTrunc(datetime,datetimePart)  Truncates the specified time value to the accuracy specified by the time_part.  Valid units are 'DAYS', 'HOURS', 'MINUTES', 'SECONDS, ''MILLISECONDS', 'MICROSECONDS', AND 'NANOSECONDS'.  Parameters:  datetime – The Date/Time value.  datetimepart – The Date/Time part to be truncated.	dateTrunc(#1973-07- 23T12:34:56#,'YEAR S') = #1973-01- 01T00:00:00#	
ехр	Exponential	exp(number)  Find the value of e raised to the power of a number.  Parameter:  number – The power that e is raised to.	exp(0.0) = 1.0	
find	Find	find(findText,withinText,startPosition) Returns the starting position of one string within another string, given a starting position. Parameters:  findText – The text to find.  withinText – The text to search within.  startPosition – Start the search from this position (optional).	find('ab','drabant') = 3	
floor	Floor	floor(number)  Returns the largest real value that is less than or equal to the argument and is equal to a mathematical integer.  Parameter:  number – The number to get the flloor value of.	floor(4.7) = 4.0	

Operator	Name	Description	Example	Nullability
get	Get	<ul> <li>get(array,position)</li> <li>Gets the nth element of the array.</li> <li>Parameters:</li> <li>array – Array of items.</li> <li>position – Array element at this position.</li> <li>NOTE: Index of the array starts with 0.</li> </ul>	get(array(5,1.1),1) = 1.1	•
if	If	<ul> <li>if(condition,exprlfTrue,explfFalse)</li> <li>The function provides branching capability. If condition is true, then it returns exprlfTrue, else it returns exprlfFalse.</li> <li>Parameters:         <ul> <li>condition – A value or logical expression that can be evaluated as true or false.</li> </ul> </li> <li>exprlfTrue – The value to return when condition evaluates to true.</li> <li>exprlfFalse – The value to return when condition evaluates to false.</li> </ul>	if(a < b, a,b)	•
ifNull	ifNull	<ul> <li>ifNull(expression,altValue)</li> <li>The ifNull function returns the specified value if the expression is null, otherwise returns the expression.</li> <li>Parameters:</li> <li>expression – The expression to test whether it is null.</li> <li>altValue – The value to return if the expression is null.</li> </ul>	ifNull(null, 'b') = 'b'	•
index	Index	<ul> <li>index(array,text)</li> <li>Sorts the input array and outputs a lookup index.</li> <li>Parameters:         <ul> <li>array – Array of items.</li> </ul> </li> <li>text – The order which the array should be sorted, the valid texts are 'asc' for ascending order or 'desc' for descending order.</li> </ul>	index(array(3,#1973- 07-23#),'asc')	
intpow	Integral Power	<ul> <li>intpow(number,power)</li> <li>Raise a number to a power.</li> <li>Parameters:</li> <li>number – Number to raise a power.</li> <li>power - The power to raise a number to.</li> </ul>	intpow(2.0, 3.9) = 8.0	
invert	Invert	Inverts a lookup index. Since the index function returns an inverse permutation, you can apply the invert function which will turn it into a forward permutation (or rank).		
left	Left	left(text,numofChars)	left('olle', 3) = 'oll'	

Operator	Name	Description	Example	Nullability
		Returns the leftmost characters from a string producing a new string.  Parameters:  text – The text from which to extract characters.		
		<ul> <li>numofChars – Number of characters to be picked from the left.</li> </ul>		
len	Length	len(value) Returns the number of characters in a string or the number of elements in an array. Parameter:  • value – String or array to find the length of.	len('olle') = 4	
In	Logarithm	In(number) The natural logarithm (base e) of a real value. Parameter:  number – A number to take the natural logarithm of.	In(1) = 0	
log	Logarithm	log(number) Logarithm with base 10. Parameter:  number – Number of which you want the logarithm.	log(1000.0) = 3.0	
logn	Logarithm	Iogn(number,logBase) Returns the Log Based N of Input. Parameters:  number – Number of which you want the logarithm.  logBase – Base of the logarithm.	logn(4711.0,4711.0) = 1.0	
lower	Lower	lower(text) Convert text to lower case. Parameter:  text – Text to change case to lower.	lower('OLLE') = 'olle'	•
max	Maximum	Maximum of the two numbers.	max(11.0, 47.0) = 47.0	
mid	Mid	mid(string,startPosition,numofChars) Returns the characters from the middle of a text string, given a starting position and length. Parameters:  string – The original string.  startPosition – Starting position in string.  numofChars – Length of the substring.	mid('olle', 2,2) = 'll'	
min	Minimum	Minimum of the two numbers.	min(47.0, 11.0) = 11.0	

Operator	Name	Description	Example	Nullability
pow	Power	<ul> <li>pow(number,power)</li> <li>Raise a number to a power.</li> <li>Parameters:</li> <li>number – Number to raise a power.</li> <li>power – The power to raise a number to.</li> </ul>	pow(-2.0, 7.0) = - 128.0	
proper	Proper	proper(text)  Converts a text to proper case; the first letter in each word in uppercase, and all other letters in the lower case.  Parameter:  text – The text to make as a proper case.	proper('olle asp') = 'Olle Asp'	•
random	Random	random(minimumValue,maximumValue) Returns a random number with a positive sign. Parameters:  minimumValue – Minimum value or a random number (optional).  maximumValue - Maximum value or a random number (optional).	random(12.0) get a floating-point random number greater than or equal to 0.0 and less than 12.0	
replaceAll	Replace All	replaceAll(string,oldText,newText) Replaces all occurences of the pattern with the replacement string. Parameters:  string – The original string.  oldText – The string to be replaced.  newText – The new replacement string.	replaceAll('axa', 'a', 'b') = 'bxb'	•
replaceFirst	Replace First	replaceFirst(string,oldText,newText) Replaces the first occurrence of the pattern with the replacement string. Parameters:  string – The original string. oldText – The string to be replaced. newText – The new replacement string.	replaceFirst('axa', 'a', 'b') = 'bxa'	•
right	Right	right(text,numofChars) Returns the rightmost characters from a string producing a new string. Parameters:  text – The text from which to extract characters.  numofChars – Number of characters to be picked from the right.	right('olle', 3) = 'lle'	
rnd	Rnd	rnd(scaleValue)  Returns a random number with a positive or negative sign depending on scale value.		

Operator	Name	Description	Example	Nullability
		Parameter:  • scaleValue – Positive scaleValue will result in a number that is maximum up to it and the negative scaleValue will result in a number that is minimum to it.		
round	Round	<ul> <li>round(number,digits)</li> <li>Round a number to a given number of digits.</li> <li>Parameters:</li> <li>number – The number to round.</li> <li>digits – The place at which number should be rounded (optional).</li> </ul>	round(47.11) = 47.0	
set	Set	set(array,position,newvalue) Sets the nth element of the array. Parameters:  array – Array of items.  position – Array element at this position.  newvalue – New value of the element.  NOTE: Index of first element starts with 0.	set(array(5, 1.1), 1, 2.2)	
sign	Sign	sign(number)  Get the sign of a number, returns one if positive, negative one if negative, and zero if zero.  Parameter:  number – The number to get the sign of.	sign(7) = 1	
sin	Sine	sin(number)  Get the sine of the number.  Parameter:  number – The number to the sine of.		
sinh	Sinus Hyperbolic	sinh(number)  Get the sinus hyperbolic of the number.  Parameter:  number – The number to the sinus hyperbolic of.	sinh(0.0) = 0.0	
sort	Sort	Applies a lookup index to an array.		
sqr	Square	sqr(number)  Returns square of the number.  Parameter:  number – The number to get the square of.	sqr(3) = 9	
sqrt	Square Root	sqrt(number) Returns square root of the number. Parameter:	sqrt(9.0) = 3.0	

Operator	Name	Description	Example	Nullability
		number – The number to get the square root of.		
tan	Tangent	tan(number) Get the tangent of the number. Parameter:  number – The number to get the tangent of.	tan(0.0) = 0.0	
trim	Trim	trim(text) Get the input text stripped of leading or following spaces.  Parameter:  text – The text to be stripped of leading or following spaces.	trim(' olle ') = 'olle'	•
trunc	Truncate	trunc(number,digits) Truncate a number to a given precision. Parameters:  number – The number to truncate. digits – The precision of the truncation (optional and the default is 0).	trunc(47.11) = 47.0	
upper	Upper	upper(text) Convert text to upper case. Parameter: text – Text to change case to upper.	upper('olle') = 'OLLE'	

### **Example**

# **Adding a Conflate Operator**

The conflate operation is used to lower the frequency of updates. The conflate will retain the last records seen on the input and push them to the output stream on a fixed interval. For example, if the input is producing a high frequency data throughput, instead of processing all of these updates, a configured conflate will only push through a small set of records on a fixed interval.


#### Steps:



1. On the *Application* page, click and select **Conflate** in the *Add Operator* pane.



The **Conflate** node icon displays in the *Graph* pane, as well as the properties to be defined in the *Operator Settings* pane, and the preview of the data in the *Schema* pane.



This operator has left (inbound) and right (outbound) edges that allow connection to other operators in the application.

2. In the Operator Settings pane, define or select the following properties:

Property	Description
Node ID	The ID of the conflate operator.
Inputs	Automatically connects to the currently-selected operator.
	You can select another ID of the operator that will be the source of the data in the <i>Inputs</i> drop-down list.
	The preview of the data (INPUT and OUTPUT) are displayed in the <i>Schema</i> pane.

Interval	The interval of which the data should be published to the output stream (in milliseconds).
Timestamp	The timestamp.
Keep Records	Check to retain or not remove flushed elements. This means the entire set of records will be flushed at each interval.

NOTE Node ID, Inputs, and Interval are required properties.

3. Save the changes.

## **Example**

```
<conflate>
     <id>Conflate </id>
     <interval>10000</interval>
</conflate>
```

# **Adding an External Input**

Sources data directly from a Kafka topic.

Steps:




1. On the *Application* page, click and select **External\_input** 

external\_input1

Input in the Add Operator pane.

The **External Input** node icon displays in the *Graph* pane, as well as the properties to be defined in the *Operator Settings* pane, and the preview of the data in the *Schema* pane.



This operator serves as the initial source of the data in the application. The right (outbound) edge allows you to connect to other operators.

2. In the *Operator Settings* pane, define or select the following properties:

Property	Description	
Node ID	The ID of the external input operator.	
Input Type	Select the input type: STREAM, TABLE, or GLOBAL_TABLE.	
Priority	<ul> <li>Select the priority of the node's startup:</li> <li>APPLICATION – running and successful completion of the node is critical in the application startup.</li> <li>HIGHEST – highest priority but not critical.</li> <li>HIGH (Default) – high priority but not critical.</li> <li>STANDARD – standard priority.</li> <li>LOW – low priority.</li> </ul>	
Topic	The stream of records or input you will be subscribed to.	
From Beginning	Select the check box to retrieve full history (from beginning to the latest) of the topic. If un-checked, only the latest messages after the application has started will be retrieved.	
Partition Count	Enter the number of partitions for the Kafka topics that will be created for the External Input operator.  Partitions allow you to parallelize a topic by splitting the data in a particular topic across multiple brokers wherein, each partition can be	

placed on a separate machine to allow for multiple consumers to read from a topic in parallel.


**NOTE:** The External Input topic pulls the default partition count from the provided topic meta with generate schema call.

**NOTE** 


Node ID, Input Type, and Topic properties are required.

#### 3. Select the Parser Plugin:

Avro



Protobuf



Click Browse

to select the File Descriptor (.desc file) in the Open dialog.

Then enter the Schema Name and Type Name.

Property	Description		
Schema Name	The Protobuf schema.		
Type Name	The message of Protobuf type that will be sent to Kafka.		
File Descriptor	The FileDescriptorSet which:		
	is an output of the protocol compiler.		
	• represents a set of .proto files, using thedescriptor_set_out option.		

XML

Parser Plugin	Xml		~	
Record Xpath				(eg. //myroot/items/item)
Generate Output Schema				
Source	Target	XPath	Туре	Date Format +
Key	+ -			
JSON				
Parser Plugin	Json		~	
Record Path				(eg. myroot.items.item)
Generate Output Schema				
Source	Target	Json Path	Туре	Date Format +
Key	+ -			
Text If <b>Text</b> has been selected message includes columr		Delimiter and Text	<b>Qualifier</b> , and i	f the first row of the
Parser Plugin	Text		~	
Column Delimiter			~	
Text Qualifier			~	
First Row Headings				
Generate Output Schema				
Source	Target	Index	Туре	Date Format + -
Key	+ -			

4. You can also click the following icons:

Button	Description
	Fetch the schema of the output topic. This populates the list of columns, with the data type found from inspecting the first 'n' rows of the file.
+	Add a new field entry.



5. Enter or select the following properties:

Property	Description
Source	The column name of the source schema.
Target	The column name of the target schema.
XPath/Json Path/Index	The column name of the target schema.
Туре	The data type of the column. Can be: BOOLEAN, DATE, DATETIME, DOUBLE, FLOAT, INT, LONG, STRING, TIME.
Date Format	Date/Time format when the data type is <b>DATE, DATETIME</b> , or <b>TIME</b> .

6. In the Key section, click \* to add a key column from the data source schema. Repeat to add more.

You can also delete a key column in the list by selecting its check box and clicking

7. Save the changes.

# **Adding a Filter Operator**


Used to filter a data source based on a predicate.

Steps:




1. On the *Application* page, click and select **Filter** in the *Add Operator* pane.

The **Filter** node icon displays in the *Graph* pane, as well as the properties to be defined in the *Operator Settings* pane, and the preview of the data in the *Schema* pane.



This operator has left (inbound) and right (outbound) edges that allow connection to other operators in the application.

2. In the Operator Settings pane, define or select the following required properties:



3. Save the changes.

#### **Example**

# **Adding a Join Operator**

Used to join data sources using common keys.


join1

#### Steps:



1. On the *Application* page, click <sup>†</sup> and select **Join** in the *Add Operator* pane.

The **Join** node icon displays in the *Graph* pane, as well as the properties to be defined in the *Operator Settings* pane, and the preview of the data in the *Schema* pane.



The left (inbound) edges allow you to select the input sources or operators that will be joined. The right (outbound) edge allows you to connect to other operators.

2. In the Operator Settings pane, define or select the following properties:

Property	Description
Node ID	The ID of the join operator.
Inputs	The left input automatically connects to the currently-selected operator. You can select another ID of the operator that will be the source of the data in the <i>Inputs</i> drop-down list.
	Then select the right input.
	The preview of the data (LEFT, RIGHT, and OUTPUT) are displayed in the <i>Schema</i> pane.
Time Window	The time window for the join operation (in milliseconds).
Join Type	The type of the join: INNER, LEFT, or OUTER
Left Field	The columns from the left source that will be used to join with.
Right Field	The columns from the right source that will be used to join with.



3. In the Fields List section, click \* . The key columns of the left and right sources are automatically displayed.



Repeat step 3 to add more columns.

You can also:

- select the topmost check box to select all of the fields
- delete a field entry in the Field List by selecting its check box and clicking

The LEFT, RIGHT, and OUTPUT schema are displayed.

ichema	LEFT RIGHT OUTPUT
Field Name	Туре
Ticker	string (key, null)
Date	datetime (null)
Adj_Close	double (null)
Period_Change_proc	double (null)
Volume	double (null)
Turnover	double (null)
SP500_Change	double (null)
Relative_Change	double (null)
Holding	double (null)

Schema	LEFT RIGHT OUTPUT
Field Name	Туре
Region	string (null)
Country	string (null)
Exchange	string (null)
Name	string (null)
Forex	string (null)
Symbol	string (null)
ISIN	string (null)
SEDOL	string (null)
Close_local	double (null)
Mcap_local	double (null)
Mcap_USD	double (null)
Industry	string (null)


chema	LEFT RIGHT OUTPUT
Field Name	Туре
Ticker	string (key, null)
Date	datetime (null)
Adj_Close	double (null)
Period_Change_proc	double (null)
Volume	double (null)
Turnover	double (null)
SP500_Change	double (null)
Relative_Change	double (null)
Holding	double (null)
Country	string (null)
Exchange	string (null)
Name	string (null)

4. Save the changes.

#### **Example**


## **Fixing Broken Joins**

Changes in the input data sources may cause issues in the Join operator of an application like broken joins and output schema.



For example, if the original data source contains **Brand** and **Country** columns:





And if eventually the column **Country** is deleted in the data source, opening the application again will display:





Click **Manually Update Output Schema** to fix this error. Note that Country is no longer in the list of the Output schema.



to apply the changes.


On the other hand, if new columns are added in the data source (e.g., if the **Country** column is added in the data source again), opening the application will display:

Click





Click Manually Update Output Schema. Note that Country is added in the Output schema.





# **Adding a Metronome Input Operator**

Similar with a synthetic input, this operator acts as a single timestamp field schema generator.


Steps:



1. On the *Application* page, click <sup>+</sup> and select **Metronome** Metronome in the *Add Operator* pane.

metronome1


The **Metronome** node icon displays in the *Graph* pane, as well as the properties to be defined in the *Operator Settings* pane, and the preview of the data in the *Schema* pane.



2. In the *Operator Settings* pane, define or select the following required properties:

Property	Description
Node ID	The ID of the metronome operator.
Topic	The stream of records or input you will be subscribed to.
	Select the <i>Use Node ID</i> check box to use the value entered in the <i>Input</i> ID. Otherwise, uncheck the box and enter a new <i>Topic</i> ID.
	When adding Topic IDs, ensure they:
	must be unique across an application
	must be specified
	<ul> <li>must start with a letter (a to Z) or an underscore. Also, it can only contain letters (a to Z), numbers (0 to 9), and underscores</li> </ul>
Partition Count	Enter the number of partitions for the Kafka topics that will be created for the Metronome operator.
	Partitions allow you to parallelize a topic by splitting the data in a particular topic across multiple brokers wherein, each partition can be placed on a separate machine to allow for multiple consumers to read from a topic in parallel.
Interval	The interval of which the data should be published to the output stream.
Name Field Id	The ID of the name field.
Name	The name of the ID.
Timestamp	The name of the new column that will include the timestamp.

The preview of the data (OUTPUT) is displayed in the Schema pane.



3. Save the changes.

#### **Example**

# **Adding a Python Transform Operator**


A Python script can be executed as a data transformation step in the data pipeline.

#### Steps:

1. On the *Application* page, click and select **Python Transform** in the *Add Operator* pane.

python\_transfor...

The **Python Transform** node icon displays in the *Graph* pane, as well as the properties to be defined in the *Operator Settings* pane, and the preview of the data in the *Schema* pane.



2. In the Operator Settings pane, define or select the following required fields:

Field	Description
Node ID	The ID of the Python Transform operator.
Inputs	The stream of records or input you will be subscribed to.
Interval	The interval of which the data should be published to the output stream (in milliseconds).
Keep Records	Check to retain or not remove flushed elements. This means the entire set of records will be flushed at each interval.
Host	Host of the Python Pyro instance.
Port	Port of the Python Pyro instance.
HMAC Key	The HMAC key that will be used to connect to the Python Pyro instance.

Data Object Name	The data structure (array of dictionaries) that Panopticon will produce, and then will be utilized by the Python Script.
Serialization Type	The serialization type: Serpent or Pickle  simple serialization library based on ast.literal_eval  faster serialization but less secure

#### NOTE

The Host, Port, HMAC Key, and Serialization Type fields will be hidden if their corresponding properties are set in the Streams.properties file.

Role	Corresponding Property in Streams.properties
Host	connector.python.host
Port	connector.python.port
HMAC Key	connector.python.password
Serialization Type	connector.python.serializertype

- 3. Enter the required *Python Script* to execute on the active Pyro instance.
- 4. Select the Use Apache Arrow check box to enable fast serialization of data frames in the Python transform.
- 5. In the *Input Schema/Sample Data* section, the column names of the <u>Input</u> data source are displayed. In cases where there are no rows from the input data source and the Python script is not handling zero rows, you can add sample data to ensure transform is applied.

To add or manage the sample data, you can use the following icons:

Button	Description
+	Add sample data for the input column names.
	Select the check box of a sample data row and click to delete, or select the topmost check box and click to delete all of the sample data rows.

- 6. In the *Generate Output Schema* section, click **Generate Output Schema** to fetch the schema of the output topic. This populates the list of columns, with the data type found from inspecting the first 'n' rows of the file.
- 7. Select the *Priority* of the node's startup:

Priority	Description
APPLICATION	Running and successful completion of the node is critical in the application startup.
HIGHEST	Highest priority but not critical.
HIGH (Default)	High priority but not critical.
STANDARD	Standard priority.

LOW	Low priority.	

8. You can also click the following icons:

Button	Description
	Fetch the schema of the output topic. This populates the list of columns, with the data type found from inspecting the first 'n' rows of the file.
+	Add a new field entry.
_	Select the check box of a field entry and click to delete.

9. <u>Save</u> the changes.

#### **Example**

```
<operators>
   <transform>
       <id>python transform1</id>
       <transformPlugin>Python</transformPlugin>
       <transformPluginSettings/>
       <interval>1000</interval>
       <columns>
           <type>STRING</type>
       </columns>
       <maxRowsCount>0</maxRowsCount>
   </transform>
   <input>
       <id>input1</id>
       <topic>input1</topic>
       <globalTopic>UntitledApplication 0.input1/globalTopic>
       <dataProducer>
           <id>StreamSimulator StocksStatic</id>
           <keyColumns>
               <field>Region</field>
           </keyColumns>
           <refreshPeriod>0</refreshPeriod>
       </dataProducer>
       <inputType>STREAM</inputType>
   </input>
   <output>
       <id>output1</id>
       <topic>output1</topic>
       <globalTopic>UntitledApplication 0.output1
       <dataConsumer>TextOutput</dataConsumer>
   </output>
</operators>
<streams>
   <stream>
       <source>python transform1
           <operator>output1</operator>
       </sink>
   </stream>
   <stream>
       <source>input1</source>
           <operator>python transform1
       </sink>
   </stream>
</streams>
```

#### Additional Best Practice Recommendations in Using Python with Panopticon

With a <u>Python transform</u> or the <u>Python connector</u> in Panopticon, it is fairly quick and easy to enter some short code snippet and use the result. However, as a project grows, and if a solution is moved into production and becomes business critical, you need more structure in your use of Python with Panopticon:

- Code should be made into functions, even if used only in one place and even if the code content is very brief. Thereby, the operations performed by each function will be contained and you avoid the risk of naming conflicts and contamination in the global environment.
- □ Ensure you handle exceptions in the code you write. For example, when applying a Python transform to data, you can do an initial check in your code to see if the dataset is either a zero-row or has any rows. In which case, you want to terminate and just return the empty dataset. You should also use try-except clauses, whereby in the event of an error, you could, for example, insert the error message into the designated column in your dataset

similar as an indicator of a no-errors result.
Functions should ideally be turned into a package. The benefit of that is mainly about the possibility of adding unit testing and automating dependency package imports.
Your package should have unit tests that are run when building the package.
Your package should import any other packages that you have a dependency on.
Developing, Testing, and Debugging the package should happen in a proper IDE, where proper debugging tools and full error messages can be monitored easily. For testing and debugging, some boiler-plate code snippets and parameter input data can be prepared, to mimic the input which could come from Panopticon parameters when the code is used via Panopticon.
In Panopticon, the code field of the transform or connector should contain an absolute mininum of code; perhaps as little as a single function call, where the function takes the necessary arguments coming from Panopticon parameters.

# **Adding a Rank Operator**

Assign a rank number to records in the same group.


Steps:



1. On the *Application* page, click and select **Rank** in the *Add Operator* pane.

rank1

The **Rank** node icon displays in the *Graph* pane, as well as the properties to be defined in the *Operator Settings* pane, and the preview of the data in the *Schema* pane.





2. In the Operator Settings pane, define or select the following required properties:

Property	Description
Node ID	The ID of the rank operator.
Inputs	The stream of records or input you will be subscribed to.
Interval	How often the collected data should be sorted, ranked, and output (in milliseconds)
Rank Field	The name of the rank number field in the output.
Rank Percentile	The name of the percentile field in the output. This is the rank number divided by the number of records in the group.
Reference	The input field to sort records on when ranking them.
Sort Order	The order to sort the records: ASCENDING (the lowest value gets rank one) or DESCENDING (the highest value gets rank one).
Cumulative Sum	The cumulative sum based on the currently applied sort order for each Reference value.  You can opt to specify a new value in the <i>Into</i> field. This column will be added in the Output schema.
Group By	The name/IDs of the fields that the data will be grouped by. Records are ranked within each group. (Proceed to step 3.)

3. In the *Group By* section, click • . A column is added in the list. Click the drop-down list to select the column that will be used to group the data.


The INPUT and OUTPUT schema are displayed.






Repeat step 3 to add more.

Two columns are added in the Output schema: <Rank Field> and the <Rank Percentile>. For example:



If you set a name for the Cumulative Sum, it will also be added in the Output schema.



You can also delete a column in the *Group By* list by selecting its check box and clicking

4. Save the changes.

#### **Example**

## Adding a Rekey Operator

Takes a stream data and changes its key. The new key can be any subset of fields from the stream.

**NOTE** 

This operator can never be applied to a table since tables require keys to be unique and therefore, you need to specify how multiple records with the same key should be aggregated.


#### Steps:



1. On the *Application* page, click and select **Rekey** in the *Add Operator* pane.

rekey1

The **Rekey** node icon displays in the *Graph* pane, as well as the properties to be defined in the *Operator Settings* pane, and the preview of the data in the *Schema* pane.



2. In the Operator Settings pane, define or select the following required properties:


Property	Description
Node ID	The ID of the rekey operator.
Inputs	The stream of records or input you will be subscribed to.
Key	The key column. Proceed to step 3.

NOTE Node ID, Inputs, and Key properties are required.

3. In the *Key* section, click <sup>+</sup> to select the new key column in the drop-down list box from the data source schema. Repeat to add more.

You can also delete a key column in the list by selecting its check box and clicking \_\_\_\_.

The preview of the data (OUTPUT) is displayed in the Schema pane.



4. <u>Save</u> the changes.

#### **Example**

# **Adding a REST Transform Operator**

Takes an input data frame, executes a REST call, and interprets the result which gets passed upstream.

Steps:




Rest

1. On the *Application* page, click <sup>+</sup> and select **Rest Transform** <sup>Transform</sup> in the *Add Operator* pane.

rest\_transform1


The **REST Transform** node icon displays in the *Graph* pane, as well as the properties to be defined in the *Operator Settings* pane, and the preview of the data in the *Schema* pane.



2. In the Operator Settings pane, define or select the following required properties:

Property	Description
Node ID	The ID of the REST Transform operator.
Inputs	The stream of records or input you will be subscribed to.
Interval	The interval of which the data should be published to the output stream (in milliseconds).
Keep Records	Check to retain or not remove flushed elements. This means the entire set of records will be flushed at each interval.

# **Property Description Authentication Type Basic** Authentication Type Basic User Id Password Enter the URL of the REST API. Then enter the User Id and the Password that will be used to the connect to the REST API. **OAuth** Authentication Type OAuth ~ Token Url Token Request Body Add Access Token To Request Headers 💙 Url Then enter the following settings: Token URL - The URL to retrieve the access token from. **Token Request Body** – The request body used for access token requests. Add Access Token To - The Access token retrieved from the Token URL can be added to headers, URL or request body, depending on how the REST endpoint needs the token. Request Headers Request Headers Request Url Request Body Request Header - A header is automatically added to the REST API request. Request URL - The URL needs to be manually parameterised with a {access token} parameter, before calling the REST API, the parameter is replaced with the actual token. Request Body - The Request Body needs to be manually parameterised with a {access token} parameter, before calling the REST API, the parameter is replaced with the actual token. URL - The URL of the REST API.



- 3. Select the Multiple Records check box to send unnamed array.
- 4. In the *Response Settings* section, click **Generate Output Schema** to fetch the schema of the output topic. This populates the list of columns, with the data type found from inspecting the first 'n' rows of the file.
- 5. Select the Response Type:
  - XML
  - JSON

If **JSON** is selected, enter the *Record Path* which allows the identification of multiple records within the JSON document.



Text

If **Text** is selected, confirm the **Column Delimiter**, **Text Qualifier**, and if the first row of the message includes column headings.



#### 6. Select the *Priority* of the node's startup:

Priority	Description
APPLICATION	Running and successful completion of the node is critical in the application startup.
HIGHEST	Highest priority but not critical.
HIGH (Default)	High priority but not critical.
STANDARD	Standard priority.
LOW	Low priority.

#### 7. Enter or select the following properties:

Property	Description
Source	The column name of the source schema.
Target	The column name of the target schema.
XPath/Json Path/Index	The column name of the target schema.
Туре	The data type of the column. Can be: BOOLEAN, DATE, DATETIME, DOUBLE, FLOAT, INT, LONG, STRING, TIME.
Date Format	Date/Time format when the data type is <b>DATE, DATETIME</b> , or <b>TIME</b> .

### 8. You can also click the following icons:

Button	Description
+	Add a new field entry.
_	Select the check box of a field entry and click to delete.

#### 9. Save the changes.

### **Adding an R Transform Operator**


An R script can be executed as a data transformation step in the data pipeline. Specifically: Data is retrieved from an underlying source. The returned data table is translated into an R data frame. The R data frame and supplied R Script are passed to an external R process running Rserve. The external Rserve process returns a resulting R data frame. The returned data frame is translated into a Panopticon table for visualization rendering. For this to occur, both R and Rserve must be installed, and initialized. Steps:



1. On the *Application* page, click and select **R Transform** R Transform in the *Add Operator* pane.



icon displays in the Graph pane, as well as the properties to be The R Transform node defined in the Operator Settings pane, and the preview of the data in the Schema pane.



2. In the Operator Settings pane, define or select the following required properties:

Property	Description
Node ID	The ID of the R Transform operator.
Inputs	The stream of records or input you will be subscribed to.
Interval	The interval of which the data should be published to the output stream (in milliseconds).
Keep Records	Check to retain or not to remove flushed elements. This means the entire set of records will be flushed at each interval.
Host	Host of the Rserve instance.
Port	Port of the Rserve instance.

User Name	The user ld if authentication is enabled on the Rserve process.
Password	The password if authentication is enabled on the Rserve process.
Frame Name	The <i>Frame Name</i> that Panopticon Streams will produce that will be utilized by the R scripts. The default is <b>df</b> .
R Script	The R script that reference the input frame name. Returns a data frame.
Timeout	The length of time to wait for the server response (10 to 300). Default is <b>10</b> .

3. On the *Input Schema/Sample Data* section, the column names of the <u>Input</u> data source are displayed. In cases where there are no rows from the input data source and the R script is not handling zero rows, you can add sample data to ensure transform is applied.

To add or manage the sample data, you can use the following icons:

Button	Description
+	Add sample data for the input column names.
_	Select the check box of a sample data row and click to delete, or select the topmost check box and click to delete all of the sample data rows.

- 4. In the *Generate Output Schema* section, click **Generate Output Schema** to fetch the schema of the output topic. This populates the list of columns, with the data type found from inspecting the first 'n' rows of the file.
- 5. Select the *Priority* of the node's startup:

Priority	Description
APPLICATION	Running and successful completion of the node is critical in the application startup.
HIGHEST	Highest priority but not critical.
HIGH (Default)	High priority but not critical.
STANDARD	Standard priority.
LOW	Low priority.

6. You can also opt to click the following icons:

Button	Description
+	<ul> <li>Add a new field entry then enter/select the following properties:</li> <li>Source – the column of the source schema.</li> <li>Target – the column name of the target schema.</li> <li>Type - The data type of the column. Can be: BOOLEAN, DATE, DATETIME, DOUBLE, FLOAT, INT, LONG, STRING, TIME.</li> </ul>
_	Select the check box of a field entry and click to delete.

7. Continue adding the necessary operators then save the changes in the application.

#### Additional Best Practice Recommendations in Using R with Panopticon

With an R transform or the Rserve connector in Panopticon, it is fairly quick and easy to enter some short code snippet and use the result. However, as a project grows, and if a solution is moved into production and becomes business critical, you need more structure in your use of R and Rserve with Panopticon:

- Code should be made into functions, even if used only in one place and even if the code content is very brief. Thereby, the operations performed by each function will be contained and you avoid the risk of naming conflicts and contamination in the global environment. Ensure you handle exceptions in the code you write. For example, when applying an R transform to data, you can do an initial check in your code to see if the dataset is either zero-row or has any rows. In which case, you want to terminate and just return the empty dataset. You should also use tryCatch clauses, whereby in the event of an error or a warning, you could, for example, insert the error/warning message into the designated column in your dataset and then return it to Panopticon. As long as there is no error, the same column could contain a plain "OK" or similar as an indicator of a no-errors result. Functions should ideally be turned into a package. The benefit of that is mainly about the possibility of adding unit testing and automating dependency package imports. Your package should have unit tests that are run when building the package. Your package should import any other packages that you have a dependency on. Developing, Testing and Debugging the package should happen in a proper IDE, where proper debugging tools and full error messages can be monitored easily. For testing and debugging, some boiler-plate code snippets and parameter input data can be prepared, to mimic the input which could come from Panopticon parameters when the code is used via Panopticon. In Panopticon, the code field of the transform or connector should contain an absolute mininum of code; perhaps as little as a single function call, where the function takes the necessary arguments coming from Panopticon parameters.
- □ With R and Rserve, it should be configured to load (import) your packages on startup, which will avoid the overhead of repeated loading of the packages upon each call.

### **Adding a Scatter Operator**

Given a record with array fields (must have the same length), the scatter operator will emit one record for each position in the array(s). This operator is similar with unpivot but on array positions instead of columns.

If the input record has an integer array field A of length N and text (non-array) field T, the operator will output N records with integer (non-array) field A and text (non-array) field T. For example, they will have values:  $\{A[0], T\}, \{A[1], T\}, ..., \{A[N-1], T\}$  (assuming zero-based indexing).

If the input has no array fields, the scatter operator is a no-op and will pass records through unchanged.


Steps:



1. On the *Application* page, click + and select **Scatter** in the *Add Operator* pane.

The **Scatter** node icon displays in the *Graph* pane, as well as the properties to be defined in the *Operator Settings* pane, and the preview of the data in the *Schema* pane.

scatter1




2. In the Operator Settings pane, define or select the following required properties:

Property	Description
Node ID	The ID of the scatter operator.
Inputs	The stream of records or input you will be subscribed to.



The preview of the data (OUTPUT) is displayed in the Schema pane.



3. <u>Save</u> the changes.

#### **Example**

## **Adding a Table to Stream Operator**

Aggregating on delta as a Table causes a change log, producing a single record. The Table to Stream operator morphs the single record back into stream.


Steps:



1. On the *Application* page, click and select **To Stream** in the *Add Operator* pane.

to\_stream1

The **To\_stream** node icon displays in the *Graph* pane, as well as the properties to be defined in the *Operator Settings* pane, and the preview of the data in the *Schema* pane.



2. In the *Operator Settings* pane, define or select the following required properties:

Property	Description
Node ID	The ID of the Table to Stream operator.
Inputs	The left input automatically connects to the currently-selected operator. You can select another ID of the operator that will be the source of the data in the <i>Inputs</i> drop-down list. Ideally, this should be an aggregation operator.
	The preview of the data (LEFT, RIGHT, and OUTPUT) is displayed in the <i>Schema</i> pane.

The preview of the data (OUTPUT) is displayed in the Schema pane.

Schema	INPUT OUTPUT
Field Name	Туре
Region	string (key, null)
Industry	string (key, null)
Mcap_USD	double (key, null)
Count	unknown
Sum_Mcap_USD	unknown

#### NOTE

The data types of the aggregated columns are still unknown. The new data type will be applied once the application is saved.

#### For example:



3. <u>Save</u> the changes.

#### **Example**

#### **Adding a Union Operator**

union1


Used to perform a union of two streams. Both streams would need the same schema. Otherwise, the output would be the combination of both, with missing values returned as Null.

#### Steps:



1. On the *Application* page, click <sup>†</sup> and select **Union** Union in the *Add Operator* pane.


The **Union** node icon displays in the *Graph* pane, as well as the properties to be defined in the *Operator Settings* pane, and the preview of the data in the *Schema* pane.



The left (inbound) edges allow you to select the input streams. The right (outbound) edge allows you to connect to the other operators.

2. In the Operator Settings pane, define or select the following required properties:

Property	Description
Node ID	The ID the union operator.
Inputs	The left input stream automatically connects to the currently-selected operator. You can select another ID of the operator that will be the source of the data in the <i>Inputs</i> drop-down list.
	Then select the right input stream.
	The preview of the data (LEFT, RIGHT and OUTPUT) is displayed in the <i>Schema</i> pane.



3. Save the changes.

## **Adding an Output Operator**


An output produces and publishes streams towards a Kafka topic or a data consumer.

#### Steps:

1. On the Application page, click and select **Output** in the Add Operator pane.

output1

The **Output** node icon displays in the *Graph* pane, as well as the properties to be defined in the *Operator Settings* pane, and the preview of the data in the *Schema* pane.



The left (inbound) edge allows you to select the input source or operator.

2. In the Operator Settings pane, define or select the following properties:

Property	Description
Node ID	The ID of the output operator.
Topic	The stream of records or output you will be subscribed to.  Select the <i>Use Node ID</i> check box to use the value entered in the <i>Output</i> ID. Otherwise, uncheck the box and enter a new <i>Topic</i> ID.  When adding Topic IDs, ensure they: must be unique across an application must be specified must start with a letter (a to Z) or an underscore. Also, it can only contain letters (a to Z), numbers (0 to 9), and underscores
Partition Count	Enter the number of partitions for the Kafka topics that will be created for the Output operator.  Partitions allow you to parallelize a topic by splitting the data in a particular topic across multiple brokers wherein, each partition can be

	placed on a separate machine to allow for multiple consumers to read from a topic in parallel.
Inputs	The left input stream automatically connects to the currently-selected operator. You can select another ID of the operator that will be the source of the data in the <i>Input</i> s drop-down list.  The preview of the data (INPUT) is displayed in the <i>Schema</i> pane.
Data Consumer	Select the Data Consumer where the output will be produced or published.  Currently, the following data consumers are supported:  Text  JDBC Legacy  InfluxDB 1.x  Email  Kx kdb+  REST  Apache Kafka

3. Save the changes.

# **ADDING APPLICATION-SPECIFIC PROPERTIES**

Panopticon Streams properties can be viewed and configured in <u>Streams.properties</u>. However, some of these server-wide properties can be overridden by adding and customizing them in an application.

#### Steps:

1. On the *Application* page, click then select **Properties**.

The Application Properties dialog displays.



**NOTE** 

- Currently, the application properties are used to assign specific retention time (in milliseconds) for topic(s).
- Partition Count values that were added in operators in the application are displayed.
- 2. To add a property, click



A new row for Key and Value entry displays.

NOTE

The Keys and Values must not be empty. Also, keys must be unique within the application property list.

- 3. Enter the Key. This is the application property to be configured.
- 4. Enter the corresponding Value of the key.

You can also opt to delete an application property entry by selecting its check box and clicking



5. Click Close

#### **Example**

```
properties>
   <!-- Keep tables alive one day -->
    <entry>
       <key>table.retention.ms</key>
       <value>86400000
   </entry>
   <!-- Keep input and output streams for 1 second -->
       <key>input.retention.ms</key>
       <value>1000</value>
   </entry>
    <entry>
       <key>output.retention.ms</key>
       <value>1000</value>
   </entry>
   <!-- Custom retention time for InputStream topic -->
   <entry>
       <key>TimeSeries.retention.ms</key>
       <value>1111</value>
   </entry>
</properties>
```

Refer to **RetentionTimeExample** in the **Example Applications** section for more information.

# SAVING AN APPLICATION

Saved applications (.app) are available in the PanopticonAppdata\CEP\Applications folder (i.e., c:\streamsserverdata\CEP\Applications).

#### Steps:

- 1. On the Application page, you can either click:
  - the Save
  - icon. The context menu displays with three saving options:
    - Save

Click to save the changes made in the application.

Save as Copy

Click to make a duplicate of the application. The original name is appended with **\_Copy**.

To change the *Application Name*, click on it to make it editable, then enter a new one and click ...




#### **NOTE**

The Name or ID must start with a letter (a to Z) or underscore. Also, it can only contain letters (a to Z), numbers (0 to 9), and underscores.

Revert to Saved

Click to revert to the previously-saved application settings.



# **EDITING AN APPLICATION**

**NOTE** 

Applications that are started or running cannot be edited.

#### Steps:

1. On the Applications tab, click an application link to modify.

The Application page displays.

2. To change the *Application Name*, click on it to make it editable, then enter a new one and click ...



NOTE

The Name or ID must start with a letter (a to Z) or underscore. Also, it can only contain letters (a to Z), numbers (0 to 9), and underscores.

- 3. You can also modify or add the following:
  - operators
  - properties
- Save the changes.


To go back to the **Applications** tab, click beside the application name.

**NOTE** 

If there are changes that were not saved, a confirmation message displays asking if you will exit the Application page without saving. Click Cancel and then save.


# **VALIDATING AND FIXING APPLICATION ISSUES**

Panopticon Streams provides an error validation to help fix application issues.



#### Steps:

1. Click **Show Issues** . The list of *Issues* is displayed with the *Source* or operator with an error.




2. Click an issue to select.

Some possible issues include the following:


- for the input nodes, the data source is not available
- the application model parts are still not complete, or has invalid values
- for all nodes except inputs, there are faulty input definition or missing input connection
- for all nodes except outputs, there are faulty output definition or missing output connection
- 3. Apply the necessary changes and save.

# STARTING AN APPLICATION



You can start an application either on the Applications tab or on the Application page.


# Starting an Application on the Applications Tab




#### Steps:

1. To execute an application, ensure the sources are already uploaded.

However, if is displayed, right-click on the application and select **Data Source Usage** in the context menu.



The list of data sources used by the application is displayed. For example:




Refer to <u>Uploading Data Sources</u> or <u>Creating a Data Source</u> for more information.

2. Click . The icon changes to and the timestamp is displayed under the *Status Updated* column.

The stream topics and the data producer are also generated.


### **Starting an Application on the Application Page**

Users with a Designer role have the ability to open and manage applications.



#### Steps:

1. On the **Applications** tab, click an application link to open and display it on the *Application* page.




2. Click to run the application.




The stream topics and the data producer are generated.


- 3. You can also perform the following:
  - click on a node in the Graph pane to display its Operator Settings as well as the preview of the data (OUTPUT) in the Schema pane



 click the Metrics tab to display the node's Metrics as well as the preview of the data (OUTPUT) in the Schema pane



• select an input or output node and click the **Data Preview** tab to display the data preview.



You can also click:

- to copy the data to a clipboard.
- to pause the update. To start the update, click .


# STOPPING AN APPLICATION


Stopping the execution of an application can either be done on the **Applications** tab or the **Application** page.

### **Stopping an Application on the Applications Tab**



### **Stopping an Application on the Application Page**





# [9] MANAGING DATA SOURCES




Figure 9-1. Data Sources page for the Administrator user role

On the Data Sources page, users with Administrator or Designer role can:

- rename data sources
- View application usages
- move or copy data sources to folders or subfolders to which the user has permission
- download a copy
- □ <u>remove</u> a data source

To <u>create</u> or <u>upload</u> a data source, a user must have a Designer role.





Figure 9-2. Data Sources page for the Designer user role

### **UPLOADING DATA SOURCES**


Users with a Designer role can upload data sources to folder or subfolders to which they have permission.

#### Steps:

- 1. To upload data sources, you can either right-click a folder or subfolder then select **Upload Data Sources**:
  - on the expanded Folder hierarchy list



or on the Data Sources pane




The Upload Data Source dialog displays.



- 2. To upload a data source, you can either:
  - drag it from your desktop and drop in the dialog, or
  - click **Choose Data Source** and select one in the *Open* dialog that displays.


The name of the data source is displayed on the uploaded data source area and in the *Name* box.




- 3. You can opt to rename the data source.
- 4. To replace an existing data source, select the Replace existing data source check box.



You will be notified when the data source has been uploaded.




The data source is added and displayed on the **Data Sources** tab.



### **Folders and Data Sources Display View**


Folders and data sources can be displayed either on a *List* or *Grid View*. By default, the folders and data sources are displayed in the *List View*.



On the toolbar, click **Grid View** 

. The folders and data sources are displayed as thumbnails.


NOTE Data Sources are placed under their corresponding plugin.



Click **List View** to return to the standard listing.

On either display view style:

- Clicking on a data source title or thumbnail displays the data source
- □ Right-clicking on a data source displays the context menu



# **SORTING THE LIST OF DATA SOURCES**


Sorting data sources can be done by Name, Last Modified, or Plugin.

Sort By	Default Sort Order	
Name	Ascending	
Last Modifed	Descending	
Plugin	Ascending	

#### Steps:

On the Folders and Data Sources Summary layout, either:

click the **Sort By** option on the *Toolbar* of the *Grid View* By default, the sorting is by **Name**.




- Name
- Last Modified
- Plugin

Then click the Sort Order.



□ click on the Name, Last Modified, or Plugin column header of the List View




Then click the Sort Order.

- Ascending
- Descending


### **SEARCHING FOR DATA SOURCES**

To search for a particular data source, enter it in the Search Data Source box.



Searching data sources in the Grid View

You can also enter one of more characters into the Search Data Source box and the suggested list of data sources that matched the entries will be displayed.




# **RENAMING DATA SOURCES OR FOLDERS**

A user with an Administrator or Designer role can rename data sources and folders.


#### Steps:

1. Right-click on a data source or folder then select **Rename** in the context menu.



Folder or Subfolder Context Menu

The Rename Data Source or Rename Folder dialog displays.




2. Enter a new name then click


# **VIEWING APPLICATION USAGES**

On the **Data Sources** tab, you can view the applications that currently use a data source.


#### Steps:

1. On the *List* view or *Grid* view, right-click on a data source and select **Application Usage**.





The list of applications that currently use the data source displays.



MOVING DATA SOURCES


Users with a Designer role can move data sources to folders or subfolders to which they have permission.

#### Steps:


Click

- 1. Select the check box of multiple data sources either on the *Grid View* or the *List View*.
- 2. Then select either:
  - the **Move** icon on the toolbar
  - Move in the context menu

The Move Data Source dialog displays with the folder or subfolders to which the user has permission to move the data sources.




3. Select the folder or subfolder.



4. Click Move

The data sources are moved and displayed on the selected folder.



NOTE

If data sources with the same name are already in the selected folder, a copy of them will be moved.

### **COPYING DATA SOURCES**


Users with a Designer role can copy data sources to folders or subfolders to which they have permission.

#### Steps:


- 1. Select the check box of one or multiple data sources either on the Grid View or List View.
- 2. Then select either:

- the **Copy** icon on the toolbar
- Copy in the context menu

The Copy Data Source dialog displays with the folder or subfolders to which the user has permission to copy the data sources.




3. Select the folder or subfolder.



4. Click Copy

The data sources are copied and displayed on the selected folder.




**NOTE** 

If data sources with the same name are already in the selected folder, it will be added as copy.

### **DOWNLOADING A DATA SOURCE**

Users with Administrator or Designer role are allowed to download a copy of a data source by right-clicking on a data source and selecting **Download** in the context menu.



The data source is downloaded.

# **DELETING DATA SOURCES**

Users with an Administrator or Designer role can delete data sources using the toolbar or context menu.

#### Steps:


1. Select the check box of one or several data sources either on the Grid View or List View.

#### 2. Then click either:


- the **Remove** icon on the toolbar
- Remove in the context menu

A notification message displays.

For a data source, the corresponding applications that will be impacted is listed:



#### For several data sources:



3. Click Yes to remove.

### **CREATING A DATA SOURCE**


Panopticon Streams supports the creation of data sources that can be used as inputs or outputs in the application model.

#### Steps:


1. On the Data Sources tab:



right-click on a folder or subfolder and select New Data Source.




The New Data Source dialog displays.




2. Enter the Name of the data source and click



The **Data Source** tab displays with the following sections:





Section/Pane	Description
Data Source Name	Name of the data source. Click the button to go back to the <i>Data</i> Sources listing page.
Connector drop-down list	Includes the input data sources and output connectors.
Save	Saves the changes made on the <b>Data Sources</b> tab.



- 3. Enter the *Name* of the data source. This should be unique and should only contain letters (a to Z), numbers (0 to 9), and underscores.
- 4. Click or press **Enter** to apply the name.
- 5. Select any of the following:
  - Output connectors
    - ♦ Email
    - ♦ InfluxDB 1.x

- JDBC Legacy
- Apache Kafka
- Kx kdb+
- ♦ MQTT
- ♦ REST
- ♦ Text
- Input data sources
  - ActiveMQ
  - Altair Al Hub
  - Azure
  - Cassandra
  - ♦ <u>DolphinDB</u>
  - DolphinDB Streaming
  - Google Analytics
  - Google Cloud
  - Google Cloud Pub/Sub
  - InfluxDB 1.x
  - JDBC Legacy
  - ♦ JDBC
  - ♦ JSON
  - Apache Kafka
  - Kx kdb+
  - Kx kdb+ Tick
  - ksqlDB
  - ksqlDB Streaming
  - MongoDB
  - MQTT
  - MQTT Publisher
  - MS Excel
  - OneTick
  - OneTick CEP
  - Python
  - RabbitMQ
  - Rserve
  - <u>S3</u>

- Solace
- Stream Simulator
- ♦ StreamBase 7.1
- StreamBase LiveView
- Text
- WebSocket
- Web Data
- XML

The tab page changes depending on the selected connector. Refer to the sections below for more information.

#### **Common Data Source Settings**

Some of the data sources share the following settings or parts:


- Data Connector File Source
- Message Type selection and definition
- Saving and loading of column definitions
- Data Souce Toolbar
- Defining Real-time Settings

#### **Selecting and Defining the Data Connector File Source**

Several connectors including <u>JSON</u>, <u>Text</u>, <u>XML</u>, and <u>Stream Simulator</u>, allow selection from a File, Web URL, or Text source.

#### Steps:

Select the connector file source:




File

You can either:


Upload a data source snapshot by clicking Upload File browse to the file source.

Upload File then Browse

After selecting the file, it is displayed with the timestamp of the snapshot.





Ensure that in a cluster, you need to use a a shared path, or put it on every node and use a path that resolves on every node. You can update its contents whenever you want.



Text

Then enter the text block to be parsed.







#### □ Web URL

The dialog changes to allow specification of the following:

JSON File Source	Web URL	<u>*</u>	
Authentication Type	Basic	<u>*</u>	
Path			
Proxy Server URI			
Headers			
Content Encoding	None	▼	
User Id			
Password		Show characters	
Http Method	GET	▼	
Timeout	10	▼	
Request Body			
Content Type	application/x-www-fo	orm-urlencoded	
Record Path			(eg. myroot.items.item)
Decimal Separator	Period {.}	<b>▼</b>	
File Encoding			



	<ul> <li>Each Header is entered as Name = Value, where Name and Value can be enclosed in double quotes to allow inclusion of any character except for double quotes</li> <li>Name and Value can also be left unquoted, in which case they may not include comma or equals characters</li> </ul>
Content Encoding	Select the <i>Content Encoding</i> with the HTTP Header: <b>None, GZip, Deflate,</b> or <b>GZip and Deflate</b>
User Id	The user ld that will be used to connect to the connector's service.
Password	The password to connect to the connector's service.  Select the <b>Show Characters</b> check box to display the entered characters.
HTTP Method	Select the appropriate HTTP method for the request from the following options:  GET – retrieve data  POST – add new data  PUT – replace existing data  DELETE – remove existing data
Timeout	The length of time to wait for the server response (10 to 300). Default is <b>10</b> .
Request Body	The Request Body for the HTTP POST.
Content Type	The required Content Type. Default is application/x-www-form-urlencoded
Record Path	The record path that will be queried by the connector's path (e.g., myroot.items.item).
File Encoding	Set the character encoding to use in text data.  UTF-8  UTF-16  UTF-32  US-ASCII  Windows-1252




#### **Defining the Message Type in Data Sources**

You can select the message type that specifies the format of the data within the message in <a href="ActiveMQ"><u>ActiveMQ</u></a>, <a href="Google Cloud">Google Cloud</a></a> <a href="PubSub">PubSub</a>, <a href="Mathematical-NativeMQ">MQTT</a>, <a href="RabbitMQ">RabbitMQ</a>, <a href="Solace">Solace</a>, and <a href="WebSocket">WebSocket</a> connectors.


#### Steps:

1. Select the Message Type:




JSON

If **JSON** is selected, enter the *Record Path* which allows the identification of multiple records within the JSON document (e.g., **myroot.items.item**) and select the *Array Handling* setting.



Text

If **Text** has been selected, confirm the **Decimal Separator**, **Text Qualifier**, **Column Delimiter**, and if the first row of the message includes column headings.



2. Define or set the columns that represent the sections of the message.

Property	Description	
Name	The column name of the source schema.	
Fix Tag/JsonPath/Column Index/XPath	The Fix Tag/JsonPath/Column Index/XPath of the source schema.	
Туре	The data type of the column. Can be a <b>Text, Numeric</b> , or <b>Time</b>	
Date Format	The <u>format</u> when the data type is <b>Time</b> .	
Enabled	Determines whether the message field should be processed.	


NOTE	To parse and format times with higher than millisecond precision, the format string needs to end with a period followed by sequence of upper case S. There can be no additional characters following them.  For example: yyyy-MM-dd HH:mm:ss.SSSSSS
o delete a co	lumn, check its or all the column entries, check the topmost , then click .

#### **Defining the Format in Data Sources**

You can select the format to use in the connector for Azure, Google Cloud, S3, and Web Data data sources.


#### Steps:

1. Select the Data Type:




JSON

If **JSON** is selected, click to fetch the *Record Paths* then select one. This allows the identification of multiple records within the JSON document. Then select the *Array Handling* setting.




Text

If **Text** is selected, confirm the **Decimal Separator**, **Text Qualifier**, **Column Delimiter**, and if the first row of the message includes column headings.




• Allow IPC



2. Define or set the columns that represent the sections of the file.

3. Property	Description
Name	The column name of the source schema.
JsonPath/Column Index/XPath	The JsonPath/Column Index/XPath of the source schema.
Туре	The data type of the column. Can be a <b>Text, Numeric</b> , or <b>Time</b>
Date Format	The format when the data type is <b>Time</b> .
Enabled	Determines whether the message field should be processed.




### Saving or Loading Column Definitions in the Data Sources

Save or load column definitions in the data sources.


## Steps:

- 1. Click Save to save a copy of a column definitions file (.exs).
- 2. Instead of generating columns done in step 8, click Load to load a column definitions (.exs) file.

The Load Column Definitions dialog displays.




- 2.1. To load column definitions, you can either:
  - drag it from your desktop and drop in the dialog, or
  - click **Choose Column Definitions File to Load** and select one in the *Open* dialog that displays.



2.2. Click Ok


A notification displays when the file is loaded.



This populates the list of columns from the .exs file.

## **Defining Real-time Settings**

Streaming connectors have a common section to specify the *Time Id Column* to generate the streaming time series window. The *Time Id Column* can be from the soure dataset, or alternatively, automatically generated.



As new data arrives from the subscription, new time slices will automatically be added, and old ones will be deleted.

#### Steps:

- 1. Select either:
  - Automatic Time Id



Then define the Time Id Column Name.


Date/Time Id column either from the source data or automatically generated




2. Select the Reset Data on Reconnect check box to flush out the stale data and reload data after reconnection.


### **Using the Data Source Toolbar**

Several data sources have a toolbar:



Click on any of the following icons:





# **Date/Time Key Elements**

The key elements of the Date/Time format include:

Component	Format
Year	уууу
Month	MM
Month as an abbreviation	MMM
Day	dd
Hour (24-hour clock)	НН
Minute	mm
Second	ss
Hour (12-hour clock; a.m./p.m.)	tt
Millisecond	SSS
Microsecond	SSSSSS
Nanosecond	SSSSSSSS
Space/separator (required if time is specified)	'T'
Zulu (Greenwich Mean Time)	'Z'
Time zone (ISO 8601 time zone)	Х
UNIX Epoch time	POSIX
Milliseconds since UNIX Epoch time	POSIXMILLIS
Seconds since midnight	Seconds
Milliseconds since midnight	Millis
Microseconds since midnight	Micros
Nanoseconds since midnight	Nanos

## NOTE

 To parse and format times with higher than millisecond precision, the format string needs to end with a period followed by sequence of upper case S. There can be no additional characters following them.


For example: yyyy-MM-dd HH:mm:ss.SSSSSS

• The "Seconds", "Millis", "Micros", and "Nanos" formats are used for parsing of the data in the data connectors and not for the display of the Date/Time columns.

# **Creating Email Output Connector**

## Steps:

1. On the **Data Source** tab, select **Output > Email** in the *Connector* drop-down list.



2. Define or select the following properties:

Property	Description
Host	Email host address.
Port	Email host port.
Mail Security Mode	Select the email security mode: NONE, SSL, or TLS
Sender Email Address	Email address of the sender.
Sender Password	Password of the sender.

To Email Address	Email address of the recipient.
CC Email Address	Email address of the CC recipient.
BCC Email Address	Email address of the BCC recipient.
Subject	Subject of the email.
Text	Content of the email.

3. Click Save


. The new data source is added in the Data Sources list.

# **Creating InfluxDB 1.x Output Connector**

Allows periodical dumping of data from a Kafka topic into a time series database such as InfluxDB 1.x.

### Steps:

1. On the **Data Source** tab, select **Output > InfluxDB 1.x** in the *Connector* drop-down list.



2. Define or select the following properties:

Property	Description
URL	URL of InfluxDB 1.x.
Port	The port running the InfluxDB 1.x HTTP service. Default is 8086.
Database	The name of the database that will be communicate over the HTTP(S).
User Id	The user ld that will be used to connect to InfluxDB 1.x.
Password	The password that will be used to connect to InfluxDB 1.x.
Measurement	The table name that can be used as measurement.


- 3. You may opt to use the toolbar to complete the data source definition.
- 4. Click . The new data source is added to the *Data Sources* list.

## **Creating JDBC Legacy Output Connector**

Allows periodical dumping of records from a Kafka topic into a JDBC database.


#### Steps:

1. On the **Data Source** tab, select **Output > JDBC Legacy** in the *Connector* drop-down list.



- 2. You can either select:
  - JNDI Name

Enter the JNDI resource name to be used.



URL

Enter the *URL* specific to the database's JDBC driver, the *Driver Class Name* specific to the driver, and the *User Id* and *Password*.

3. Select the appropriate *SQL Dialect* in the drop-down list to be able to generate the correct *SQL* for the required data repository.

You can select any of the following *SQL dialects*: AnsiSQL, MySQL, Oracle, SQL Server, SAP IQ, SAP ASE, Netezza, Vertica, SQLite, HadoopHive, DB2, PostgreSQL, Impala, Redshift, Informix, Teradata, dBase, SparkSQL.


- 4. Enter the source *Table* (can be parameterized).
- 5. You may opt to use the toolbar to complete the data source definition.
- 6. Click . The new data source is added to the *Data Sources* list.

## **Creating Apache Kafka Output Connector**

Allows publishing of events to an external Kafka JSON or Avro topic. For Avro, ensure to point towards the schema registry used by the external Kafka cluster.

#### Steps:

1. On the Data Source tab, select Output > Kafka in the Connector drop-down list.



2. Enter or select the following properties:

Property	Description
Bootstrap Server	List of host/port pairs of Kafka servers used to bootstrap connections to a Kafka cluster.
	By default, the value is localhost: 9092. However, this can be overridden by specifying another bootstrap server in the <i>External Settings</i> text box (as specified in step 3).
Schema Registry Host	Where the Schema Registry is located. This can be in a different location from the Kafka cluster.
Schema Registry Port	The port number of the schema registry which provides the serving layer for the metadata. Default is <b>8081</b> .

3. Enter the *External Settings* to support authentication (i.e., username and password). Note that if the bootstrap server is not secure, then there is no need to authenticate and you may leave this text box blank.

Below is an example of system settings for an SASL authentication:

```
bootstrap.servers=localhost:9093
sasl.jaas.config=\
  org.apache.kafka.common.security.plain.PlainLoginModule required \
```


- 4. Enter the *Topic* name.
- 5. Select the Message Composer: Avro or JSON.
- 6. You may opt to use the toolbar to complete the data source definition.
- 7. Click . The new data source is added in the *Data Sources* list.

# **Creating Kx kdb+ Output Connector**

Allows periodical dumping of records from a Kafka topic into a Kx kdb+ connector.

#### Steps:

1. On the Data Source tab, select Output > Kdb+ in the Connector drop-down list.



2. Define or select the following properties:

Property	Description
Host	Kx kdb+ host address.
Port	Kx kdb+ host port. Default is <b>5001</b> .
TLS Enabled	Ensure to check if you have started q with TLS only.
User Id	The user ld that will be used to connect to Kx kdb+.
Password	The password that will be used to connect to Kx kdb+.
Table	The source table.

NOTE These properties can be parameterized.


- 3. You may opt to <u>use the toolbar</u> to complete the data source definition.
- 4. Click Save . The new data source is added in the Data Sources list.

# **Creating a MQTT Output Connector**

Allows publishing of data to external MQTT topic.

## Steps:

1. On the **Data Source** tab, select **Output > MQTT** in the *Connector* drop-down list.




2. Define the following properties:

Property	Description
Broker URL	The location of the message broker. Default is tcp://localhost:1883
Topic	The topic or the queue physical name. Can be parameterized.  Example: level1/level2/level3/level4 etc.
	NOTES:  You can also opt to use a wild card in the topic name specification.
	The plus sign symbol (+) can be used as a wild card for any value at one specific level.

	<ul> <li>Example: level1/level2/+/level4</li> <li>The hash sign symbol (#) can be used as a wild card for any values across more than one level.</li> <li>Example: level1/#/level4</li> </ul>
User Id	The user Id that will be used to connect to MQTT.
Password	The password that will be used to connect to MQTT.
Payload Template	The template that will be rendered to generate the payload.  Can be parameterized with output schema columns.

3. To allow encrypted connections, you can either:



- 4. You may opt to use the toolbar to complete the data source definition.
- 5. Click Save . The new data source is added in the Data Sources list.

# **Creating a REST Output Connector**


Outputs an event to a REST API. This output connector can also be used as an alerting system.

#### Steps:

1. On the **Data Source** tab, select **Output > Rest** in the *Connector* drop-down list.


## ← RestDataSource





2. Define or select the following properties:





	<ul> <li>PUT – replace existing data</li> <li>DELETE – remove existing data</li> </ul>	
Content Type	The required Content Type. Default is application/x-www-form-urlencoded	
Timeout	The length of time to wait for the server response (10 to 300). Default is <b>10</b> .	
Request Body	The Request Body for the HTTP POST.	




. The new data source is added in the Data Sources list.

# **Creating Text Output Connector**

Allows retrieval and processing of delimited Text files (such as CSV, TSV, etc.). The files produced can be consumed by the Text connector.

## Steps:

1 On the **Data Source** tab, select **Output > Text** in the *Connector* drop-down list.



2 Define or select the following properties:

Property	Description
Folder Path	The path where the Text output will be placed.
File Name Prefix	The prefix for the file name.  This can be parameterized with field names. Consequently, each event can generate a new file in the given folder.
	For example, if the Text output connector is attached as the consumer to StockStatic, you can use "{Region}" inside the <i>File Name Prefix</i> , causing it to create three files for Asia Pacific, Europe, and North America.
	Note that partitioning file names with current date in "yyyyMMdd" format is still done automatically and can't be controlled, at the moment. For the StockStatic example, if it was executed today, it would have created three files like Asia Pacific_20181219.tsv.
File Name Extension	File name extension of the text output. Possible values are .tsv and .csv.
Timestamp Column	The name of the new column that will include the timestamp. Default is <b>Timestamp</b> .

3. Select the Column Delimiter from the drop-down list to be used when parsing the text file.



- 4. You may opt to use the toolbar to complete the data source definition.
- 5. Click . The new data source is added in the *Data Sources* list.

# **Creating ActiveMQ Input Data Source**

Allows connection to Apache's ActiveMQ message bus on a real-time streaming basis. Specifically, the connector allows Panopticon Streams to subscribe to XML, JSON or FIX based messages that are published on topics. The data format itself is arbitrary, and consequently, the connection includes the message definition.

### Steps:

1. In the New Data Source page, select Input > ActiveMQ in the Connector drop-down list.

## ← ActiveMQInput ☐ Save Connector ActiveMQ Broker tcp://localhost:61616 User Id Password topic://topicname.\* Topic Use durable subscription Messages can contain partial data Message Type Decimal Separator Period {.} Prepend 'default:' for the elements falling under default namespace. Generate Columns Save Load Enabled + Name **XPath Date Format** Type Real-Time Settings Time Id Column [No Time Id] Time Id Column Name Reset Data on Reconnect

2. Enter the following information:

Property	Description
Broker	The location of the message broker. Default is tcp://localhost:61616.
User Id	The user Id that will be used to connect to the ActiveMQ service.
Password	The password to connect to the ActiveMQ service.
Topic	Accepts topic in topic://topicname.* format and also topicname.*. Therefore, topic://pano.> and pano.> both will work as topic value.  Default is topic://topicname.*

3. Select/unselect the Use durable subscription check box.

NOTE

When connecting to a message bus, it is recommended to disable durable messaging. When it is enabled, this puts a heavier load to the server, and slows down the start and stop of subscriptions.

- 4. Select/unselect **Messages can contain partial data** check box.
- 5. Select the Message Type.

6. Select either the period (.) or comma (,) as the Decimal Separator.

NOTE Prepend 'default:' for the elements falling under default namespace.

- 7. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the **Save** button is enabled.
- 8. You can also opt to load or save a copy of the column definition.
- 9. You can also opt to click to add columns to the MQ connection that represent sections of the message. Then enter or select:

Property	Description
Name	The column name of the source schema.
Fix Tag/JsonPath/Text Column Index/XPath	The Fix Tag/JsonPath/Text Column Index/XPath of the source schema.
Туре	The data type of the column. Can be a <b>Text</b> , <b>Numeric</b> , or <b>Time</b>
Date Format	The format when the data type is <b>Time</b> .
Filter	Defined parameters that can be used as filter.
Enabled	Determines whether the message field should be processed.

NOTE

To parse and format times with higher than millisecond precision, the format string needs to end with a period followed by sequence of upper case S. There can be no additional characters following them.

For example: yyyy-MM-dd HH:mm:ss.SSSSS


If Message Type is set to Fix, the Add Column will display as:



If Message Type is set to **JSON**, the Add Column will display as:



If Message Type is set to Text, the Add column will display as:




## **Creating Altair Al Hub Input Data Source**

The Altair Al Hub allows you to request data from endpoints created in Altair Al Hub.

#### Steps:


- 1. In the New Data Source page, select Input > Altair Al Hub in the Connector drop-down list.
- 2. Enter or select the following properties:



	<ul> <li>be added to each specific Endpoint in Altair Al Hub, in the Deployment settings of the Endpoint.</li> <li>API Token</li> <li>Can be used with Endpoints that have Consumer Permissions = "Long-living API token", and an API token is entered. API tokens can be created in Altair Al Hub, in the Deployment settings of the Endpoint.</li> </ul>
Input Data	By default, this setting has a JSON object entered, with a single name "data" and a value which is a JSON array containing an empty JSON object. The array can contain some number of JSON objects, each being a single name-value pair of column names and column values. The required structure is further exemplified in the Test section of each Endpoint in Altair Al Hub.
Timeout	This is the time in seconds that will be allowed before Panopticon aborts the request. Possible values are one of a fixed set of seconds from 10 to 300.

- 3. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the **Save** button is enabled.
- 4. You can also opt to load or save a copy of the column definition.
- 5. Click to add columns to the Altair Al Hub connection that represent sections of the message. Then enter or select:

Property	Description
Name	The column name of the source schema.
JsonPath	The JsonPath of the source schema.
Туре	The data type of the column. Can be a <b>Text</b> , <b>Numeric</b> , or <b>Time</b>
Date Format	The <u>format</u> when the data type is <b>Time</b> .
Enabled	Determines whether the message field should be processed.



## **Creating Azure Input Data Source**

Azure connector allows for retrieval of the file from an Azure blob storage. This connector allows JSON/XML/Text/Excel files to be read from the Azure blob storage.

#### Steps:

1. In the New Data Source page, select Input > Azure in the Connector drop-down list.

2. Enter the following information:

Property	Description
Container	Azure container where the file resides.
Account Name	Azure storage account name.
Account Key	Azure storage account key.  To test the connection, click  Test Connection
	If Connection Failed displays, ensure the Container, Account Name, and Account Key values are correct. You can also hover on this message to view the connection error.

- 3. Click the Browse tab. The available Azure blob files in the container you specified are displayed.
- 4. Select the Azure blob file. The file name is displayed in the *File Path* field and the <u>Data Type</u> is updated with its related fields.
- 5. Select the Only Show Know File Types checkbox to narrow down the list based on the selected data type.
- 6. Select either the period (.) or comma (,) as the Decimal Separator.




- 7. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the **Save** button is enabled.
- 8. You can also opt to <u>load or save</u> a copy of the column definition.

NOTE This option is not available for the Excel data type.

9. You can also opt to click to add columns to the Azure connection that represent sections of the message. Then enter or select:

Property	Description
Name	The column name of the source schema.
JsonPath/Column Index/XPath	The JsonPath/Column Index/XPath of the source schema.
Туре	The data type of the column. Can be a <b>Text, Numeric,</b> or <b>Time</b>
Date Format	The format when the data type is <b>Time</b> .
Enabled	Determines whether the message field should be processed.




## **Creating AMPS Input Data Source**

The AMPS connector allows connection to AMPS message bus on a real-time streaming basis. The connector allows Panopticon Streams to subscribe to the Native FIX and XML message support. The data format itself is arbitrary, and in turn the connection includes the message definition.

#### Steps:

1. In the New Data Source page, select Input > AMPS in the Connector drop-down list.



### 2. Enter the following information:

Property	Description
Host	AMPS host address.
Port	AMPS host port. Default is 9004.
User Id	The user Id that will be used to connect to the AMPS service.
Password	The password to connect to the AMPS service.
Topic	The topic or queue physical name.
Filter	The filter expression.

- 3. Select the *Protocol*. This will specify the format of the headers: Amps (default) Fix

  - NvFix
  - XML
- 4. Select the <u>Message Type</u>. This will specify the format of the data within the message:
- 5. Select from any of the following Subscription Modes:
  - Sow
  - SowAndSubscribe
  - SowAndDeltaSubscribe (default)
  - Subscribe
  - DeltaSubcribe
- 6. Enter the Order By Statement in order to limit the returned data. For example:

/orderDate DESC

/custumerName ASC

- 7. Enter any of the following Option/s for the selected Subscription Mode:
  - cancel
  - live
  - no\_empties
  - null
  - no\_sowkey
  - oof
  - pause
  - replace
  - resume
  - send\_keys
  - timestamp

NOTE

Leave the Options box blank if you selected the Subscribe subscription mode.

- 8. Enter the Batch Size. This is the number of messages that will be sent at a time as results are returned. Default is 100.
- 9. Enter the *Timeout* for the length of time to wait for the Server response. Default is **5000**.

10. Select either the period (.) or comma (,) as the Decimal Separator.

NOTE Prepend 'default:' for the elements falling under default namespace.

- 11. Click to the fetch the schema based on the connection details. This populates the list of columns with the data type found from inspecting the first 'n' rows of the input data source.
- 12. You can also opt to click . This adds columns to the AMPS connection that will represent sections of the message.
- 13. Provide the following information:

Property	Description
Name	The column name of the source schema.
Fix Tag/XPath/Json Path	The Fix Tag/XPath/Json Path of the source schema.
Туре	The data type of the column. Can be a <b>Text, Numeric,</b> or <b>Time</b>
Date Format	The format when the data type is <b>Time.</b>
Filter	Defined parameters that can be used as filter. Only available for Fix, JSON, and XML message types.
Enabled	Determines whether the message field should be processed.

To delete a column, check its  $\Box$  or all the column entries, check the topmost  $\Box$  , then click  $\overline{\phantom{a}}$  .

14. Define the Real-time Settings.



## **Creating Cassandra Input Data Source**

The Apache Cassandra connector allows connection to Apache and Datastax Cassandra instances, by executing a pre-defined CQL query, and retrieving the resulting data.

#### Steps:

1. On the New Data Source page, select Cassandra in the Connector drop-down list.

## ← CassandraInput



Connector	Cassandra	~	
Host	localhost		
Port	9042		
KeySpace			
User Id			
Password			
Enclose parameters in quot	es 🗌		
CQL Query			

### 2. Enter the following information:

Property	Description
Host	Apache Cassandra host address.
Port	Apache Cassandra host port. Default is 9042.
KeySpace	Namespace that defines data replication in nodes.
User Id	The username used to connect to the Apache Cassandra service.
Password	The password used to connect to the Apache Cassandra service.


- 3. Select whether the parameters should be automatically enclosed in quotes, by selecting the **Enclose** parameters in quotes check box.
- 4. Enter the CQL Query, which can contain parameters in a similar manner to the database connector.
- 5. The time zone of input parameters and output data is by default, unchanged. Changing the time zone is supported by using the *Show in Timezone* drop-down list box based on the assumption that data are stored in UTC time and outputs are presented in the selected time zone.
- 6. Click . The new data source is added in the *Data Sources* pane.

## **Creating DolphinDB Input Data Source**

The DolphinDB connector allows you to connect and query tables using DolphinDB java API.

### Steps:

1. On the New Data Source page, select DolphinDB in the Connector drop-down list.



2. Enter the following information:

Property	Description
Host	DolphinDB host address.
Port	DolphinDB host port. Default is 8848.
User Id	The username used to connect to the DolphinDB service.
Password	The password used to connect to the DolphinDB service.  Check the <i>Show Characters</i> box to display the entered password characters.

- 3. Enter the Query, which can contain parameters in a similar manner to the database connector.
- 4. Click Save

  The new data source is added in the Data Sources pane.

## Creating DolphinDB - Streaming Input Data Source

The DolphinDB streaming connector allows you to connect and subscribe streaming data using DolphinDB Java Streaming API.

### Steps:

1. On the New Data Source page, select DolphinDB - Streaming Beta in the Connector drop-down list.

## ← DolphinDBStreamingInput



Connector	DolphinDB - Streaming Beta	
Host	localhost	
Port	8848	
User Id		
Password		Show characters
Table		
From Beginning		
	Fetch Schema	
Real-Time Settings		
Time Id Column	[No Time Id] ▼	
Time Id Column Name		
Reset Data on Reconnect		

#### 2. Enter the following information:

Property	Description
Host	DolphinDB - Streaming host address.
Port	DolphinDB - Streaming host port. Default is 8848.
User Id	The user Id that will be used to connect to the DolphinDB - Streaming service.
Password	The password to connect to the DolphinDB - Streaming service.  Check the <i>Show Characters</i> box to display the entered password characters.
Table	Table to subscribe against.

3. Check the From Beginning box to subscribe from the beginning to the latest messages.

ı
---

If un-checked, you will only be subscribed to the latest messages.

4. Click to retrieve the schema of the configured subscription.

This populates the *Id Column* with the set of columns from the schema of type sym and the text array such as Character/Boolean/GUID, etc. The selected *Id Column* can be used to select a key column to manage data updates and inserts.

**NOTE:** Every message definition needs a text column to be defined as the Id column. By default, only the latest data will be loaded into memory.

Furthermore, a streaming time series window can be generated by creating a compound key with the *Id Column*, plus a separately specified *Time ID* column. This *Time ID* column can be from the source dataset, or alternatively automatically generated.

If the *Time Id column* is selected, then a scrolling time window can be specified.

Time Id Column	[Automatic Time Id] ▼	
Time Id Column Name	Automatic_Timestamp_Column	

For Automatic Time Id, define the Time Id Column Name.

As new data arrives from the subscription, new time slices will automatically be added, and old ones will be deleted.

If a new Id is received, a new row is added to the in-memory data set representing the DolphinDB - Streaming topic subscription. While if an existing ID is received, an existing row is updated.

5. Modify the Real-time settings if further changes are required.



Click . The new data source is added in the *Data Sources* pane.

# **Creating Google Analytics Input Data Source**

The Google Analytics connector allows you to track and report website traffic using the Google Analytics service. You will need the following to fetch Google Analytics data:


Field	Description
Service Account E-mail	The Service Account ID that is generated while creating credentials for the service account authentication.
Key File	The Key File (.p12) furnished by Google Analytics when you created the Service Account.
Profile ID	The Profile ID of the page you want to access in Google Analytics.

## Steps:


1. In the New Data Source page, select Input > Google Analytics in the Connector drop-down list.

## ← GoogleAnalyticsInput






- 2. Enter the Service Account Email that was generated while creating credentials to the service account authentication.
- 3. Set the Key File that will be used to connect to Google Analytics in Panopticon. Do one of the following:



- 4. Enter the *Profile ID* of the page you want to access in Google Analytics.
- 5. Enter the Start Date and End Date, if needed.
- 6. Click boxes. Fetch Dimensions And Metrics . This populates the Filter By Categories, Dimensions, and Metrics list



# **Creating Google Cloud Input Data Source**

Google Cloud connector allows for retrieval of the file from Google Cloud storage. This connector allows JSON/XML/Text/Excel files to be read from the Google Cloud storage.

### Steps:

1. In the New Data Source page, select Input > Google Cloud in the Connector drop-down list.

2. Enter the following information:

Property	Description
Bucket	Google Cloud bucket where the file resides.
Access Key	Access key to your Google Cloud service account.
Secret Key	Secret key to your Google Cloud service account.  To test the connection, click  Test Connection
	If Connection Failed displays, ensure the Bucket, Access Key, and Secret Key values are correct. You can also hover on this message to view the connection error.

- 3. Click the **Browse** tab. The available Google Cloud store files in the bucket you specified are displayed.
- 4. Select the Google Cloud file. The file name is displayed in the *File Path* field and the <u>Data Type</u> is updated with its related fields.
- 5. Select the **Only Show Know File Types** checkbox to narrow down the list based on the selected data type.
- 6. Select either the period (.) or comma (,) as the Decimal Separator.



- 7. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the **Save** button is enabled.
- 8. You can also opt to <u>load or save</u> a copy of the column definition.

NOTE This option is not available for the Excel data type.

9. You can also opt to click to add columns to the Google Cloud connection that represent sections of the message. Then enter or select:

Property	Description
Name	The column name of the source schema.
JsonPath/Column Index/XPath	The JsonPath/Column Index/XPath of the source schema.
Туре	The data type of the column. Can be a <b>Text, Numeric,</b> or <b>Time</b>
Date Format	The format when the data type is <b>Time</b> .
Enabled	Determines whether the message field should be processed.

NOTE

To parse and format times with higher than millisecond precision, the format string needs to end with a period followed by sequence of upper case S. There can be no additional characters following them.

For example: yyyy-MM-dd HH:mm:ss.SSSSSS

To delete a column, check its or all the column entries, check the topmost , then click .

. The new data source is added in the Data Sources list.


# **Creating Google Cloud Pub/Sub Input Data Source**

The Google Cloud Pub/Sub connector allows connection to Google Cloud Pub/Sub's message bus on a real-time streaming basis. Specifically, the connector allows Panopticon Streams to subscribe to XML, JSON, TEXT or FIX based messages that are published on particular topics. The data format itself is arbitrary, and consequently, the connection includes the message definition.

#### Steps:

10. Click

1. In the New Data Source page, select Input > Google Cloud PubSub in the Connector drop-down list.



2. Enter the *Service Account Credential JSON Text* with the generated JSON key (contains the private key) in the following format:

```
"type": "service_account",
   "project_id": "project-id",
   "private_key_id": "some_number",
   "private_key": "----BEGIN PRIVATE KEY----\n...
   =\n----END PRIVATE KEY----\n",
   "client_email": "<api-name>api@project-id.iam.gserviceaccount.com",
   "client_id": "...",
   "auth_uri": "https://accounts.google.com/o/oauth2/auth",
   "token_uri": "https://accounts.google.com/o/oauth2/token",
   "auth_provider_x509_cert_url":
   "https://www.googleapis.com/oauth2/v1/certs",
   "client_x509_cert_url": "https://www.googleapis.com/...<api-name>api%40project-id.iam.gserviceaccount.com"
}
```

#### **NOTE**

Ensure that when parameterizing the values in the Credential JSON Text, there is no white space as a single line content.

3. Click to populate the *Topic* drop-down list. Initially, the first topic in the list is displayed in the *Topic* drop-down box.

Select a topic.

4. Click to populate the *Subscription Name* drop-down list and select a subscription name.

You can also opt to create a subscription by manually entering the value into the Subscription Name list box.

#### **NOTE**

 A subscription name will be automatically generated when it is not entered or selected in the drop-down list.

This subscription will be created for connection and will be deleted as soon as its work is done. For example, when starting a presentation mode, a subscription will be created. Upon quitting the presentation mode, the subscription will then be deleted.

- Pub/Sub can automatically delete inactive subscriptions. This can be done by configuring the minimum required time of inactivity to schedule a subscription for deletion. This time must be longer than the message retention duration.
- 5. Select the Message Type.

6.	or.				
	NOTE	Prepend 'def	ault:' for the elements falling und	der default namespace.	
7.	Click			the connection details. Consequently, the list of	
	columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the Save button is enabled.				
8.	You can also o	opt to <u>load or save</u>	e a copy of the column definition	1.	
9.	Click . This message.	adds columns to	the Google Cloud Pub/Sub con	nection that will represent sections of the	
10.	Provide the fol	lowing informatio	n:		
	Property		Description		
	Name		The column name of the source	ce schema.	
	Fix Tag/XPa	th/Json Path	The Fix Tag/XPath/Json Path	of the source schema.	
	Туре		The data type of the column. Can be a <b>Text, Numeric,</b> or <b>Time</b>		
	Date Format	t	The <u>format</u> when the data type is <b>Time</b> .		
	Filter		Defined parameters that can be Text, and XML message types	be used as filter. Only available for JSON,	
	Enabled		Determines whether the mess	age field should be processed.	
11.	Google Cloud Panopticon Go column logic a	oogle Cloud Pub/s utomatically chec	les can have additional metadate Sub connector supports reading eks and generates attribute colur	eck the topmost , then click .  a as custom attributes.  these attributes as column values. The generations if messages received contain attributes.  y add them by clicking . A new entry display	
	Attribute Co	lumns			
	Name	2	Attribute Name	Enabled + -	
	Attrib	bute_1	Attribute_1	✓	
	name in messa columns, we ca	age otherwise it v an't change colur	vill be treated as null value. Curr	The attribute name must match to an attribute ently all attribute columns are treated as Text	

To delete an attribute column, check its  $\Box$  or all the column entries, check the topmost  $\Box$  , then click  $\overline{\phantom{a}}$  .

12. Define the Real-time Settings.




# Creating an InfluxDB 1.x Input Data Source

The InfluxDB 1.x connector allows for the retrieval of a JSON data set from InfluxDB 1.x. The database communicates over HTTP(S) where you can define a query in the URL to return the desired data.

### Steps:

1. In the New Data Source page, select Input > InfluxDB 1.x in the Connector drop-down list.




2. Enter the following information:

Property	Description
URL	InfluxDB 1.x host address.
Port	InfluxDB 1.x host port. Default is 8086.
User Id	The user Id that will be used to connect to the InfluxDB 1.x service.
Password	The password to connect to the InfluxDB 1.x service.  Select the <b>Show Characters</b> check box to display the entered characters.
Database	The name of the database that will communicate over the HTTP(S).
Time out (Secs)	The time out period applied to both the TCP socket and for individual read IO operations. Default is <b>10</b> .

- 3. Enter an SQL-like query language into the *Query* box.
- 4. Click . The new data source is added to the *Data Sources* list.


# **Creating JDBC Legacy Input Data Source**

The JDBC Legacy connector allows the retrieval and processing of data from virtually any database that has a JDBC driver.



### Steps:

1. In the New Data Source page, select Input > JDBC Legacy in the Connector drop-down list.



2. You can either select:

JNDI Name

	JNDI Nam	e <b>v</b>		(JNDI resource name as defined inside Context eg. jdbc/MyDB)
	Enter the	JNDI resource nam	ne to be used.	
	NOTE	The JNDI reso	urce name needs to be on the form:	
		jdbc/[reso	ourcename]	
•	URL			
	URL	~		
	Driver Cl	ass Name		
	User Id			
	Passwor	d	☐ Show o	haracters

Enter the *URL* specific to the database's JDBC driver, the *Driver Class Name* specific to the driver, and the *User Id* and *Password*.

Select the **Show Characters** check box to display the entered characters.

3. Select the appropriate *SQL Dialect* in the drop-down list to be able to generate the correct *SQL* for the required data repository.

You can select any of the following *SQL dialects*: AnsiSQL, MySQL, Oracle, SQL Server, SAP IQ, SAP ASE, Netezza, Vertica, SQLite, HadoopHive, DB2, PostgreSQL, Impala, Redshift, Informix, Teradata, dBase, SparkSQL.

Default is AnsiSQL.

- 4. Enter the *Timeout*. This is the length of time to wait for the server response. Default is **60**.
- 5. Check any of the following options when building the query:
  - Enclose parameters in quotes

By default, this option is checked, as the common use case for parameters is a filter WHERE clause.


Allow in-memory parameter filtering

Allows the whole dataset to be returned, and then filtered in memory. This process is much less efficient than adding the parameter as a  $\mathtt{WHERE}$  clause of the SQL query; however, it may be efficient in cases where small sets of records are returned on a very frequent basis.

Use data modification query


Signals that the table is created for writing data. This property is also used for filtering out target data tables for further data update action configuration

6. When **Table** is selected, the section below is enabled:



7. On the *Table* field, click Load to populate the drop-down list with tables. Select a table.

The list of tables that you can join is displayed. Also, the SQL query is generated and displayed in the *Query* text box.




8. Perform a join by checking one or more tables in the list.

The Left Column and Right Column fields are automatically filled out with the common fields.



You can also opt to select other common fields.

The SQL query is generated and displayed in the Query text box.



9. Click Generate Columns

The columns populate the Output Column section.

Column	Parameterize	Aggregate	
stocks.id	~	Sum	~
stocks.region		Group By	~
stocks.country		Group By	~
stocks.forex	~	Group By	~
stocks.mcaplocal	~	Group By	~
forex.id		Sum	~
forex.forex		Group By	~
forex.exchange	~	Group By	~

10. Individual columns can be added by selecting the corresponding *Column* check box in the *Output Column* listing. To select all of the columns, select the topmost check box.

The SQL query is generated and displayed in the Query text box.

- 11. If the data returned is to be aggregated, then the **Aggregate** box should be checked. For each selected column, the possible aggregation methods are listed including:
  - Text Columns: Last, First, Count, Group By
  - Date Columns: Count, Min, Max, Group By
  - Numeric Columns: Last, First, Sum, Count, Min, Max, Mean, Group By

The SQL query is generated and displayed on the Query text box.

12. Select the **Parameterize** check box and match the parameter to the appropriate column. By default, they will be matched by name.

The appropriate SQL Query is updated in the *Query* text box. This shows the default parameter value for the preview, and at run time the SQL will be updated to whatever the parameter value is.

13. If the data is to be filtered or aggregated on Date/Times, then a valid *Date Time* field needs to be selected from either a single Date/Time field, or a compound column created from a selected *Date* and a selected *Time* column.




- 14. Select the Constrain by Date Time check box and enter From and To Date/Time constraints.
- 15. Click the Query radio button to enable the text box and modify the SQL-like query language.
- 16. Click . The new data source is added to the *Data Sources* list.

## **Creating JDBC Input Data Source**


JDBC connector is the new version of JDBC Legacy connector and is the recommended connector for any new JDBC connectivity for better performance and configuration UI. Just like JDBC Legacy connector, it also allows the retrieval and processing of data from virtually any database, that has a JDBC driver.

#### Steps:

1. In the New Data Source page, select Input > JDBC in the Connector drop-down list.




- 2. On the Connection tab, set either of the following connection settings:
  - URL



- 3. Adjust the *Timeout*, if needed. Default is **60**.
- 4. Query definition and execution can be done, using either the query builder or freeform SQL. To use the query builder, select the **Query Builder** tab. Otherwise, proceed to step 5.

The Use Query Builder option is turned on by default.




4.1. Select the appropriate *SQL Dialect* in the drop-down list to be able to generate the correct *SQL* for the required data repository.


4.2. In the *Table* field, click to populate the drop-down list with tables. Select a table.

The SQL query is generated and displayed in the Preview Query text box.

Also, expanding the Join Tables displays the list of tables that you can join.



4.3. Perform a join by checking one or more tables in the list.



You can also opt to select other common fields.

The SQL query is generated and displayed in the Preview Query text box.

Search Tables	1.6.6.1	P1 1 - G 1	
Join Table	Left Column	Right Column	
public.forex	forex	▼ forex	
public.industry			
Generate Columns			
Column	Parameterize	Aggregate	
Date Time	▼ or	<u> </u>	
Constrain By Date Time From	То		
Preview Query			
Generate Columns	e columns populate the Outp	on "stocks"."forex" = "forex".  out Column section.	"forex'
Generate Columns			"forex"
Click Generate Columns . The			"forex"
Click Generate Columns . The	e columns populate the <i>Outp</i>	ut Column section.	"forex"
Click Generate Columns . The Generate Columns	e columns populate the <i>Outp</i>	out Column section.  Aggregate	"forex"
Click  Generate Columns  Column  stocks.id	e columns populate the <i>Outp</i>	ut Column section.  Aggregate  Sum	"forex"
Click  Generate Columns  Column  stocks.id stocks.region	e columns populate the <i>Outp</i>	Aggregate  Sum Group By	"forex"
Click  Generate Columns  Column  stocks.id stocks.region stocks.country	e columns populate the <i>Outp</i>	Aggregate  Sum Group By Group By	"forex"
Click  Generate Columns  Column  stocks.id stocks.region stocks.country stocks.forex	e columns populate the <i>Outp</i>	Aggregate  Sum Group By Group By Group By Group By	"forex"

4.5. Individual columns can be added by selecting the corresponding *Column* check box in the *Output Column* listing. To select all of the columns, select the topmost check box.

The SQL query is generated and displayed in the Preview Query text box.

- 4.6. If the data returned is to be aggregated, then the **Aggregate** box should be checked. For each selected column, the possible aggregation methods are listed including:
  - Text Columns: Count, Group By
  - Date Columns: Count, Group By

Date Time

- Numeric Columns: Sum, Count, Min, Max, Group By
- 4.7. Select the **Parameterize** check box and match the parameter to the appropriate column. By default, they will be matched by name.


The appropriate SQL Query is updated in the *Preview Query* text box.

4.8.	If the data is to be filtered or aggregated on Date/Times, then a valid Date Time field needs to be selected
	from either a single Date/Time field, or a compound column created from a selected Date and a selected
	Time column.


4.9. Select the **Constrain by Date Time** check box, and enter *From* and *To* Date/Time constraints that are assumed to be in this time zone for incorporation into the query.

If the query is to filter/constrain the results on Date/Time, the constrain sections are completed.


5. To use freeform SQL, select the **SQL** tab and turn on **Use SQL** toggle button.



5.1. Modify the SQL-like query language in the User Query text box.



6. Select the Advanced tab.



# Set the following property, if needed:

Property	Description
Use data modification query	Signals that the table is created for writing data. This property is also used for filtering out target data tables for further data update action configuration.
Fetch Size	Sets the number of rows to fetch per iteration.
Auto Commit	Postgres ignores fetch size if auto commit is not set to <b>False</b> . You would need to explicitly set it to force when using fetch size.
Connection Properties	NOTE: This property is only applicable for URL connection.  Enter Java-style properties format which can consist of a series of lines (terminated by CRLF, CR or LF) where each is a key-value pair, a comment, or a blank line.


7. Click . The new data source is added to the *Data Sources* list.

# **Creating a JSON Input Data Source**

The JSON connector allows the retrieval and processing of JSON files, either from a disk, a Text, or from a defined URL.

### Steps:

1. In the New Data Source page, select Input > Json in the Connector drop-down list.



- 2. Select the JSON File Source.
- 3. Select either the period (.) or comma (,) as the Decimal Separator.
- 4. Set the File Encoding to use:
  - UTF-8
  - UTF-16
  - UTF-32
  - US-ASCII
  - Windows-1252
- 5. Click Fetch to fetch the Record Paths then select one.
- Set the Array Handling setting to control how the data table will be created and to accommodate the array of values. Can be any of the following:
  - Add Rows (default) one row will be created for each value in the array
  - Add Columns one column will be created for each value in the array
  - Concatenate one column will be created for all values in the array, concatenated with a delimiter character
- 7. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the Save button is enabled.
- 6. You can also opt to load or save a copy of the column definition.
- 7. Click to add columns and specify their properties:



Name		The column name of the source schema.		
Json Path		The Json Path of the source schema.  The data type of the column. Can be a <b>Text, Numeric,</b> or <b>Time</b>		
Туре				
Date Format		The <u>format</u> when the data type is <b>Time</b> .		
Enabled		Determines wh	nether the message field should	be processed.
Name	JsonPath	Туре	Date Format	Enabled +
Column_1		Text	~	<b>▼ ☑</b>


8. Click Save . The new data source is added to the Data Sources list.

# **Creating Apache Kafka Input Data Source**

Allows Panopticon Streams to subscribe to Kafka topics on an external cluster.

# Steps:

1. In the New Data Source page, select Input > Kafka in the Connector drop-down list.



2. Enter the connection details:

Property	Description
Bootstrap Server	List of host/port pairs of Kafka servers used to bootstrap connections to a Kafka cluster.
	By default, the value is localhost: 9092, broker: 29092. However, this can be overridden by specifying another bootstrap server in the <i>External Settings</i> text box (as specified in step 3).
Schema Registry Host	Where the Schema Registry is located. This can be in a different location from the Kafka cluster.
Schema Registry Port	The port number of the schema registry which provides the serving layer for the metadata. Default is <b>8081</b> .


3. Enter the *External Settings* to support authentication (i.e., username and password). Note that if the bootstrap server is not secure, then there is no need to authenticate and you may leave this text box blank.

Below is an example of system settings for an SASL authentication:


```
bootstrap.servers=localhost:9093
sasl.jaas.config=\
  org.apache.kafka.common.security.plain.PlainLoginModule
required \
  username="dwchuser" \
  password="dwchpwd";
```

4. Click Fetch Topics. The first topic in the Topic drop-down list is selected and the schema is displayed.

By default, the **Hide Internal Topics** toggle button is enabled and the **Avro** message type is selected.




Tap the slider to turn it off. The internal Kafka topics are also displayed in the drop-down list.



Click the drop-down list to search and select the desired topic.

For non-Avro topics, select the Message Type: Fix, XML, Text, JSON, or Protobuf.

• If **Text** is selected, confirm the **Text Qualifier**, **Column Delimiter**, and if the first row of the message includes column headings.



Column Index controls the position of a column, Must be >= 0.

Property	Description
Text Qualifier	Specifies if fields are enclosed by text qualifiers, and if present to ignore any column delimiters within these text qualifiers.
Column Delimiter	Specifies the column delimiter to be used when parsing the text file.
First Row Headings	Determines if the first row should specify the retrieved column headings, and not be used in data discovery.


• If **JSON** is selected, enter *the Record Path* which allows the identification of multiple records within the JSON document (e.g., **myroot.items.item**).



Property	Description
Record Path	The record path that will be queried by the connector's path (e.g., myroot.items.item) .

If Protobuf is selected, confirm the Decimal Separator, and enter the Schema Name and Type Name.

Then click to select the File Descriptor (.desc file) in the Open dialog.



Property	Description
Schema Name	The Protobuf schema.
Type Name	The message of Protobuf type that will be sent to Kafka.
File Descriptor	The FileDescriptorSet which:  • is an output of the protocol compiler.  • represents a set of .proto files, using thedescriptor_set_out option.

5. Select the **From Beginning** check box to subscribe from the beginning to the latest messages.

If un-checked, you will only be subscribed to the latest messages.

6. Select either the period (.) or comma (,) as the Decimal Separator.

NOTE Prepend 'default:' for the elements falling under default namespace.

- 7. Click to fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the **Save** button is enabled.
- 8. For non-Avro message types, except **Protobuf**, click to add columns to the Kafka connection that represent sections of the message. Then enter or select:

Property	Description
Name	The column name of the source schema.
Fix Tag/JsonPath/Text Column Index/XPath	The Fix Tag/JsonPath/Text Column Index/XPath of the source schema.
Туре	The data type of the column. Can be a <b>Text</b> , <b>Numeric</b> , or <b>Time</b>
Date Format	The format when the data type is <b>Time</b> .
Filter	Defined parameters that can be used as filter. Only available for Avro, JSON, Text, and XML message types.
Enabled	Determines whether the message field should be processed.


### **NOTE**

To parse and format times with higher than millisecond precision, the format string needs to end with a period followed by sequence of upper case S. There can be no additional characters following them.

For example: yyyy-MM-dd HH:mm:ss.SSSSSS

9. You can also opt to load or save a copy of the column definition.

10. Define the Real-time Settings.




# **Creating Kx kdb+ Input Data Source**

The Kx kdb+ input data source allows connection to the Kx kdb+ databases on a polled basis.

## Steps:

1. In the New Data Source page, select Input > Kdb+ in the Connector drop-down list.




## 2. Enter the following properties:

Property	Description			
Host	Kx kdb+ host address.			
Port	Kx kdb+ host port. Default is <b>5001</b> .			
TLS Enabled	Ensure to check if you have started q with TLS only.			
User Id	The user ld that will be used to connect to Kx kdb+.			

Password	The password that will be used to connect to Kx kdb+.		
Timeout	The length of time to wait for the server response in seconds. Default is ${\bf 30}.$		
Retry Count	For long running queries, a query timeout can be specified to prevent the server from locking up. Default is ${\bf 0}$ .		

3. When **Table** is selected, the section below is enabled:



#### You can either:

- click and select a namespace from the list of all root level namespaces. By default, the selected namespace will be root (backtick `).
- For nested namespaces, enter them in the *Namespace* box (e.g., panopticon.test) to get the tables that were created under these namespaces.
- 4. On the *Table* field, click Load to populate the drop-down list with tables and views. Select a table or view.
- 5. Click Generate Columns

  The columns of the selected table or view populates the Output Column section.
- 6. Individual columns can be added by selecting the corresponding Column check box in the Output Column listing.
- 7. If the data returned is to be aggregated, then the **Aggregate** checkbox should be selected. For each selected column, the possible aggregation methods are listed including:
  - Text Columns: Group By
  - Date Columns: Count, Min, Max, Group By
  - Numeric Columns: Sum, Count, Min, Max, Group By
     In addition, the qSQL query is generated and displayed on the Query text box.
- 8. Select the **Parameterize** check box and match the parameter to the appropriate column. By default, they will be matched by name.


The appropriate qSQL query is updated on the *Query* text box. This shows the default parameter value for the preview, and at run time the qSQL will be updated to whatever the parameter value is.

9. If the data is to be filtered or aggregated on Date/Times, then a valid *Date Time* field needs to be selected from either a single Date/Time field, or a compound column created from a selected *Date* and a selected *Time* column.



- 10. Select the Constrain by Date Time check box and enter From and To Date/Time constraints.
- 11. In Kx kdb+, you can modify the query to regroup the aggregated data per time units (i.e., Seconds, Minutes, Hours, Date, Week, Month). Select the **Period** check box, enter the time duration and click then select the

Hours, Date, Week, Month). Select the **Period** check box, enter the time duration and click then select the time unit.



- 12. Click the Query radio button to enable the text box and modify the qSQL query language.
- 13. Select the Flatten List Limit.

This allows retrieval of the first 'n' items in the list and produce new columns in the output schema with a dot notation.

For example, if there are two nested fields (BidPrices and OfferPrices) and the flatten list limit selected is five, then the output schema will be:

BidPrices.1, BidPrices.2, BidPrices.3, BidPrices.4, BidPrices.5, OfferPrices.1, OfferPrices.2, OfferPrices.3, OfferPrices.4, OfferPrices.5

If there are less than five items in the list, then the values will be null.



- 14. Select Pass to function check box to activate a connection to a server using a proxy. Enter the value.
- 15. You may also define a **Deferred Sync Query**.
- 16. Click . The new data source is added in the *Data Sources* list.

### Kx kdb+ - Deferred Sync Query

The Deferred Sync Query feature allows the Kx kdb+ connector to support synchronous and asynchronous reads. The advantage of using this option is that there is no queue on the Kx kdb+ server side, queries are farmed out to slaves and returned to asynchronous instead.

Deferred Sync Query (use {Query} parameter here as a place holder for the target	query)
$ \{@[\text{neg }z.w;@[\text{value};x;`\$"failed to run query"];`\$"failed to post back"]\}["\{Query\}"] $	
Selecting the Deferred Sync Query check box would enable the query bo	x:
✓ Deferred Sync Query (use {Query} parameter here as a place holder for the target	query)
{@[neg .z.w;@[value;x;`\$"failed to run query"];`\$"failed to post back"]}["{Query}"]	

The {Query} parameter is used as a place holder for the target query that is defined in the *Query* builder.


# Creating Kx kdb+Tick Input Data Source

The Kx kdb+tick input data source allows connection to a Kx kdb+ ticker plant on a real-time streaming basis.

Specifically, it allows Panopticon Streams to subscribe to Kx kdb+tick through the definition of *Service*, *Table*, *Symbol*, or directly through *Functional Subscription*.

### Steps:

1. In the New Data Source page, select Input > KDB+ Tick in the Connector drop-down list.



## 2. Enter the following properties:

Property	Description			
Host	Kx kdb+tick host address.			
Port	Kx kdb+tick host port. Default is <b>5010</b> .			
TLS Enabled	Ensure to check if you have started q with TLS only.			
User Id	The user ld that will be used to connect to Kx kdb+tick.			
Password	The password that will be used to connect to Kx kdb+tick.			

NOTE	These properties can be parameterized.
------	--

- 3. Select either Subscription Type:
  - Service

Enter the following properties:

Subscription Name (e.g., .u.sub)

#### NOTE

Instead of entering the table and symbol to subscribe against in the Table and Symbol text boxes, you can specify the full subscription syntax in the Subscription Name text box. For example:

.u.sub[`table;`symbol]

To subscribe to the trade table and AAPL, AIG, and DOW symbols, enter this in the Subscription Name text box:

.u.sub[`trade;`AAPL`AIG`DOW]

• Table to subscribe against (e.g., trade)

### **NOTE**

- You may use just a back tick for the table name, intending to subscribe to all available tables.
- When a table name is not entered in the Table text box, then the Symbol text box is disabled meaning it will not be used while doing subscription.

Symbol to subscribe against (e.g., AAPL)

**NOTE** 

Multiple symbols should be separated by a comma.

Functional Subscription

Enter the functional subscription that needs to be issued (e.g., .u.sub[`trade;`])

4. Click Fetch Schema

to retrieve the schema of the configured subscription.

This populates the *Id Column* with the set of columns from the schema of type sym and the text array such as Character/Boolean/GUID, etc.

5. Check *Constrain subscription to matching symbols* to select the column which contains specific symbols. Otherwise, the filtering against these symbols will not take place.

**NOTE** 

The Constrain subscription to matching symbols only lists sym fields. Therefore, if you select a non sym type in the *Id Column*, it is not recommended to select the default value [Id Column] in the Constrain subscription to matching symbols drop-down list.

- 6. Activate or deactivate *Initialize with historic data*. If unchecked, the data source will only be populated with streaming updates that are subscribed against. If checked, the data source is first initialized against a store of data, after which subscribed streaming updates are then applied.
- 7. Enter the following information:
  - Host
  - Port
  - User Id
  - Password
  - Timeout
  - Query

These entries can be parameterized.

8. Select *Deferred Sync Query* check box to allow the Kxkdb+tick data source to support synchronous and asynchronous reads. The advantage of using this option is that there is no queue on the Kx kdb+tick server side, queries are farmed out to slaves and returned to asynchronous instead.

The {Query} parameter is used as a place holder for the target query that is defined in the Query builder.

9. Select the Flatten List Limit.

This allows retrieval of the first 'n' items in the list and produce new columns in the output schema with a dot notation.

For example, if there are two nested fields (BidPrices and OfferPrices) and the flatten list limit selected is five, then the output schema will be:

BidPrices.1, BidPrices.2, BidPrices.3, BidPrices.4, BidPrices.5, OfferPrices.1, OfferPrices.2, OfferPrices.3, OfferPrices.4, OfferPrices.5

If there are less than five items in the list, then the values will be null.



10. Define the Real-time Settings.




# **Creating ksqIDB Input Data Source**

The ksqlDB connector allows executing ksqlDB pull queries and terminating push queries.



#### Steps:

1. In the New Data Source page, select Input > ksqIDB in the Connector drop-down list.



2. Enter the following properties:

Property	Description
Server URL	ksqlDB host address.

Username	User Id that will be used to connect to ksqIDB.
Password	Password that will be used to connect to ksqlDB.

- 3. Select the **Collection** check box to enable and select either:
  - Stream

Immutable and append-only collections which are useful for representing a series of historical facts. Adding multiple events with the same key allows these events to be appended to the end of the stream.

Table

Mutable collections. Adding multiple events with the same key allows the table to only keep the value for the last key. This collection is helpful in modeling change over time and often used to represent aggregations.

- 4. Click Fetch to populate the drop-down list. Select the collection.
- 5. Enter an SQL-like query language into the Query box.
- 6. Select the From Beginning check box to subscribe from the beginning to the latest messages.

From Beginning

If un-checked, you will only be subscribed to the latest messages.

- 7. Enter the Timeout. Default is 5 (in seconds).
- 8. Select either the dot (.) or comma (,) as the Decimal Separator.
- 9. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the **Save** button is enabled.
- 10. You can also opt to load or save a copy of the column definition.
- 11. Click . A new column entry displays. Enter or select the following properties:

Property	Description		
Name	The column name of the source schema.		
Туре	The data type of the column. Can be a <b>Text</b> , <b>Numeric</b> , or <b>Time</b>		
Date Format	The format when the data type is <b>Time</b> .		
Enabled	Determines whether the message should be processed.		

To delete a column, check its  $\square$  or all the column entries, check the topmost  $\square$ , then click  $\overline{}$ .

12. Click

Save


. The new data source is added in the Data Sources list.

# **Creating ksqIDB - Streaming Input Data Source**

The ksqlDB - Streaming connector allows executing ksqlDB push queries.

## Steps:

1. In the New Data Source page, select Input > ksqlDB - Streaming in the Connector drop-down list.



2. Enter the following properties:

Property	Description
Server URL	ksqIDB - Streaming host address.
Username	User Id that will be used to connect to ksqIDB - Streaming.
Password	Password that will be used to connect to ksqIDB - Streaming.

- 3. Select the **Collection** check box to enable and select either:
  - Stream

Immutable and append-only collections which are useful for representing a series of historical facts. Adding multiple events with the same key allows these events to be appended to the end of the stream.

• <u>Table</u>

Mutable collections. Adding multiple events with the same key allows the table to only keep the value for the last key. This collection is helpful in modeling change over time and often used to represent aggregations.

- 4. Click Fetch to populate the drop-down list. Select the collection.
- 5. Enter an SQL-like query language into the *Query* box.
- 6. Select the From Beginning check box to subscribe from the beginning to the latest messages.

Erou	m Be	ainr	nina
110	III DC	yıı ıı	mny

If un-checked, you will only be subscribed to the latest messages.

- 7. Enter the Timeout. Default is 5 (in seconds).
- 8. Select either the dot (.) or comma (,) as the Decimal Separator.
- 9. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the **Save** button is enabled.
- 10. You can also opt to load or save a copy of the column definition.
- 11. Click . A new column entry displays. Enter or select the following properties:

Property	Description		
Name	The column name of the source schema.		
Туре	The data type of the column. Can be a <b>Text</b> , <b>Numeric</b> , or <b>Time</b>		
Date Format	The <u>format</u> when the data type is <b>Time</b> .		
Enabled	Determines whether the message should be processed.		

To delete a column, check its or all the column entries, check the topmost, then click

12. Define the Real-time Settings.



13. Click . The new data source is added in the Data Sources list.

# **Creating MongoDB Input Data Source**


The MongoDB connector is an interface used to import MongoDB's schema-less BSON documents into a table schema that Panopticon Streams can interpret and analyze. It uses many BSON structure types and MongoDB query features.

#### Steps:

1. In the New Data Source page, select Input > MongoDB in the Connector drop-down list.

# ← MongoDBInput







2. Enter the following properties:

Property	Description	
URL	<ul> <li>Enter either:</li> <li>localhost if the database resides on the same computer, or</li> <li>enter the IP address and port of the computer where MongoDB is installed (e.g., 192.168.1.1:27017). If no port is specified, the default is 27017.</li> </ul>	
User Id	The user Id that will be used to connect to MongoDB.	
Password	The password that will be used to connect to MongoDB.	
Authentication DB	The database where the user is created.	
Database	The database that will be used.	
Collection	The collection that will be used.	

3. To make the Query Document feature of MongoDB available in Panopticon, select **Use Query Document**.



The *Plugin Settings* pane updates to display the settings of this query option.



For the *Method* option, select any of the following values:

#### Find (Default)

Allows you to fetch a document from a MongoDB collection.

Two more configurable settings are available:

#### Sort

Provide a JSON object that defines the sort criteria, then set the order to either 1 for ascending or -1 for descending (e.g., {"address.building":1}).

#### Projection

Provide a JSON object to include or exclude from the result of the **Find** query.

For example, if a document has 9 documents and you only need to display 5, you can either:

select 5 JSON objects, then set the limit value to 1 to display

```
{"cuisine":1, "grades":1, "restaurant_id":1, "name":1, "borough":1}
```

select 4 JSON objects then set the limit value to 0 to hide

{"address.zipcode":0, "address.coord":0, "address.street":0, "address.building":0}

#### **NOTE**


\_id field is always displayed while executing the Find method. You can opt to set this field to 0 to hide it (e.g., {"\_id":0}).

### Aggregate


Allows you to specify aggregation pipeline using multiple stages.

Python format of the pipeline query can be used, see <u>Getting Started with Aggregation Pipelines in Python</u> for more information. In addition, JSON style syntax with query contained in a JSON object can also be used.

See Query Documents for more information on the Query Documents feature on MongoDB.



4. Instead of using **Use Query Document**, select the **Parameterize** query option.



Click **Fetch Parameters** to populate the *Parameter* drop-down and select a value. Then select what column to filter on in the *Filter By* drop-down.

5. Select either the period (.) or comma (,) as the *Decimal Separator*.



6. Select the Data Type Discovery. This property specifies how many rows to fetch from the input data source,


Generate Columns

when auto generating the schema after clicking



- 7. You can also opt to load or save a copy of the column definition.
- 8. You can also opt to click . A new row displays in the JSON list box. Enter the necessary information for each column.

Property	Description	
Name	The column name of the source schema.  NOTE: It is recommended to name the column the same as its JSON path for clarity and uniformity.	
JsonPath	The JsonPath of the source schema.	
Туре	The data type of the column. Can be a <b>Text</b> , <b>Numeric</b> , or <b>Time</b>	
Structure	Used for more advanced features and are covered in the Row-Wise Array Expansion, Column-Wise Array Expansion, and Bson-Wise Array Expansion	



To delete a column, check its or all the column entries, check the topmost, then click.

# **Row-Wise Array Expansion**

MongoDB's BSON document structure can store array data types. In order to interpret that data, the user has to decide how they want those multi-value fields to be displayed.

Row-wise array expansion takes an array of values and expands them in a single column creating a new row for each value in the array. If there are multiple row-expanded arrays in the same document, then the number of rows generated is equal to the largest array size. Additionally, an *Automatic x-axis* column is automatically generated for use as an x-axis value for visualizations using array data.

To use the row-wise array expansion feature, select **Row-Expanded Array** from the *Structure* drop-down box.

This feature will only work for an array data type. If the actual data type in MongoDB is not array or the array is empty, the column will not populate.

#### **Column-Wise Array Expansion**

MongoDB's BSON document structure can store array data types. In order to interpret that data, the user has to decide how they want those multi-value fields to be displayed.

Column-wise array expansion takes an array of values and expands them into multiple table columns creating a number of columns equal to an array specific number set by the user. If there are multiple column-expanded arrays in the same document, the combined number of new columns is appended to the end of the table with their respective array indices and the original columns are removed.

To use the column-wise expansion feature, select Column-Expanded Array in the Structure drop-down box.

The corresponding *Column Count* text box will be enabled and the user can enter the number of columns for the plugin to generate as columns for that array.

#### **Bson-Wise Array Expansion**

MongoDB's BSON document structure can store array data types. In order to interpret that data, the user has to decide how they want those multi-value fields to be displayed.

Bson-wise array expansion allows parsing of all the fields of a nested hierarchy in a sub document of a JSON array. During data retrieval, the column value is converted to JSON, and nested columns are flattened based on a JSON parser logic.

To use the Bson-wise expansion feature, select **Bson-Expanded Array** in the *Structure* drop-down box.


# **Creating MQTT Input Data Source**

The	MO	TT	connector	allows:

- connection to MQTT's message bus on a real-time streaming basis.
- Panopticon Streams server to subscribe to FIX, JSON, Text or XML based messages that are published on particular topics. The data format itself is arbitrary, and consequently, the connection includes the message definition.
- encrypted/SSL connections using a generated CA certificate file.


#### Steps:

1. In the New Data Source page, select Input > MQTT in the Connector drop-down list.



## 2. Enter the following properties:

Property	Description	
Broker URL	The location of the message broker. Default is tcp://localhost:1883.	
Topic	The topic or the queue physical name.  Example: level1/level2/level3/level4 etc.  NOTES: You can also opt to use a wild card in the topic name specification.  The plus sign symbol (+) can be used as a wild card for any value at one specific level.  Example: level1/level2/+/level4  The hash sign symbol (#) can be used as a wild card for any values across more than one level.	
	Example: level1/#/level4	
User Id	The user ld that will be used to connect to MQTT.	



4. In MQTT, a topic consists of one or more topic levels. Enter the *Topic Level Separator* to use. Default is / (forward slash).

Upload File

Link To File

Link To File

and entering a File Path.

(File Type: .crt,.cer,.der,.pem)

5. Select the Message Type.

Load Type

CA Certificate

6. Select either the period (.) or comma (,) as the Decimal Separator.

Link to a CA Certificate file by clicking Link to File

NOTE Prepend 'default:' for the elements falling under default namespace.

- 7. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the Save button is enabled.
- 8. You can also opt to load or save a copy of the column definition.
- 9. You can opt to click to add columns to the MQTT connection that represent sections of the message. Then enter or select:

Property	Description
Name	The column name of the source schema.
XPath/JsonPath/Fix Tag/Column Index	The XPath/JsonPath/Fix Tag/Column Index of the source schema.
Туре	The data type of the column. Can be a <b>Text</b> , <b>Numeric</b> , or <b>Time</b>

Filter  Defined parameters that can be used as filter. Only available for JSON, Text, and XML message types.  Enabled  Determines whether the message field should be processed.	Date Format	The <u>format</u> when the data type is <b>Time</b> .  NOTE:  To parse and format times with higher than millisecond precision, the format string needs to end with a period followed by sequence of upper case S. There can be no additional characters following them.  For example: yyyy-MM-dd HH:mm:ss.SSSSSS
Enabled Determines whether the message field should be processed.	Filter	· ·
	Enabled	Determines whether the message field should be processed.

To delete a column, check its  $\square$  or all the column entries, check the topmost  $\square$  , then click - .

10. Text for topic levels can be consumed as additional columns into the data table.

The *Topic Columns* section shows and allows defining data table columns and mapping them to topic hierarchy levels (index based from left, 0 based).

Like columns from message data, manually add them by clicking . A new entry displays.


# Name Level Enabled + − Level\_1 0 ✓

Name can be any unique topic level within the topic name. The Level is the hierarchy level of the topic column.

Select the Enabled check box to enable a topic column.

To delete a topic column, check its or all the topic column entries, check the topmost, then click.

11. Define the Real-time Settings.



# **Creating MQTT Publisher Input Data Source**

The MQTT Publisher connector allows writing message to a MQTT topic.

### Steps:

1. Enter the following properties:

Property	Description
Broker URL	The location of the message broker. Default is tcp://localhost:1883
Topic	The topic or the queue physical name.  Example:

	level1/level2/level3/level4 etc.
	NOTES:
	You can also opt to use a wild card in the topic name specification.
	• The plus sign symbol (+) can be used as a wild card for any value at one specific level.
	Example: level1/level2/+/level4
	The hash sign symbol (#) can be used as a wild card for any values across more than one level.
	Example: level1/#/level4
User Id	The user ld that will be used to connect to MQTT Publisher.
Password	The password that will be used to connect to MQTT Publisher.

2. To allow encrypted connections, select the *CA Certificate*, *Client Certificate*, and *Client Key* by clicking **Browse**Browse

to browse to the file sources.

3. For *Payload*, enter the data that you want to send as message. The format can be anything supported by MQTT broker, typically JSON.

NOTE This property can also be parameterized.

# **Creating MS Excel Input Data Source**


This is the most commonly used data connector when prototyping and is used for retrieving data from MS Excel workbooks or spreadsheets, where for each selected sheet, the first row contains the field/column names, and subsequent rows contain the data.

The MS Excel connector supports reading data files stored in either the legacy XLS, and the newer XLSX format. The XLSX format is read on a row-by-row basis, allowing for better performance and less memory consumption compared to the XLS format.

NOTE
In production use, it is not advised to use a single Excel file as multiple Panopticon data sources. This is because, when using the same Excel file with the data on several sheets, conflicts may occur in reading the file.


### Steps:

1. On the New Data Source page, select MS Excel in the Connector drop-down list.



2. Upload a data source snapshot by clicking Browse and browse to the file source.

When a file is selected, the MS Excel connector will automatically select the first available sheet, set the first row as headers, and populate available columns.




By default, all the generated columns are enabled. You can uncheck the **Select All** box, then check the boxes of the columns that will be enabled.

- 3. Adjust Sheet selection, if required. Selecting a new sheet will re-populate the Columns list.
- 4. Adjust the **Headers On First Row** if needed. By default, the connector will pick up headers from the first row if all cells on the first row contain text data.

You can opt to select one of the following:

- Leave headers on first row as Auto if you want the connector to automatically pick up column names from sheet
- Select Yes to force picking first row as headers.

Select No to force not picking first row as headers. This will auto generate all column names.



5. Adjust column *Type* or *Date Format* to adjust data interpretation.



. The new data source is added in the Data Sources pane.


# **Creating OneTick Input Data Source**

The OneTick connector allows connection to OneMarketData OneTick tick history databases on a polled basis. In general, it is used to retrieve conflated time series data sets. The connector supports either:

- Execution of a specified OTQ
- Execution of a specified parameterized OTQ
- Execution of a custom SQL Query

### Steps:

1. In the New Data Source page, select Input > OneTick in the Connector drop-down list.



- 2. Enter the *Context* (for example, **REMOTE**).
- 3. You can either check:
  - Show Local OTQs box to display the local OTQs in the Selected OTQ drop-down list.
  - Show Remote OTQs box to display the remote OTQs in the Selected OTQ drop-down list.

An OTQ can be specified for execution, or a custom SQL query can be executed, through selection of the appropriate radio button:

- OTQs
- Query
- 4. Click **Load** to populate the *Selected OTQ* drop-down list. Select an OTQ.

The list of input parameters that the OTQ expects is displayed. In addition, the basic SQL query is generated allowing the OTQ to be executed and the input parameters specific to the selected OTQ. The following are generic to all OTQs:

Symbol List



- From
- To

These add additional filter criteria such as symbol, and time window onto the basic OTQ.

- 5. Check the **Separate DB Name** box to generate a separate field for the database name.
- Check the Show per symbol errors as warnings box to proceed with warnings in the log if symbol errors are returned.

The result is a fully generated OneTick SQL query. This can be edited as required.



. The new data source is added in the Data Sources list.


# **Creating OneTick CEP Input Data Source**

The OneTick CEP connector allows connection to OneMarketData OneTick tick history databases on a streaming subscription basis. The connector supports either:

- Execution of a specified OTQ
- Execution of a specified parameterized OTQ
- To use the OneTick CEP connector, it requires a JAR file to be added and some configurations to be performed. Further details are provided in the <a href="Panopticon Real Time Installation and Troubleshooting Guide">Panopticon Real Time Installation and Troubleshooting Guide</a>.

### Steps:

1. In the New Data Source page, select Input > OneTick CEP in the Connector drop-down list.



- 2. Enter the *Context* (for example, **REMOTE**).
- 3. You can either check:
  - Show Local OTQs box to display the local OTQs in the Selected OTQs drop-down list.
  - Show Remote OTQs box to display the remote OTQs in the Selected OTQs drop-down list.
- 4. Click **Load** to populate the *Selected OTQ* drop-down list. Select an OTQ.

The OTQ Parameters section displays with the list of input parameters based on the selected OTQ.



- 5. Select/unselect the Separate DB Name box.
- 6. Click Fetch Schema to populate the *Id Column* list box.
- 7. From this list box select the field which will define a unique data record to subscribe against.

The following are generic to all OTQs

- Symbol List
- From

То

These add additional filter criteria such as symbol, and time window onto the basic OTQ.

8. Define Real-time Settings.



. The new data source is added in the Data Sources list.

# **Creating Python Input Data Source**

The Python connector lets you load data through Python. This can be useful for example when connecting to unusual data sources for which there is a client library in Python, or when you want to apply custom data transforms to the data in Python.

A requirement for using the Python connector is that your Panopticon server has been configured to integrate with a running Python environment, as described in the <u>Real Time Installation and Reference Guide</u>.

The Python connector has settings that may be pre-configured by the Panopticon server administrator, and thereby not exposed to the users of the connector. If the settings are not pre-configured, you will see the following settings:

When using Pyro4 integration:

Setting	Description
Host	The hostname or IP-number where Python is running.
Port	The port number where Pyro4 is listening.
HMAC Key	A secret password set in the integration configuration that must be matched.
Serialization Type	Can be either <b>serpent</b> or <b>pickle</b> .

When using FAST API integration (Linux servers only):

Setting	Description
Host	The hostname or IP-number where Python is running.
Port	The port number where FAST API is listening.

You will also see the following setting:

Setting	Description
Python Script (checkbox)	Whether Apache Arrow serialization should be applied to the data during transfer from Python to Panopticon. This will make the data transfer significantly faster.

**NOTE** 


If your Panopticon server has not been configured for integration with a Python environment, you will not be able to use the Python connector, regardless of what settings you make in the connector.

# **Creating RabbitMQ Input Data Source**

The RabbitMQ connector allows connection to RabbitMQ's message bus on a real-time streaming basis. Specifically, the connector allows Panopticon Streams to subscribe to XML, JSON, Text or FIX based messages that are published on particular topics.

### Steps:

1. In the New Data Source page, select Input > RabbitMQ in the Connector drop-down list.



2. Enter the connection details including:

Property	Description
Broker	The location of the message broker.

User Id	The user Id that will be used to connect to RabbitMQ.
Password	The password that will be used to connect to RabbitMQ.

# 3. Select any of the following Exchange Types:

Exchange Type	Description
Default	A direct exchange with no name that is pre-declared by the broker.  Selecting this exchange type disables the <i>Exchange</i> section ( <i>Exchange</i> and <i>Routing Key</i> properties).
	Exchange Type default   Exchange  Durable Auto Delete  Routing Key  Explicit Queue
Fanout	Broadcasts all of the messages it receives to all of the queues it knows and the routing key is ignored (the <i>Routing Key</i> field is disabled).
Direct	Delivers messages to queues based on a message routing key. It is ideal for the unicast routing of messages, although it can be used for multicast routing as well.
Topic	A message sent with a particular routing key will be delivered to all of the queues that are bound with a matching binding key.
Headers	Exchanges routed based on arguments containing headers and optional values.

# 4. Depending on the selected *Exchange Type*, select or define the following:

Exchange Type Property	Description
Exchange	Name of the exchange.
Durable	Enable so the exchange can survive a broker restart.
Auto Delete	Enable so the exchange is deleted when the last queue is unbound from it.
Routing Key	The routing key used to deliver messages to queues.
Headers	This field is only available when the message type is <b>Header</b> . Binding a queue to a Headers exchange is possible using more than one header for matching. Setting <i>x-match</i> to <b>any</b> , means just one matching value is sufficient. Setting it to <b>all</b> means that all values must match. Default is <b>x-match=all</b> .

5. Select the *Explicit Queue* check box and enter the custom queue name. Then enter or enable the following properties:

Queue Property	Description
Properties	The custom queue property.
Durable	Enable so the queue can survive a broker restart.
Auto Delete	Enable so the queue that had the least consumer will be deleted when that connection closes.

- 6. Select the Message Type.
- 7. Select either the period (.) or comma (,) as the Decimal Separator.

NOTE Prepend 'default:' for the elements falling under default namespace.

- 8. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the Save button is enabled.
- 9. You can also opt to load or save a copy of the column definition.
- 10. You can opt to click to add columns to the RabbitMQ connection that represent sections of the message. Then enter or select:

Property	Description
Name	The column name of the source schema.
Fix Tag/Json Path/Text Column Index/Xpath	The Fix Tag/Json Path/Text Column Index/Xpath of the source schema.
Туре	The data type of the column. Can be a <b>Text</b> , <b>Numeric</b> , or <b>Time</b>
Date Format	The <u>format</u> when the data type is <b>Time</b> .  NOTE:  To parse and format times with higher than millisecond precision, the format string needs to end with a period followed by sequence of upper case S. There can be no additional characters following them.  For example: yyyy-MM-dd HH:mm:ss.SSSSSS
Filter	Defined parameters that can be used as filter. Only available for JSON, Text, and XML message types.
Enabled	Determines whether the message field should be processed.

			_
To delete a column, check its	or all the column entries, check the topmost	, then click	Ξ.

11. Define the Real-time Settings.

. The new data source is added in the Data Sources list.

# **Creating Amazon S3 Input Data Source**

The S3 connector allows for retrieval of the file from an S3 storage location. This connector allows JSON/XML/Text/Excel files to be read from the S3 storage. This connector will work with any S3 compliant storage providers.

### Steps:

- 1. In the New Data Source page, select Input > S3 in the Connector drop-down list.
- 2. Enter the following information:

Property	Description
URL	URL where the S3 bucket can be accessed. Default is <a href="https://s3.amazonaws.com">https://s3.amazonaws.com</a> .
Bucket	S3 bucket where the file resides.
Access Key	Access key to your S3 service account.
Secret Key	Secret key to your S3 service account.  To test the connection, click  Test Connection  If Connection Failed displays, ensure the Bucket, Access Key, and Secret Key values are correct. You can also hover on this message to view the connection error.
File Path	Path of the on the S3 bucket.

- 3. Select the <u>Data Type</u>.
- 4. Select either the period (.) or comma (,) as the Decimal Separator.



- 5. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the **Save** button is enabled.
- 6. You can also opt to load or save a copy of the column definition.

7. You can also opt to click to add columns to the S3 connection that represent sections of the message. Then enter or select:

Property	Description
Name	The column name of the source schema.
JsonPath/Column Index/XPath	The JsonPath/Column Index/XPath of the source schema.
Туре	The data type of the column. Can be a <b>Text, Numeric,</b> or <b>Time</b>
Date Format	The <u>format</u> when the data type is <b>Time</b> .
Enabled	Determines whether the message field should be processed.

NOTE

To parse and format times with higher than millisecond precision, the format string needs to end with a period followed by sequence of upper case S. There can be no additional characters following them.

For example: yyyy-MM-dd HH:mm:ss.SSSSSS

To delete a column, check its or all the column entries, check the topmost , then click . The new data source is added in the *Data Sources* list.

# **Creating Rserve Input Data Source**

The Rserve connector allows the retrieval of an output data frame from a running Rserve process.


For R connectivity, R must be first installed, together with the Rserve library. In addition, R must be open, and the Rserve library must be loaded and initialized.

### Steps:

1. In the New Data Source page, select Input > Rserve in the Connector drop-down list.

# ← RserveInput





### 2. Enter the following properties:

Property	Description
Host	Rserve host address.
Port	Rserve host port. Default is <b>6311</b> .
User Id	The user ld that will be used to connect to the Rserve service.
Password	The password that will be used to connect to the Rserve service.


- 3. Enter the required *R script* to execute on the active Rserve instance.
- 4. The Timeout is set to **10** seconds by default to ensure that slow running R scripts do not impact other areas of the product. You can opt to enter a new value.
- 5. Select whether the parameters should be automatically enclosed in quotes by selecting the *Enclose parameters* in quotes check box.
- 6. Click Save . The new data source is added in the Data Sources list.

# **Creating Solace Input Data Source**

The Solace connector allows connection to Solace's message bus on a real time streaming basis. Specifically, the connector allows Panopticon Streams to subscribe to messages that are published in particular topics in Solace and consequently, perform operational analytics.

### Steps:

1. In the New Data Source page, select Input > Solace in the Connector drop-down list.



2. Enter the connection details including:


Property	Description
Host	Solace host address.
VPN Name	Message VPN name. Default is <b>default</b> .

User Id	The user ld that will be used to connect to Solace.
Password	The password that will be used to connect to Solace.

- 3. Enter the *Topic* or the queue physical name.
- 4. Select the Message Type. This will specify the format of the data within the message.


Aside from the **JSON**, **Text**, and **XML** message types, **Protobuf** and **SDTMap** are also supported in Solace.

If **Protobuf** is selected, confirm the **Decimal Separator**, and enter the *Schema Name* and *Type Name*.



Property	Description
Schema Name	The Protobuf schema.
Type Name	The message of Protobuf type that will be sent to Kafka.
File Descriptor	The FileDescriptorSet which:  • is an output of the protocol compiler.  • represents a set of .proto files, using thedescriptor_set_out option.

### For SDTMap, confirm the Decimal Separator.



5. Select either the period (.) or comma (,) as the Decimal Separator.



- 6. Click Generate Columns to the fetch the schema based on the connection details. This populates the list of columns with the data type found from inspecting the first 'n' rows of the input data source.
- 7. You can opt to click to add columns to the Solace connection that represent sections of the message. Then enter or select:

Property	Description
Name	The column name of the source schema.
JsonPath/Column Index/XPath	The JsonPath/Column Index/XPath of the source schema.
Туре	The data type of the column. Can be a <b>Text</b> , <b>Numeric</b> , or <b>Time</b>
Date Format	The format when the data type is <b>Time</b> .  NOTE:  To parse and format times with higher than millisecond precision, the format string needs to end with a period followed by sequence of upper case S. There can be no additional characters following them.  For example: yyyy-MM-dd HH:mm:ss.SSSSSS
Filter	Defined parameters that can be used as filter. Only available for JSON, Text, and XML message types.
Enabled	Determines whether the message field should be processed.

- To delete a column, check its or all the column entries, check the topmost , then click .
- 8. To create a new Timestamp field, enter a new *Timestamp Name* and then select the valid Date/Time from either a single *Date* or *Time* field, or a compound column created from *Date* and *Time* fields.
- 9. Define the Real-time Settings.
- 10. Click . The new data source is added in the Data Sources list.


### **Creating Stream Simulator Input Data Source**

The Stream Simulator connector is very similar to the Text connector with the addition of the time windowing of message queue connectors.

Creating the Stream Simulator input data source includes setting for how fast and how many messages are pushed through in each batch.

### Steps:

1. In the New Data Source page, select Input > Stream Simulator in the Connector drop-down list.



# 2. Select the Text File Source.

The standard settings controlling how the text file is parsed, is listed.

### These include:

Property	Description
Skip First N Rows	Specifies the number of rows that will be skipped.
Data Type Discovery	Specifies how many rows from the text file should be used when automatically determining the data types of the resulting columns.
Decimal Separator	Select either the period (.) or comma (,) as the decimal separator.
Text Qualifier	Specifies if fields are enclosed by text qualifiers, and if present, to ignore any column delimiters within these text qualifiers.
	Can be any of the following options:
	None

	<ul><li>Single Quote</li><li>Double Quote</li></ul>
Column Delimiter	Specifies the column delimiter to be used when parsing the text file.
First Row Headings	Determines if the first row should specify the retrieved column headings, and not be used in data discovery.


- 3. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the **Save** button is enabled.
- 4. You can also opt to load or save a copy of the column definition.
- 5. You can opt to click . A new column entry displays. Enter or select the following properties:

Property	Description
Name	The column name of the source schema.
Column Index	The column index controls the position of a column. Must be >= <b>0</b> .
Туре	The data type of the column. Can be a <b>Text</b> , <b>Numeric</b> , or <b>Time</b>
Date Format	The <u>format</u> when the data type is Time.
Enabled	Determines whether the message should be processed.

To delete a column, check its or all the column entries, check the topmost, then click.


- 6. Select the Simulation Type:
  - Record

Sends the number of records for each interval of time. By default, records are sent in the same order of the source.



This simulation type allows the specification of the following:


Sort Order



When you select the **Use file sort order**, it will use the default sorting order of the file.

When you either select **Ascending** or **Descending** as the Sort Order, this enables the *Sorted by Column* drop down list.

Select the column that will be used for the sorting.



Playback Set Size

The number of records set to be updated during simulate/playback.

Start Up Set Size


The number of records set to be published initially (on start-up).

Playback Interval (ms)

The update interval period for the record-based playback. Default is 1000 (ms).

Time

Simulates records as they occur in real-time.



This simulation type allows the specification of the following:

Playback Column

The playback column which is a Date/Time type.

Playback Speed

A multiplier which to either speed up or slow down the playback. Default is 1.

- o If 0 < value < 1 slow down</p>
- If value = 1 records will be published as they occur
- o if value > 1 speed up

NOTE

For time-based simulation, if the Date/Time column have improper dates, it will fail and stop.

- 7. Select the **Loop** check box to enable looping through the file.
- 8. Define the Real-time Settings.
- 9. Modify the Real-time Limit to vary the data throttling. This defaults to 1000 milliseconds.
- 10. Click . The new data source is added in the Data Sources list.

# **Creating StreamBase Input Data Source**


The StreamBase 7.1 connector allows connection to the StreamBase CEP engine instance on a real-time streaming basis.

To use the StreamBase connector, Streambase 7.1 redistributable must be installed.

Refer to  $\label{lem:model} $$ $ Refer to $$ http://www.streambase.com/products/streambasecep/download-streambase/ for more information in downloading StreamBase products.$ 

### Steps:

1. In the New Data Source page, select Input > StreamBase 7.1 in the Connector drop-down list.



2. Enter the following properties:

Save

Property	Description
Primary URL	Primary URL of the StreamBase 7.1. Default is sb://localhost:100000.
Secondary URL	Secondary URL of the StreamBase 7.1.  NOTE: More than two StreamBase server URLs can be specified by comma separation.
User Id	User Id that will be used to connect to StreamBase 7.1.
Password	Password that will be used to connect to StreamBase 7.1.

3. Click Fetch Streams to return a list of updated streams. Selection of a stream returns a list of available Id columns for the stream.

This populates the *Id Column* with the set of columns from the schema of type sym and the text array such as Character/Boolean/GUID, etc. The selected *Id Column* can be used to select a key column to manage data updates and inserts.

**NOTE:** Every message definition needs a text column to be defined as the *Id column*. By default, only the latest data will be loaded into memory.

Furthermore, a streaming time series window can be generated by creating a compound key with the Id Column, plus a separately specified *Time Id* column. This *Time Id* column can be from the source dataset, or alternatively automatically generated.

If the *Time Id* column is selected, then a scrolling time window can be specified.


Time Id Column	[Automatic Time Id] ▼
Time Id Column Name	Automatic_Timestamp_Column

For Automatic Time Id, define the Time Id Column Name.

As new data arrives from the subscription, new time slices will automatically be added, and old ones will be deleted.

If a new ID is received, a new row is added to the in-memory data set representing the StreamBase topic subscription. While if an existing ID is received, an existing row is updated.

- 4. Enter the *Predicate* expression to force emission.
- 5. The time zone of input parameters and output data is by default unchanged. Changing the time zone is supported through the *Show in Timezone* list box, based on the assumption that data is stored in UTC time and outputs are presented in the selected time zone.
- 6. Select whether the parameters should be automatically enclosed in quotes, by selecting the **Enclose** parameters in quotes box.
- 7. Select the **Reset Data on Reconnect** check box to flush out the stale data and reload data after reconnection.



# **Creating StreamBase LiveView Input Data Source**


The StreamBase LiveView connector allows connection to the StreamBase LiveView instance on a real-time streaming basis.

NOTE

Supported Java versions must be earlier than 255. For example, if you are using JDK or JRE, it should be less than 1.8.0\_255.

### Steps:

1. In the New Data Source page, select Input > StreamBase LiveView in the Connector drop-down list.



2. Enter the following properties:

Property	Description
Primary URL	Primary URL of the StreamBase LiveView.
User Id	User Id that will be used to connect to StreamBase LiveView.
Password	Password that will be used to connect to StreamBase LiveView.

3. You can either:

select the **Table** radio button then click



to return a list of updated Tables.

Select the required table.

By default, the whole table will be subscribed against. To subscribe against a subset, enter a predicate.

The  ${\tt IN}\,$  syntax is recommended for use of parameters to support multiple values. The square bracket notation should be used for the  ${\tt IN}\,$  clause.

Example: color IN [{color}]





- 4. The time zone of input parameters and output data is by default unchanged. Changing the time zone is supported through the *Show in Timezone* list box, based on the assumption that data is stored in UTC time and outputs are presented in the selected time zone.
- 5. Enter the ID Column Name.

LiveView supplies a unique Id for each row. This Id field is by default given a title of **Key**.

Id Column Name Key

Furthermore, a streaming time series window can be generated by creating a compound key with the *Id Column*, plus a separately specified *Time Id* column. This *Time Id* column can be from the source dataset, or alternatively automatically generated.

If the *Time Id* column is selected, then a scrolling time window can be specified.



For Automatic Time Id, define the Time Id Column Name.

As new data arrives from the subscription, new time slices will automatically be added, and old ones will be deleted.

If a new Id is received, a new row is added to the in-memory data set representing the StreamBase LiveView topic subscription. While if an existing ID is received, an existing row is updated.


- 6. Select the **Reset Data on Reconnect** check box to flush out the stale data and reload data after reconnection.
- 7. Click . The new data source is added in the *Data Sources* list.

## **Creating Text Input Data Source**


The Text connector allows the retrieval and processing of delimited Text files (such as CSV, TSV, and so on), either from a disk or from a defined URL.

### Steps:

1. In the New Data Source page, select Input > Text in the Connector drop-down list.



2. Select the Text File Source.



The standard settings controlling how the text file is parsed are listed.

These include:

Property	Description
Skip First N Rows	Specifies the number of rows that will be skipped.
Data Type Discovery	Specifies how many rows from the text file should be used when automatically determining the data types of the resulting columns.
Decimal Separator	Select either the dot (.) or comma (,) as the decimal separator.
File Encoding	Set the character encoding to use in text data.

	<ul> <li>UTF-8</li> <li>UTF-16</li> <li>UTF-32</li> <li>US-ASCII</li> <li>Windows-1252</li> </ul>
Text Qualifier	Specifies if fields are enclosed by text qualifiers, and if present, to ignore any column delimiters within these text qualifiers.  Can be any of the following options:  None Single Quote Double Quote
Column Delimiter	Specifies the column delimiter to be used when parsing the text file.
First Row Headings	Determines if the first row should specify the retrieved column headings, and not be used in data discovery.

3. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the Save button is enabled.

By default, all the generated columns are enabled. You can uncheck the **Select All** box, then check the boxes of the columns that will be enabled.

- 4. You can also opt to load or save a copy of the column definition.
- 5. You can opt to click \*\* . A new column entry displays. Enter or select the following properties:

Property	Description
Name	The column name of the source schema.
Column Index	The column index controls the position of a column. Must be >= 0.
Туре	The data type of the column. Can be a <b>Text</b> , <b>Numeric</b> , or <b>Time</b>
Date Format	The <u>format</u> when the data type is <b>Time</b> .
Enabled	Determines whether the message should be processed.


To delete a column, check its or all the column entries, check the topmost , then click.

# **Creating WebSocket Input Data Source**

The WebSocket connector is very similar to the Stream Simulator connector, except that rather than looping through a file, it would either connect through web sockets, long polling, or repeatedly poll an external URL for new records to process.

Steps:

1. In the New Data Source page, select Input > WebSocket in the Connector drop-down list.



2. Enter the connection details:

Property	Description
Path	The path to which the WebSocket server will respond to.
Proxy Server URI	he HTTP Proxy setting that will allow the WebSocket connector to reach the endpoint
User ID	The User ID that will be used to connect to the WebSocket server.
Password	The password that will be used to connect to the WebSocket server.  Select the <b>Show Characters</b> check box to display the entered characters.
Request Body	For both the HTTP and ws:// POST requests sent to the WebSocket server.
Timeout	The length of time to wait for the server response (10 to 300). Default is <b>10</b> .

- 3. Select the Message Type.
- 4. Select either the period (.) or comma (,) as the Decimal Separator.

**NOTE** 

Prepend 'default:' for the elements falling under default namespace.

- 5. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the Save button is enabled.
- 6. You can also opt to load or save a copy of the column definition.
- 7. You can opt to click to add columns to the WebSocket connection that represent sections of the message.

  Then enter or select:

Property	Description
Name	The column name of the source schema.
JsonPath/Text Column Index/XPath	The JsonPath/Text Column Index/XPath of the source schema.
Туре	The data type of the column. Can be a <b>Text</b> , <b>Numeric</b> , or <b>Time</b>
Date Format	The format when the data type is <b>Time</b> .
Filter	Defined parameters that can be used as filter.
Enabled	Determines whether the message field should be processed.

**NOTE** 

To parse and format times with higher than millisecond precision, the format string needs to end with a period followed by sequence of upper case S. There can be no additional characters following them.

For example: yyyy-MM-dd HH:mm:ss.SSSSSS


- 8. Define the Real-time Settings.
- 9. Click Save . The new data source is added in the Data Sources list.

# **Creating Web Data Input Data Source**

The Web Data connector allows the retrieval and processing of JSON, XML, delimited Text (such as CSV, TSV), Excel files, HTML tables and Arrow IPC files that are accessible over HTTP/HTTPS.

### Steps:

1. In the New Data Source page, select Input > Web Data in the Connector drop-down list.




2. Select the appropriate *HTTP Method* for the request from the following options:

HTTP Method	Description
GET	To retrieve data.
POST	To add new data.
PUT	To replace existing data


3. Enter the absolute URL of the web data including scheme (HTTP/HTTPS) into the URL field.



- 4. Click Test Connection and Update Settings . A successful connection will result to the following:
  - The Connection Successful status is displayed along with some raw data returned by the server.



The connector tries auto discovery of the <u>Data Type</u> (JSON, Text, XML, Excel, HTML, Arrow IPC)
 When loading JSON data, the *Record Path* can be suggested automatically by pressing the **Fetch** button.



For the Web Data connector, you can also select the **HTML** data type.



Property	Description
Table Name	Click Fetch to fetch HTML table elements then select the HTML table.

Header Rows

Select the number of rows in the table to be retrieved as column headings.

The default value is 1, but a higher number should be set if the HTML table has column titles that use more than 1 row. If all rows of the table are data and there are no column headers, set it to 0.

NOTE


If no table element is found in the HTML document, an error message displays.


You can also opt to load or save a copy of the column definition.

- 5. Adjust the Authentication Type, if required.
  - 5.1 Select the Authorization tab.



### 5.2. Set the required settings:





Enter or select the following settings:


- Token URL The URL to retrieve the access token from.
- Add Access Token To The Access token retrieved from the Token URL
  can be added to headers, URL or request body, depending on how the
  endpoint needs the token.

Request Headers Request Url Request Body

- Request Headers A header is automatically added to the REST API request.
- Request URL The URL needs to be manually parameterised with a {access\_token} parameter, before calling the REST API, the parameter is replaced with the actual token.
- Request Body The Request Body needs to be manually parameterised with a {access\_token} parameter, before calling the REST API, the parameter is replaced with the actual token.

### NOTE:


The given request parameters key/value pairs are formatted by the connector as **application/xwww-form-urlencoded**, and posted to *Token URL*.



6. The **Headers** tab allows you to enter any custom headers required to be passed to the URL endpoint, typically to provide additional metadata. Enter any key/value pairs you need, and the connector will send them along with request.



- 7. Set the Body if a POST/PUT request is required.
  - 1.1. Select the **Body** tab.



7.2. Set the required settings:

Property	Description
Content Type	Select or enter content-type based on request body (payload) format.  NOTE: This property is disabled when the HTTP Method is GET.
Request Body	The Request Body for the HTTP POST method.

- 8. Set the Advanced settings, if needed.
  - 8.1. Select the **Advanced** tab.



8.2. Set the required settings:

Property	Description
Proxy Server URI	The HTTP Proxy setting that will allow the connector to reach the endpoint.
Content Encoding	Select the <i>Content Encoding</i> with the HTTP Header: <b>None</b> , <b>GZip</b> , <b>Deflate</b> , or <b>GZip</b> and <b>Deflate</b>
Timeout	The length of time to wait for the server response (10 to 300). Default is <b>10</b> .
Decimal Separator	Select either the dot (.) or comma (,) as the decimal separator.
File Encoding	Set the character encoding to use in text data.  UTF-8  UTF-16  UTF-32  US-ASCII  Windows-1252




. The new data source is added to the Data Sources list.

# **Creating XML Input Data Source**

The XML connector allows the retrieval and processing of XML files, either from a disk, a Text, or from a defined URL.

### Steps:

1. In the New Data Source page, select Input > XmI in the Connector drop-down list.



- 2. Select the XML File Source.
- 3. Enter the Record XPath (e.g., //myroot/items/item).
- 4. Select either the period (.) or comma (,) as the Decimal Separator.
- 5. Click to the fetch the schema based on the connection details. Consequently, the list of columns with the data type found from inspecting the first 'n' rows of the input data source is populated and the Save button is enabled.
- 6. You can also opt to load or save a copy of the column definition.
- 7. You can opt to click . A new column entry displays. Enter or select the following properties:

Property	Description
Name	The column name of the source schema.
XPath	The XPath of the source schema.
Туре	The data type of the column. Can be a <b>Text, Numeric,</b> or <b>Time</b>
Date Format	The <u>format</u> when the data type is <b>Time</b> .
Enabled	Determines whether the message should be processed.
To delete a column, check its or all the column entries, check the topmost , then click .	


8. Click . The new data source is added in the *Data Sources* list.

# **MODIFYING DATA SOURCES**

### Steps:

1. On the **Data Sources** tab, click the link of a data source you want to modify.

The corresponding data source page is displayed.



All of the controls that are editable can be modified.

2. Make the necessary changes then click saving options:



icon. The context menu displays with two

■ Save

Click to save the changes made in the data source.

Save As Copy...

Click to make a duplicate of the data source. The original name is appended with \_Copy.


To change the Data Source Name, click on it to make it editable, then enter a new one and click ...

# [10] MANAGING DATA PRODUCERS


When an application has been started, the data producers used to generate data from the data sources will be displayed on the **Data Producer** tab where you can:

Refresh data producers

Start or Stop data producers



Data Producer tab. Initially, no records are displayed when there are no running applications or the applications that are running have no data producers



Data Producer tab with data producers currently started

#### **Refresh Data Producers**

#### Steps:

- On the **Data Producers** tab, click the Refresh icon of a data producer.
   A confirmation message displays.
- 2. Click Yes

## **Starting or Stopping Data Producers**

To start a Data Producer:


- 1. Click . A confirmation message displays.
- 2. Click **Yes**. The icon changes to .

To stop the Data Producer:


- 1. Click . A confirmation message displays.
- 2. Click **Yes**. The icon changes to

# [11] MONITORING ENGINE METRICS AND APPLICATION TOPICS

The **Monitoring** tab provides the ability to monitor the engine metrics that can help determine which part of the application is causing data bottlenecks, among others.




Engine Metric	Description
Free Physical Memory	The amount of free physical memory available to the Panopticon Streams server.
Total Physical Memory	The total amount of physical memory.
Total JVM CPU Usage	The recent CPU usage for the Java Virtual Machine process.



Monitoring tab when disconnected to the engine

It also displays the list of input and output topics currently running.



Monitoring tab when the engine has been started along with some applications. The list of input and output topics is displayed.

## **MANAGING TOPICS**

While running or executing an application, input and output topics are retrieved and displayed on the Monitoring tab.

You can perform the following:

- □ View and monitor the number of retrieved messages and the number of retrieved messages per second
- □ Define a <u>filter</u> among the topics
- □ Sort the list of topics

## **Filter Topics**

The topics can be filtered by entering letters, numbers, or underscores in the *Topic* or *Application* text box.

For the *Type* of application, enter a text (either **Output** or **Input**) into the text box above the listing.

#### **Sorting the List of Topics**

Modify the sorting of the list by clicking the or button of the *Topic*, *Type*, *Application*, #Messages, or #Messages/sec column. The icon beside the column that was used for the sorting will indicate if it was in an ascending or descending order.


#### **Moving to Other Topics List Pages**



- any link of a page number
- This displays the previous page
- . This displays the next page

# [12] MANAGING PARAMETERS

The **Parameters** tab supports adding, modifying, and deleting global parameters that will pull and enter specific data into the different components of an application model.




# **ADDING PARAMETERS**

#### Steps:


1. On the Parameters tab, click



A new parameter entry displays.



- 2. Enter a Name for the new parameter and the Value.
- 3. Select the *Encrypted* check box to encrypt the value.
- 4. Click . The new parameter is added in the list.




New parameters are added in the Parameters.json file located in the AppData folder (i.e., c:\streamsseverdata).

## **Modifying Parameters**

#### Steps:

1. On the **Parameters** tab, click the **Edit** icon of a parameter you want to modify.



1. Make the necessary changes then click ...

#### **Deleting Parameters**

#### Steps:


1. On the **Parameters** tab, click  $\stackrel{\frown}{\mathbb{I}}$  of a parameter you want to delete.

A confirmation message displays.



2. Click Yes to delete.

#### **Refresh Parameters**



### **Sorting the List of Parameters**

By default, the parameters are listed based on the sequence that they were added. Modify the sorting of the list by clicking the or button of the *Name, Value,* or *Encrypted* columns. The icon beside the column that was used for the sorting will indicate if it was in an ascending or descending order.

# [13] EXAMPLE APPLICATIONS

Panopticon Streams is installed with a series of example applications: AggregationExample - Demonstrates how to aggregate data based on a grouping key and a set of aggregated Includes simple aggregations such as avg, count, first, last, max, min, samples, sum, sdevp, sdevs, Sum, varp, and vars. BranchExample – Demonstrates how to split a stream into one or more branches. CalculateRemoveReplaceNull – Demonstrates how to: remove and replace fields from output schemas set a field value to null set a field value to the current timestamp CalculationExample – Includes the SquareRoot calculation. CalculationsExample – Includes the following calculations: Numeric calculations such as Abs, SquareRoot, Subtract, Multiply, Divide, Truncate, IF Text calculations such as Upper, Lower, Proper, Left, Right, Mid, Concat, Find Time Period calculations such as DateDiff In addition, data type casting between Text, Number, and Date/Time ConflateExample – Demonstrates how to lower the frequency of updates by setting a fixed interval. EmailExample - Shows how to send an email via SMTP where the SMPT and email settings can be parameterized. Each record passed to the connector results in an email which can be primarily used as an output for alerting, having a conditional expression that would need to be fulfilled for a record to be forwarded to the output. Requires the EmailWriter plugin. ExternalInputExample - Demonstrates how to directly source data from a Kafka topic (defined in the schema registry with the message format set to Avro). ExternalInputJsonParserExample - Demonstrates how to directly use a parsed input Json data. ExternalInputXMLParserExample - Demonstrates how to directly use a parsed input XML data. FilterExample – Demonstrates how to filter a data source based on a predicate. InfluxDBExample - Allows periodical dumping of records from a Kafka topic into an InfluxDB 1.x output connector. Requires the InfluxDBWriter plugin. JDBCExample - Allows periodical dumping of records from a Kafka topic into a JDBC database output connector. Requires the JDBCWriter plugin. JoinExample – Demonstrates how to join a stream to a global table. KdbExample - Allows periodical dumping of records from a Kafka topic into a Kx kdb+ output connector. Requires the KdbWriter plugin. MetronomeExample – Demonstrates how the metronome operator works in generating a timestamp field schema. A static metronome has a defined frequency while a dynamic metronome takes frequency as an input which determines the speed of the simulation. RetentionTimeExample - Demonstrates how to define the different retention time periods set for tables, input streams, output streams, and topics in an application.

This helps minimize memory utilization and the amount of data retrieved when subscribing from the beginning to the latest messages.

**NOTE** 

Setting these properties in the application level overrides the defaults set in the Streams.properties file.

For example, if the following properties are defined in the streams.properties file:

```
cep.kafka.table.retention.ms=86400000
cep.kafka.input.retention.ms=60000
cep.kafka.output.retention.ms=900000
```


In the application level, the input retention period will be 1,000 milliseconds instead of 60,000 and the output retention period will be 1,000 milliseconds instead of 900,000. Also, a custom topic retention period has been added using the following pattern: TopicName.retention.ms (i.e., TimeSeries.retention.ms).

```
properties>
   <!-- Keep tables alive one day -->
   <entry>
       <key>table.retention.ms</key>
       <value>86400000
   </entry>
   <!-- Keep input and output streams for 1 second -->
       <key>input.retention.ms</key>
       <value>1000</value>
   </entry>
   <entry>
       <key>output.retention.ms</key>
       <value>1000</value>
   </entry>
   <!-- Custom retention time for InputStream topic -->
       <key>TimeSeries.retention.ms</key>
       <value>1111
   </entry>
</properties>
```

- StockMarketSimulator Shows a stock market simulation using a streaming data with join, calculations, and metronome operators.
- StockStaticTimeSeriesApp Joins a static and a time series data sources using common keys. Also demonstrates adding a sum aggregation.
- □ StreamtoGlobalTableJoinExample Joins stream and global table inputs using common keys.
- StreamToTableJoinExample Joins stream and table inputs using common keys.
- □ TextExample Allows periodical dumping of records from a stream Kafka topic into a Text connector. Requires the TextWriter plugin.
- UnionExample- Unioning of two streams.
- □ WindowedStreamExample Demonstrates aggregation across a windowed stream.

# [14] PANOPTICON RESOURCES

Clicking on the top right section of the toolbar displays the available Panopticon online resources.



Select the Language on the drop-down list: English or Japanese.



Then click *Panopticon Streams Reference Guide* either on a PDF or HTML Help format. This guide is also available upon installation.

# [APPENDIX]

## **PROPERTIES: STREAMS**

The majority of configuration options for the server are set in the Streams.properties file in the <appdata> directory (e.g., C:\streamsserverdata\). If this file does not exist when the server starts, it will create it with all default values. When the server starts after an upgrade, it may add new properties and remove deprecated ones.

You can optionally move sensitive properties like passwords and URLs from this file, where they are stored in clear text, into a file named Secret.properties in the same directory. The Secret.properties file stores values encrypted, and you can manage it with <a href="PCLI">PCLI</a>. A property can only be defined in one of these files at a time.

The following properties can be set in the property files:

С	
Property	Access
Attribute	access.administrator.groups
Description	The role that is mapped to the administrator group.
Default Value	admin
Property	Access
Attribute	access.administrator.users
Description	Normally administrator access should be handled with the access.adminstrator.groups mapping, but for scenarios where the authentication cannot provide roles or you want to make exceptions for specific users, you can list individual usernames in this property.  Any user listed here will get administrator access, regardless of their roles. Separate multiple users with the access.list.delimiter.
Default Value	manple assis with the access, 1150, actimized.
Property	Access
Attribute	access.default.roles
Description	The default roles applied to all users of the server.  For example, if access.default.roles=DESIGNER,ADMINISTRATOR and a user with a VIEWER role logs on to the server, then the user will simultaneously have a VIEWER, DESIGNER, and ADMINISTRATOR roles.  However, if no default roles are wanted, then leave the property blank.  NOTE: The roles that can be assigned in this property can only be ADMINISTRATOR, VIEWER, ANONYMOUS, and/or DESIGNER. This property is case sensitive.
Default Value	VIEWER
Property	Access
Attribute	access.designer.groups
Description	The role that is mapped to the designer group.

Default Value	designer
Property	Access
Attribute	access.designer.users
Description	Normally designer access should be handled with the access.designer.groups mapping, but for scenarios where the authentication cannot provide roles or you want to make exceptions for specific users, you can list individual usernames in this property.  Any user listed here will get designer access, regardless of their roles.  Separate multiple users with the access.list.delimiter.
Default Value	
Property	Access
Attribute	access.viewer.groups
Description	The role that is assigned to the viewer group.  NOTE: Currently not in use. Development ongoing.
Default Value	
Property	Access
Attribute	access.viewer.users
Description	Normally viewer access should be handled with the access.viewer.groups mapping, but for scenarios where the authentication cannot provide roles or you want to make exceptions for specific users, you can list individual usernames in this property.  Any user listed here will get viewer access, regardless of their roles.  Separate multiple users with the access.list.delimiter.
Default Value	
Property	Access
Attribute	access.list.delimiter
Description	The value delimiter to use when parsing access groups.  Examples:  access.list.delimiter=,  access.administrator.groups=group1,group2  The groups are mapped to {'group1', 'group2'}  access.list.delimiter=,  access.administrator.groups=group1;group2,group3  The groups are mapped to {'group1;group2', 'group3'}  access.list.delimiter=;  access.list.delimiter=;  access.administrator.groups=group1;group2,group3

	The groups are mapped to {'group1', 'group2,group3'}
Default Value	',' (comma)
	Authentication: Header
Property	
Attribute	authentication.header.role.delimiter
Description	The delimiter used to separate the roles. Example: role1, role2,role3
Default Value	, (Comma)
Property	Authentication: Header
Attribute	authentication.header.roles
Description	The name of the header that contains all the roles.
Default Value	
Property	Authentication: Header
Attribute	authentication.header.rolesdynamic
Description	Supports the ability to create dynamic roles using free form patterns or string replacement.  To create dynamic roles, use '{header value to be used}'.  Example: authentication.header.rolesdynamic={HEADER_ROLES},financials,role_for_compal_{HEADER_COMPANY}}  Given this table:  KEY VALUE HEADER_ROLES designer, watcher HEADER_COMPANY industrials, consumers  Then the roles to create the authentication token will be the following:  designer watcher financials
	<ul><li>role_for_company_industrials</li><li>role_for_company_consumers</li></ul>
Default Value	- Toto_tot_company_consumers
Property	Authentication: Header
Attribute	authentication.header.username
Description	The name of the header that contains the username
Pescubiion	THE HATTE OF THE HEAVET THAT CONTRAINS THE USEFHAME
Default Value	
Default Value	Authorization: Hooder
Property Attribute	Authentication: Header authentication.header.validate.token

Description	If set to <b>true</b> , the authentication will validate the token. If set to <b>false</b> , the authentication of every request will be based on headers.
Default Value	
Property	Authentication: Logout
Attribute	authentication.logout.redirect.url
Description	Takes a URL as a parameter. Clicking the logout button redirects the user to the specified URL.  If this property is not set, user will be returned to the start page of Panopticon.
Default Value	
Property	Authentication: OAuth 2.0
Attribute	authentication.oauth2.client.ID
Description	The ID of the OAuth 2.0 client.
Default Value	
Property	Authentication: OAuth 2.0
Attribute	authentication.oauth2.client.secret
Description	The secret used by the OAuth 2.0 client.
Default Value	
Property	Authentication: OAuth 2.0
Attribute	authentication.oauth2.identity.attribute.roles
Description	The attribute that will be extracted from the identity response and used as the role. There can be multiple assigned roles for a user.
Default Value	
Property	Authentication: OAuth 2.0
Attribute	authentication.oauth2.identity.attribute.roles.pattern
Description	Takes regex used to extract the roles from the OAuth 2.0 server identity response.  For example, the returned string:  cn=admin, ou=groups, dc=openam, dc=openidentityplatform, dc=org, cn= designer, ou=groups, dc=openam, dc=openidentityplatform, dc=org  contains two roles, admin and designer  The regex to extract the roles is cn=([^,]+).
Default Value	
Property	Authentication: OAuth 2.0
Attribute	authentication.oauth2.identity.attribute.username
Description	The attribute that will be extracted from the identity response and used as the username.
Default Value	
Property	Authentication: OAuth 2.0

Attribute	authentication.oauth2.identity.method
Description	The method on how the access token is passed along in the identity request. Supported values are <b>QUERY</b> , <b>BODY</b> , and <b>HEADER</b> .
Default Value	QUERY
Property	Authentication: OAuth 2.0
Attribute	authentication.oauth2.identity.url
Description	The URL to the REST service that provides details about the authenticated user.
Default Value	
Property	Authentication: OAuth 2.0
Attribute	authentication.oauth2.login.callback.url
Description	The callback URL. The URL should be the same as one of the specified callback URLs used by the client. The URL should refer to Panopticon Streams.
Default Value	
Property	Authentication: OAuth 2.0
Attribute	authentication.oauth2.login.redirect.url
Description	Redirects the user to the specified URL after successfully logging in. This property can be left blank, in which case the user is redirected to the URL they requested to access.
Default Value	
Property	Authentication: OAuth 2.0
Attribute	authentication.oauth2.login.response.type
Description	The response type. The only response type that is currently supported is <b>CODE</b> . The value can also be left blank.
Default Value	
Property	Authentication: OAuth 2.0
Attribute	authentication.oauth2.login.scope
Description	The requested scope. The field can be left blank.
Default Value	
Property	Authentication: OAuth 2.0
Attribute	authentication.oauth2.login.url
Description	The URL to the OAuth 2.0 login resource.
Default Value	
Property	Authentication: OAuth 2.0
Attribute	authentication.oauth2.logout.redirect.url
Description	Logging out revokes the token from the authentication server if the property authentication.oauth2.logout.url is set to the revocation URL. If this property is not set, the server will only remove its own token.

	If none of these properties are set, the server will attempt to redirect to the start page of Panopticon when logging out.
Default Value	
Property	Authentication: OAuth 2.0
Attribute	authentication.oauth2.logout.url
Description	The URL to the OAuth 2.0 logout resource. This field can be left blank.
Default Value	
Property	Authentication: OAuth 2.0
Attribute	authentication.oauth2.token.method
Description	The method on how the token should be retrieved. Supported values are <b>QUERY</b> , <b>BODY</b> , and <b>HEADER</b> .
Default Value	
Property	Authentication: OAuth 2.0
Attribute	authentication.oauth2.token.url
Description	The URL to the OAuth 2.0 token resource.
Default Value	
Property	Service authentication level
Attribute	authentication.role
Description	The authentication role.
Default Value	
Property	Service authentication level
Attribute	authentication.required
Description	The property that will make the authentication required. It will force the user to login in order to use any of the services provided by the server.
Default Value	true
Property	Authentication: SAML
Attribute	authentication.saml.serviceprovider.id
Description	The ID of the service provider configured in the IdP.
Default Value	
Property	Authentication: SAML
Attribute	authentication.saml.assertionconsumerservice.url
Description	The URL to the Panopticon assertion consumer service. URL: [Protocol]://[Host]:[Port]/[Context]/server/rest/auth/login
Default Value	
Property	Authentication: SAML
Attribute	authentication.saml.identityprovider.url

Description	The URL to the IdP login service.
Default Value	The ONE to the full login sorvice.
20.00.00	Authentication: SAML
Property	
Attribute	authentication.saml.assertion.username
Description	User attribute for username configured in the IdP.
Default Value	
Property	Authentication: SAML
Attribute	authentication.saml.assertion.roles
Description	User attribute for roles configured in the IdP.
Default Value	
Property	Authentication: SAML
Attribute	authentication.saml.certificate.name
Description	The name of the certificate used to validate signature and/or sign outgoing SAML messages
Default Value	
Property	Authentication: SAML
Attribute	authentication.saml.certificate.password
Description	The password of the certificate used to validate signature and/or sign outgoing SAML messages.
Default Value	
Property	Authentication: SAML
Attribute	authentication.saml.challenge.required
Description	This property determines whether the IdP-first authentication with SAML is enabled or not. To enable, set this property to <b>false</b> .
Default Value	true
Property	Authentication: SAML
Attribute	authentication.saml.identityprovider.logout.url
Description	The URL to the IdP logout service.
Default Value	
Property	Authentication: SAML
Attribute	authentication.saml.keystore.file
Description	The location of the Keystore file that contains the certificate.
Default Value	
Property	Authentication: SAML
Attribute	authentication.saml.keystore.password

Description	The password to the Keystore file.
Default Value	
Property	Authentication: SAML
Attribute	authentication.saml.identityprovider.certificate.file
Description	Takes a file path to a certificate file that contains the IdP's public key.
Default Value	
Property	Authentication: SAML
Attribute	authentication.saml.identityprovider.signature.validation .required
Description	Specifies whether to require a valid IdP signature to be present on the SAML response. Default value is <b>false</b> .
Default Value	false
Property	Authentication: SAML
Attribute	authentication.saml.provider
Description	The IdP provider. Possible values are <b>OPENSAML</b> , <b>OPENAM</b> .
Default Value	OPENSAML
Property	Authentication: SAML
Attribute	authentication.saml.keystore.type
Description	The key store type. Possible values are <b>JKS</b> , <b>JCEKS</b> , <b>PKCS12</b> .
Default Value	JKS
Property	Authentication: SAML
Attribute	authentication.saml.login.redirect.url
Description	Redirects the user to the specified URL after successfully logging in. This property can be left blank, in which case the user is redirected to the URL they requested to access.
Default Value	
Property	Authentication: SAML
Attribute	authentication.saml.logout.redirect.url
Description	Redirects the user back to the specified URL after logging out. This is mainly used with a proxy. In which case, Panopticon Real Time does not know the endpoint which the user is going towards to, and therefore cannot redirect the user back to the Overview page. If you are using OpenAM this is required, otherwise this property can be left blank.
Default Value	
Property	Authentication: SAML
Attribute	authentication.saml.openam.meta.alias
Description	The meta alias for the IdP if you are using OpenAM.

Default Value	
Property	Authentication: SAML
Attribute	authentication.saml.protocolbinding
Description	Protocol binding for the use of SAML authentication. Possible values are <b>HTTP-Redirect</b> , <b>HTTP-POST</b> , <b>HTTP-Artifact</b> , <b>HTTP-POST-SimpleSign</b> , or <b>SOAP</b> .
Default Value	HTTP-Redirect
Property	Service authentication login request
Attribute	authentication.timeout.callback
Description	The timeout (in milliseconds) for the user between initiated login and callback. The default value is five minutes.
Default Value	300000
Property	Authentication: Token
Attribute	authentication.token.cookie
Description	Used when sticky load balancer is using cookies.
Default Value	stoken
Property	Authentication: Token
Attribute	authentication.token.domain
Description	The domain in which the token cookie should be registered under.
Default Value	
Property	Authentication: Token
Attribute	authentication.token.persistence
Description	This property is used to determine if the token should persist if the browser is closed or if it should only last while the browser is open. There are two possible values: PERSISTENT and SESSION. PERSISTENT will persist the token in the browser even if the browser has been closed and reopened. SESSION will remove the token from the browser if it is shutdown.  IMPORTANT:  After modifying the property value to SESSION, ensure to clear the AppData/Token folder before starting the server.
Default Value	PERSISTENT
Property	Authentication: Token
Attribute	authentication.token.refreshable
Description	This property determines if the token can refresh itself. The web client can identify if the token is about to expire and then request a new token with the existing token. A token is refreshable if the property is set to true. The token will expire and invalidate the user session if the property is set to false.
Default Value	true
Property	Authentication: Token
Attribute	authentication.token.secret

Description	The secret is used to sign the token. The secret will be auto-generated when the server starts for the first time.  NOTE: This value should be kept a secret.
Default Value	Auto-generated
Property	Authentication: Token
Attribute	authentication.token.validity.seconds
Description	The number of seconds that the token should be valid.
Default Value	604800
Property	Authentication
Attribute	authentication.type
Description	The type of the authentication mechanism that will be used on Panopticon Streams.
Default Value	BASIC
Property	Cache
Attribute	cache.plugin.ID
Description	The ID of the cache plugin that will be used. Possible value: BinaryTableFile-Cache
Default Value	BinaryTableFile-Cache
Property	Cache
Attribute	cache.purge.condition
Description	The condition for determining when the cache should be purged or cleared.  Possible values: <b>NONE</b> , <b>MEMORY</b> .
Default Value	MEMORY
Property	Cache
Attribute	cache.purge.condition.memory.threshold
Description	The memory threshold used to determine if the cache should be purged or not. The values are presented in percent, 0-100. 80 means that the cache will be purged if the memory consumption reaches 80 % or more.
Default Value	80
Property	Cache
Attribute	cache.purge.enabled
Description	Enable or disable the purge functionality. Possible values: true, false
Default Value	true
Property	Cache
Attribute	cache.schedule.clear.enabled
Description	Enable the cache clearing schedule. This is scheduling the clear cache operation which will remove all the expired cache entries.
Default Value	true

Property	CEP: Application
Attribute	cep.application.autostart
Description	Determines whether all of the stored applications in the Streams server should auto start when the Streams server starts.
Default Value	false
Property	CEP: Application
Attribute	cep.kafka.application.state.path
Description	Where the tmp folder of Panopticon Streams data are created.
Default Value	C:/PanopticonStreams/Data/tmp/kafka-streams
Property	CEP: Kafka
Attribute	cep.kafka.connection.timeout
Description	The connection timeout towards Kafka. The value is presented in milliseconds.
Default Value	10000
Property	CEP: Kafka
Attribute	cep.kafka.input.retention.ms
Description	Specifies the retention period of input streams.
Default Value	60000
Property	CEP Kafka
Attribute	cep.kafka.monitoring.consumer.interceptor
Description	Names of classes that will be used to monitor data consumed from topics in a Streams application. In addition, these are hooks that will allow an external application to inspect this traffic.  NOTE: The default value enables the Confluent Control Center to show metrics for a
	Streams application.
Default Value	io.confluent.monitoring.clients.interceptor.MonitoringConsumerInterceptor
Property	CEP Kafka
Attribute	cep.kafka.monitoring.producer.interceptor
Description	Names of classes that will be used to monitor data produced to topics in a Streams application. In addition, these are hooks that will allow an external application to inspect this traffic.
	<b>NOTE:</b> The default value enables the Confluent Control Center to show metrics for a Streams application.
Default Value	io. confluent. monitoring. clients. interceptor. Monitoring Producer Interceptor
Property	CEP: Kafka
Attribute	cep.kafka.output.retention.ms
Description	Specifies the retention period of output streams.
Default Value	900000
Property	CEP: Kafka

Attribute	cep.kafka.properties						
Description	The user-defined file that contains the properties for controlling the Kafka configurations in Panopticon Streams.						
Default Value	kafka.properties						
Property	CEP: Kafka						
Attribute	cep.kafka.schemaregistry.url						
Description	The URL to the Schema Registry.						
Default Value	http://localhost:8081						
Property	CEP: Kafka						
Attribute	cep.kafka.servers						
Description	The URL to all the Kafka servers.						
Default Value	localhost:9092						
Property	CEP: Kafka						
Attribute	cep.kafka.session.timeout						
Description	The timeout for the Kafka session. The value is presented in milliseconds.						
Default Value	15000						
Property	CEP: Kafka						
Attribute	cep.kafka.table.retention.ms						
Description	Specifies the retention period for tables.						
Default Value	86400000						
Property	CEP: Kafka						
Attribute	cep.kafka.topic.partitions						
Description	Propagates the server-wide default for topic partitions.  NOTES:						
	• The <i>Partition Count</i> priority is applied in the following sequence (top to bottom):						
	1. Topic level						
	2. Application level						
	<ul> <li>Property level</li> <li>The event processor create topic gets the partition count for that topic.</li> </ul>						
	If the topic exists, it checks for an existing partition count and deletes the topic if it has a different value, and then creates it with the provided partition count.						
	<ul> <li>Kafka server with auto topic creation on connect will cause issues due to preemptive metric collector component.</li> </ul>						
	This can be fixed with Kafka-client version 2.3 onward upgrade and adding "allow.auto.create.topics=false" in KafkaConsumer properties for TopicMetricsThread:						
	<ul> <li>PreviewSubscriptionThread</li> </ul>						
	<ul> <li>TopicInputSchemaRepository</li> </ul>						
Default Value	1						

Property	CEP: Kafka					
Attribute	cep.kafka.watcher.wait					
Description	The interval (in milliseconds) at which Streams will check the status of the ZooKeeper, Kafka Broker, and Schema Registry services.					
Default Value	5000					
Property	CEP: Kafka					
Attribute	cep.kafka.zookeeper.servers					
Description	The URL to the ZooKeeper servers.					
Default Value	localhost:2181					
Property	CEP: Kafka					
Attribute	cep.type					
Description	The CEP type. For now, the available value is <b>KAFKA</b> .					
Default Value	KAFKA					
Property	Server Cluster					
Attribute	cluster.bully.bind					
Description	The URL of the server in bully mode. This should be the URL to the Panopticon server web application on the server itself, by which is reachable from the other servers.					
Default Value						
Property	Server Cluster					
Attribute	cluster.bully.boot					
Description	Comma-separated list of server URLs in bully mode.					
	At least one of these servers should be running at all time for the bully mode to work correctly. The URLs should be the same as the cluster.bully.bind value on each boot server.					
Default Value						
Property	Server Cluster					
Attribute	cluster.bully.id					
Description	The unique server ID in bully mode.					
	Can be any string, but do not change it after the server has participated in a cluster the other servers will store it and expect it to identify the same server in the future. The running server with the lowest ID lexicographically will be leader.					
Default Value						
Property	Server Cluster					
Attribute	cluster.fixed.leader					
Description	The leader URL in fixed mode.  This should be the URL to the Panopticon server web application on the preset leader server, by which it is reachable from the follower servers. Leave blank on the leader server itself.					

Default Value							
Property	Server Cluster						
Attribute	cluster.kubernetes.container_name						
Description	Optionally name of the container that runs the Panopticon server, if the pod also runs other containers. If left blank, the first container will be used.						
Default Value							
Property	Server Cluster						
Attribute	cluster.kubernetes.id						
Description	Set to the name of the pod that runs the container.						
Default Value	(blank)						
Property	Server Cluster						
Attribute	cluster.kubernetes.label_selector						
Description	Standard Kubernetes label selector that should only match the pods that are running the server.						
Default Value							
Property	Server Cluster						
Attribute	cluster.mode						
Description	NONE (default), FIXED, BULLY, or KUBERNETES  Controls how multiple servers connect to each other. This needs to be the same on all connected servers.						
Default Value	NONE						
Property	Server Cluster						
Attribute	cluster.shared.secret						
Description	Any alphanumeric string.  Secret used to encrypt a challenge in peer-to-peer communication handshake. Needs to be the same, and non-empty, on all connected servers.						
Default Value							
Property	Server Cluster						
Attribute	cluster.shared.store.shared_directory.path						
Description	Shared store location in <b>SHARED_DIRECTORY</b> mode.						
	This path must be reachable by all connected servers, and must point to the same physical directory on all of them.						
Default Value							
Property	Server Cluster						
Attribute	cluster.shared.store.type						
Description	PRIVATE_DIRECTORY (default) or SHARED_DIRECTORY  The shared store is used to store information that should be synchronized between servers but is not content, for example authentication tokens. If you have a tightly-						

	coupled cluster, e.g., behind a load balancer, it is recommended that you configure this as a shared directory.					
Default Value						
Property	AMPS Connector Custom Authenticator					
Attribute	connector.amps.authenticators					
Description	This property is required when a custom authenticator is needed for AMPS connection. A custom authenticator needs be implemented as java .JAR file. The property excepts a JSON object, where key is fully qualified name of the Authenticator Java class, and values are list of constructor parameter names, e.g., "{"com.panopticon.examples.amps.AMPSClientAuthenticator":["User", "Shared Key"]}"					
Default Value						
Property	Host Lookup					
Attribute	connector.kdb.host.lookup.script					
Description	Full path of the shell script file that is accessible on the server. When set, before making a new kdb+ connection, this script is executed to get the host info. This property helps in overriding connection details entered inside the kdb+ connector UI centrally, and may help when different authentications are set at kdb+ like Kerberos/Custom etc. The output of this script is expected to be a JSON object like below.  { "host": "localhost", "port": 5001, "username": "", "password": "" }					
Default Value						
Property	Host Lookup					
Attribute	connector.kdb.host.lookup.script.arguments					
Description	Delimited set of arguments to be passed to the script when it is executed. '{host}, {port}, {userid}, {password}' is the default value, and these parameters are mapped to respective settings in the connector UI i.e., the value entered against these settings in the connector UI are passed as arguments to the script.  This property can be extended or updated if you want to pass other datatable parameters as arguments. System parameter like {_user_id} or {_workbook_folder}, if added to the data table, can also be used. If the value of some parameter is null or empty at the time of execution of the script, two single quotes are passed (") against that parameter, this is to make sure that arguments count matches the arguments set at this property.					
Default Value	{host},{port},{userid},{password}					
Property	Host Lookup					
Attribute	connector.kdb.host.lookup.script.arguments.delimiter					
Description	Used to split the arguments set at above property.					
Default Value	,					
Property	Host Lookup					
	connector.kdb.host.lookup.script.timeout					

Description	The timeout (in milliseconds) to wait for the host lookup script to run and return the host info.					
Default Value	5000					
Property	Amazon Kinesis – Data Streams connector					
Attribute	connector.kinesis.datastreams.accesskeyid					
Description	The Access Key ID from the AWS account.					
Default Value						
Property	Amazon Kinesis – Data Streams connector					
Attribute	connector.kinesis.datastreams.secretaccesskey					
Description	The Secret Access Key ID from the AWS account.					
Default Value						
Property	Python connector					
Attribute	connector.python.host					
Description	The default Python Pyro instance host address.  NOTES:  For connector.python.host, connector.python.password, connector.python.port, and connector.python.serializertype properties:  If set in the Streams.properties file, these fields will be hidden in the Python connector and will be applied to the Python transform as well.  These default Streams Server connection properties will be applied at runtime.  These default Streams Server connection properties will override old Python connection settings.					
Default Value						
Property	Python connector					
Attribute	connector.python.password					
Description	The default HMAC Key.					
Default Value						
Property	Python connector					
Attribute	connector.python.port					
Description	The default Python Pyro host port.					
Default Value						
Property	Python connector					
Attribute	connector.python.serializertype					
Description	The default Python serialization type. Possible values are <b>serpent</b> or <b>pickle</b> .					
Default Value						

Attribute	connector.rserve.host				
Description	The default Rserve host address.  NOTES:  For connector.rserve.host, connector.rserve.password, connector.rserve.port, and connector.rserve.userid properties:  If set in the Streams.properties file, these fields will be hidden in the Rserve connector and will be applied to the R transform as well.  These default Streams Server connection properties will be applied at runtime.  These default Streams Server connection properties will override old Rserve connection settings.				
Default Value					
Property	Rserve connector				
Attribute	connector.rserve.password				
Description	The default password that will be used to connect to the Rserve service.				
Default Value					
Property	Rserve connector				
Attribute	connector.rserve.port				
Description	The default Rserve host port.				
Default Value					
Property	Rserve connector				
Attribute	connector.rserve.userid				
Description	The default user Id that will be used to connect to the Rserve service.				
Default Value					
Property	REST Documentation				
Attribute	documentation.enabled				
Description	Enable or disable the OpenAPI Specification documentation for the REST interface.				
Default Value	false				
Property	REST				
Attribute	error.default.message				
Description	The error message that will be displayed instead of the actual error message. This is used to mask or hide error messages that may contain internal or sensitive details.				
Default Value					
Property	File Upload				
Attribute	file.upload.size.max.bytes				
Description	Limit for files size to be uploaded through the web browser (i.e., workbooks, streams applications, streams data sources).				

D ( 10)(:						
Default Value	3000000					
Property	Log level					
Attribute	logger.level.file					
Description	Controls the level that is logged to file.					
Default Value	INFO					
Property	Server Metrics					
Attribute	metrics.authorization.level					
Description	Specifies the required authorization level to get server metrics. Available values are <b>ANONYMOUS</b> , <b>VIEWER</b> , <b>DESIGNER</b> , <b>ADMINISTRATOR</b> . <b>NOTE:</b> This property is case sensitive.					
Default Value	ADMINISTRATOR					
Property	Server Metrics					
Attribute	metrics.collection.rate					
Description	Specifies the rate at which metrics are collected in milliseconds.					
Default Value	1000					
Property	Server Metrics					
Attribute	metrics.file.flush.rate					
Description	Specifies how often metrics should be saved to disk in milliseconds. Only used if the metrics.publisher.type is set to FILE.					
	modifies (pasification) points (i.e.,					
Default Value	10000					
Default Value Property						
	10000					
Property	10000 Server Metrics					
Property Attribute	10000  Server Metrics  metrics.memory.queue.size  Specifies how many metric entries are stored in memory. When the number of metrics goes above the specifies value, the oldest value is removed to make room for the newest one (FIFO). Only used if the metrics.publisher.type is set to					
Property Attribute Description	10000  Server Metrics  metrics.memory.queue.size  Specifies how many metric entries are stored in memory. When the number of metrics goes above the specifies value, the oldest value is removed to make room for the newest one (FIFO). Only used if the metrics.publisher.type is set to MEMORY.					
Property Attribute Description Default Value	10000  Server Metrics  metrics.memory.queue.size  Specifies how many metric entries are stored in memory. When the number of metrics goes above the specifies value, the oldest value is removed to make room for the newest one (FIFO). Only used if the metrics.publisher.type is set to MEMORY.  100					
Property  Attribute  Description  Default Value  Property	10000  Server Metrics  metrics.memory.queue.size  Specifies how many metric entries are stored in memory. When the number of metrics goes above the specifies value, the oldest value is removed to make room for the newest one (FIFO). Only used if the metrics.publisher.type is set to MEMORY.  100  Server Metrics					
Property Attribute Description  Default Value Property Attribute	10000  Server Metrics  metrics.memory.queue.size  Specifies how many metric entries are stored in memory. When the number of metrics goes above the specifies value, the oldest value is removed to make room for the newest one (FIFO). Only used if the metrics.publisher.type is set to MEMORY.  100  Server Metrics  metrics.publisher.type  Specifies the current metric publisher that is used. Available values are NONE,					
Property Attribute Description  Default Value Property Attribute Description	10000  Server Metrics  metrics.memory.queue.size  Specifies how many metric entries are stored in memory. When the number of metrics goes above the specifies value, the oldest value is removed to make room for the newest one (FIFO). Only used if the metrics.publisher.type is set to MEMORY.  100  Server Metrics  metrics.publisher.type  Specifies the current metric publisher that is used. Available values are NONE, MEMORY, FILE, EMAIL, INFLUX_DB, JDBC, KAFKA, KDB, MQTT, REST, TEXT.					
Property Attribute Description  Default Value Property Attribute Description  Default Value	10000  Server Metrics  metrics.memory.queue.size  Specifies how many metric entries are stored in memory. When the number of metrics goes above the specifies value, the oldest value is removed to make room for the newest one (FIFO). Only used if the metrics.publisher.type is set to MEMORY.  100  Server Metrics  metrics.publisher.type  Specifies the current metric publisher that is used. Available values are NONE, MEMORY, FILE, EMAIL, INFLUX_DB, JDBC, KAFKA, KDB, MQTT, REST, TEXT.  MEMORY					
Property Attribute Description  Default Value Property Attribute Description  Default Value Property	10000  Server Metrics  metrics.memory.queue.size  Specifies how many metric entries are stored in memory. When the number of metrics goes above the specifies value, the oldest value is removed to make room for the newest one (FIFO). Only used if the metrics.publisher.type is set to MEMORY.  100  Server Metrics  metrics.publisher.type  Specifies the current metric publisher that is used. Available values are NONE, MEMORY, FILE, EMAIL, INFLUX_DB, JDBC, KAFKA, KDB, MQTT, REST, TEXT.  MEMORY  Server Metrics					
Property Attribute Description  Default Value Property Attribute Description  Default Value Property Attribute Attribute	10000  Server Metrics  metrics.memory.queue.size  Specifies how many metric entries are stored in memory. When the number of metrics goes above the specifies value, the oldest value is removed to make room for the newest one (FIFO). Only used if the metrics.publisher.type is set to MEMORY.  100  Server Metrics  metrics.publisher.type  Specifies the current metric publisher that is used. Available values are NONE, MEMORY, FILE, EMAIL, INFLUX_DB, JDBC, KAFKA, KDB, MQTT, REST, TEXT.  MEMORY  Server Metrics  metrics.publisher.configuration					
Property Attribute Description  Default Value Property Attribute Description  Default Value Property Attribute Description  Default Value Property Attribute Description	10000  Server Metrics  metrics.memory.queue.size  Specifies how many metric entries are stored in memory. When the number of metrics goes above the specifies value, the oldest value is removed to make room for the newest one (FIFO). Only used if the metrics.publisher.type is set to MEMORY.  100  Server Metrics  metrics.publisher.type  Specifies the current metric publisher that is used. Available values are NONE, MEMORY, FILE, EMAIL, INFLUX_DB, JDBC, KAFKA, KDB, MQTT, REST, TEXT.  MEMORY  Server Metrics  metrics.publisher.configuration					

Attribute	repository.import.archived.applications						
Description	Allows to import all application backups from the <appdata>/CEP/Archive/.</appdata>						
	Refer to step 4 in the <u>Migration to Streams Server 2024.0 from an Older Version</u> section for more information.						
Default Value	true						
Property	Repository						
Attribute	repository.startup.filesystemcheck						
Description	If set to <b>true</b> , server runs on startup to verify the repository integrity and reports any of the following issues:  • a deleted /HEAD file,						
	• a modified /HEAD,						
	• a modified /refs/heads/master file,						
	<ul> <li>any file deleted inside /objects/ (e.g., /objects/94/443eec118fb8bb2021071896ff7d386a9c9518),</li> </ul>						
	• any file modified inside /objects/.						
	<b>NOTE:</b> There may be dangling files in the <code>/objects/</code> directory or those that are not in use. These files are typically results of failed saves and/or sync conflicts. The check may or may not detect deleted or modified dangling files, but that is not critical.						
Default Value	false						
Property	REST						
Attribute	rest.response.error.stacktrace.included						
Description	Include the error stackrace in REST responses.						
Default Value	false						
Property	Server Downgrade						
Attribute	server.force_downgrade						
Description	The server normally refuses to start if it detects that the AppData directory has been used by a server with a newer version. This is because downgrading content and other AppData files is not supported and can cause irreversable issues. You can set this property to true to force the server to start anyway, but it is strongly recommended that you do not.						
Default Value	false						
Property	Server						
Attribute	server.id						
Description	Specifies an id for the current server. The value of this property will be part of each metric entry so that it can be tied to a specific server if a server cluster is used. If no value is specified, the MAC address of the localhost network will be attempted to be used to identify the server. If this is not possible, a UUID will be generated.						
Default Value							
Property	Licensing						
Attribute	license.hwu.hosted						

Description	Boolean stating if you wish to use Managed or Local Altair Units licensing. Set to <b>true</b> if you wish to use managed licensing.						
Default Value	false						
Property	Licensing						
Attribute	license.hwu.hosted.authorization.username						
Description	Username to the Altair One account.						
Default Value							
Property	Licensing						
Attribute	license.hwu.hosted.authorization.password						
Description	Password to the Altair One account.						
Default Value							
Property	Licensing						
Attribute	license.hwu.hosted.authorization.token						
Description	An authorization token generated through the Altair One admin portal. Used to authorize a machine to the managed Altair Units system.						
Default Value							
Property	Licensing						
Attribute	license.hwu.uri						
Description	The path where the License Server is running e.g., 6200@191.255.255.0 where the syntax is PORTNUMBER@HOST. If multiple servers are specified, use the ';' semicolon separator sign for Windows and the ':' colon separator sign for Linux.  NOTE:						
	If value is not set in the Streams.properties, the environment variable ALTAIR_LICENSE_PATH serves as the backup path and will be used.						
Example	For Windows: license.hwu.uri=6200@192.168.5.51;6200@192.168.5.52 For Linux: license.hwu.uri=6200@192.168.5.51:6200@192.168.5.52						
Default Value							
Property	Licensing						
Attribute	license.hwu.use_client_timezone						
Description	Determines how the ALJDK should process the timezone details. If set to <b>true</b> , the ALJDK will process the timezone details sent by Panopticon client to the Panopticon server. If set to <b>false</b> , the Panopticon server timezone is used.						
Default Value	true						
Property	Licensing						
Attribute	license.mode						

Description	The license mode. Possible values are <b>FILE</b> or <b>HWU</b> . To use the Altair Units license, set this property to <b>HWU</b> .					
Default Value	FILE					
Property	Timeout Session					
Attribute	timeout.session.enabled					
Description	Boolean value stating if timeout functionality should be used or not.					
Default Value	false					
Property	Timeout Session					
Attribute	timeout.session.exception.delimiter					
Description	The delimiter to use for the usernames stated in the timeout.session.exception.usernames property.					
Default Value	, (comma)					
Property	Timeout Session					
Attribute	timeout.session.exception.usernames					
Description	Usernames that should be excluded from the timeout functionality. Separated by the delimiter stated in the timeout.session.exception.delimiter property.					
Default Value						
Property	Timeout Session					
Attribute	timeout.session.minutes					
Description	Minutes of inactivity before a user session is terminated by logging out the user.					
Default Value	480					

12.2024

ΔR			

For more information on Panopticon and other resources, go to <a href="https://www.altair.com/panopticon">https://www.altair.com/panopticon</a>.